z/OS

DFSMSrmm Implementation and Customization Guide

Release 1

SC26-7405-00

z/OS

DFSMSrmm Implementation and Customization Guide

Release 1

SC26-7405-00

Note

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 413.

First Edition, March 2001

This edition applies to Version 1 Release 1 of z/OS™ (5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

IBM welcomes your comments. A form for readers’ comments may be provided at the back of this publication, or you may address your comments to the following address:

International Business Machines Corporation
RCF Processing, Department M86/050
5600 Cottle Road
San Jose, CA 95193-0001
United States of America

IBMLINK from US: STARPUBS at SJEVM5
IBMLINK from Canada: STARPUBS at TORIBM
IBM Mail Exchange: USIB3VVD at IBMMAIL
Internet: starpubs@us.ibm.com
World Wide Web: http://www.storage.ibm.com/software/sms/smshome.htm

If you would like a reply, be sure to include your name, address, telephone number, or FAX number.

Make sure to include the following in your comment or note:

- Title and order number of this book
- Page number or topic related to your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1992, 2001. All rights reserved.
US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures xiii

Tables xvii

About This Book xix
Required Product Knowledge xix
Referenced Publications xix
How To Use This Book xx
How to Find Samples in this Book xxi
Notational Conventions xxi
How to Read Syntax Diagrams xxi
How to Abbreviate Commands and Operands xxiv
How to Use Continuation Characters xxiv
Delimiters xxiv
Character Sets xxv
Accessing z/OS DFSMS® Books on the Internet xxvi
Accessing Messages Using LookAt xxvi
How to Send Your Comments xxvi

Chapter 1. Introducing DFSMSrmm 1
What Libraries and Locations Can DFSMSrmm Manage? 1
What Is in a Removable Media Library? 1
What Is in a System-Managed Tape Library? 2
What Is in a Non-System-Managed Tape Library? 3
What Is in a Storage Location? 3
How Does DFSMSrmm Manage These Libraries and Locations? 4
Setting Up Your Installation Options 4
Defining Retention and Movement Policies 5
Running DFSMSrmm Utilities 7
What Resources Does DFSMSrmm Manage? 8
Shelf Locations 8
Volumes 10
Data Sets 13
Year 2000 Support 14
Software Products 14
Owner Information 14
How Does DFSMSrmm Help You Create Reports? 14
Using DFSMSrmm ISPF Dialog and RMM TSO Subcommands 14
Using the EDGAUD and EDGRPTD Report Utilities 15
Using the DFSMSrmm EDGRRPTE Exec 15
Using the DFSORT ICETOOL Utility 15
Using the DFSMSrmm Application Programming Interface 16
How Does DFSMSrmm Authorization and Security Work? 16
What Tape Usage Does DFSMSrmm Support? 16
How Does DFSMSrmm Validate Tape Mounts? 17
Why Does DFSMSrmm Reject Tape Volumes? 18
Rejects Caused by Installation Controls 18
Rejects Caused by Validation Failure 18
Rejects Caused by DFSMSrmm Rules 19
Who Can Use DFSMSrmm and How? 20
General User 20
Tape Librarian 20
Storage Administrator 20

© Copyright IBM Corp. 1992, 2001

System Programmer 20
Operator 21
Using DFSMSrmm 21

Chapter 2. Implementing DFSMSrmm 23
Step 1: Preparing to Implement DFSMSrmm 23
Step 2: Running the IVP (Optional) 23
Step 3: Updating JES3 (Optional) 23
Step 4: Updating Installation Exits 24
Step 5: Updating SYS1.PARMLIB Members 25
Updating IEFSSNxx 25
Updating IKJTSOxx to Authorize DFSMSrmm Commands 26
Updating SMFPRMxx (Optional) 27
Updating GRSRNLxx (Optional). 27
Updating SCHEDxx (Optional) 29
Ensuring DFSMSrmm is Enabled 29
Step 6: Using the Problem Determination Aid Facility (Optional) 30
Step 7: Setting Up DFSMSrmm Disposition Processing (Optional) 30
Step 8: Updating the Procedure Library 30
Step 9: Assigning DFSMSrmm a RACF User ID. 33
Step 10: Defining Parmlib Member EDGRMMxx. 34
Step 11: Tailoring Parmlib Member EDGRMMxx. 35
Step 12: Creating the DFSMSrmm Control Data Set 35
Calculating DASD Space for the DFSMSrmm Control Data Set 36
Placing the DFSMSrmm Control Data Set 36
Allocating Space for the Control Data Set 37
Protecting the Control Data Set 38
Initializing the Control Data Set 38
Backing Up the Control Data Set 39
Step 13: Creating the Journal 39
Calculating DASD Space for the Journal 40
Placing the Journal 40
Allocating Space for the Journal 41
Protecting the Journal 41
Backing Up the Journal 42
Step 14: Authorizing Users 42
Step 15: Making the DFSMSrmm ISPF Dialog Available to Users 42
Adding DFSMSrmm to an ISPF Selection Panel. 42
Modifying an ISPF Selection Panel 43
Step 16: Making TSO HELP Information Available to Users 44
Step 17: Restarting MVS with DFSMSrmm Implemented 44
Step 18: Tailoring DFSMSrmm Set Up 45
Step 19: Starting DFSMSrmm 45
Stopping DFSMSrmm 46
Quiescing DFSMSrmm 47
Restarting DFSMSrmm 48
Checking DFSMSrmm Status 48
Step 20: Defining Resources 48
Defining Shelf Locations 48
Defining Owner Information to DFSMSrmm 49
Defining Volumes 49
Defining Vital Record Specifications 51
Step 21: Updating the Operational Procedures 52
Step 22: Initializing the DFSMSrmm Subsystem and Tape Recording 52
Enabling the DFSMSrmm Subsystem Interface 52
Changing the DFSMSrmm Running Mode 52

Activating the DFSMShsm Interface . . . 53
Restarting the DFSMSrmm Subsystem . . . 53
Step 23: Setting Up DFSMSrmm Utilities . . . 53

Chapter 3. Organizing the Removable Media Library . . . 55
Organizing the Library by Pools . . . 55
Pooling Overview . . . 55
Pooling Considerations . . . 56
Defining Pools in Parmlib Member EDGRMMxx . . . 58
Calculating Pool Size . . . 59
Changing Pool Definitions . . . 60
Designing Pools . . . 60
Planning to Use Scratch Pools . . . 62
Using Storage Groups for DFSMSrmm Scratch Pooling . . . 63
Making an ACS Storage Group Assignment . . . 63
A Pooling Example . . . 66
Managing Pools with Job Name and Data Set Name . . . 67
Assigning Policies . . . 67
Using SMS Management Class to Retain Non-System-Managed Volumes 68
Managing Volumes with Special Dates . . . 70
Using Volumes with Special Expiration Dates . . . 71
Using Management Class to Retain System-Managed Volumes . . . 71
Using the SMS Pre-ACS Interface . . . 73
Managing Duplicate or Undefined Volume Serial Numbers . . . 73
Using Volumes with Duplicate Volume Serial Numbers . . . 74
Changing Duplicate Volume Serial Numbers . . . 74
Ignoring Duplicate or Undefined Volume Serial Numbers . . . 75

Chapter 4. Running DFSMSrmm with System-Managed Tape Libraries . . . 77
Using DFSMSrmm with System-Managed Tape Libraries . . . 77
Associating Volumes and System-Managed Libraries . . . 78
Cartridge Entry Processing . . . 78
Manual Cartridge Entry Processing . . . 79
Scratch Pool Management . . . 79
Ejecting Volumes from System-Managed Libraries . . . 79
Returning Volumes to the System-Managed Library . . . 80
Volume-Not-In-Library Processing . . . 81
Confirming Volume Movement For System Managed Libraries . . . 82
Defining System-Managed Volume Information . . . 82
Initializing Scratch Volumes in System-Managed Libraries . . . 84
DFSMSrmm Support for Storage Group Name . . . 84
Using DFSMSrmm with the IBM Virtual Tape Server . . . 85
Defining Logical Volumes in a Virtual Tape Server Library . . . 85
Logical Volume Cartridge Entry Processing . . . 86
DFSMSrmm Support for Logical Volumes . . . 87
DFSMSrmm Support for Stacked Volumes . . . 87
Managing Stacked Volumes . . . 88
Deleting Stacked Volume Information . . . 89
DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled . . . 89
DFSMSrmm Support for Stacked Volumes When Stacked Volume Support Is Not Enabled . . . 93
Enabling Stacked Volume Support . . . 95
Performing a Virtual Export of Logical Volumes . . . 96
Recovering a Logical Volume from an Exported Stacked Volume . . . 97
Setting Up DFSMSrmm for the System-Managed Tape Library . . . 98

Using the System-Managed Tape Library With New Volumes 98
Using the System-Managed Tape Library with Volumes Already Defined in DFSMSrmm 98
Using the System-Managed Tape Library with Existing Volumes 99
Using DFSMSrmm with an Existing Tape Library Dataserver 99
Returning Volumes to Scratch Status 100
Partitioning System-managed Tape Libraries 101
Sharing a System-Managed Library and a BTLS-Managed Library 101
Moving from a Non-system-managed to a System-Managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver 102

Chapter 5. Running DFSMSrmm with BTLS 103
Setting Up Scratch Pools for BTLS-Managed Volumes 103
Running DFSMSrmm Inventory Management with BTLS 104
Running EDGINERS for BTLS-managed Volumes 105
Restrictions 105
Defining Volume Information for BTLS-managed Volumes 105
Returning BTLS-managed Volumes to Scratch 106

Chapter 6. Managing Storage Locations 107
Types of for Storage Locations 107
Defining Storage Locations 108
Processing for Storage Locations 108
Implementing Installation Defined Storage Locations 108
Changing Storage Locations 110
Deleting Storage Locations 110
Moving Volumes to Storage Locations Using Media Shape 110
Converting from Built-In Storage Locations 112
Switching Volumes to Installation Defined Storage Locations 112
Going Back to Built-In Storage Locations 113
Using Manual Move Control 113

Chapter 7. Using the Parmlib Member EDGRMMxx 115
Defining Storage Locations: LOCDEF 115
LOCDEF Command Syntax 115
LOCDEF Command Operands 116
Defining Mount and Fetch Messages: MNTMSG 119
MNTMSG Command Syntax 120
MNTMSG Command Operands 121
Defining System Options: OPTION 122
OPTION Command Syntax 123
OPTION Command Operands 126
Defining Tapes Not Available on Systems: REJECT 144
REJECT Command Syntax 144
REJECT Command Operands 145
Defining Security Classes: SECCLS 145
SECCLS Command Syntax 146
SECCLS Command Operands 147
Defining Pools: VLPOOL 148
VLPOOL Command Syntax 149
VLPOOL Command Operands 149

Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security 153
Protecting DFSMSrmm Resources with RACF Profiles 153
Creating Profiles 154
Setting the Level of Access for the DFSMSrmm Resources 155

Authorizing Resources 157
General User Functions 158
Storage Administrator Functions 159
System Programmer Functions 160
Librarian Functions 160
Inventory Management Functions 161
Operator Functions 161
Using the Tape Relabeling Resources 162
Creating Audit Trails 162
Control Data Set Information 162
SMF Audit Information 163
RACF Audit Information 163
Using Security Classification Processing 163
Preventing the Use of IEHINITT 163
Controlling RACF Tape Profile Processing 164
Recommendations for Using RACF Tape Profile Processing 167
Rejecting Volumes on Specific Systems in a System Complex 167
Maintaining the User Access List 168
RACF Considerations When Implementing DFSMSrmm 168
DFSMSrmm RACF Tape Security Support 169
DFSMSrmm Automatic Tape Security Support Processing 169
Data Set Profile Processing Implications 169
Converting From RACF Installation Exits 169
Using the SAF Interface 170
SAF Calls for Authorization Checking 171
SAF and RACF Calls For Creating, Updating and Deleting Security Profiles 173

Chapter 9. Using DFSMSrmm Programming Interfaces 177
Releasing Tapes: EDGTVEXT 177
Invocation 178
Input 178
Output 178
Processing 178
Environment 178
Managing DFSMShsm Tapes: EDGDFHSM 178
Invocation 179
Input 179
Output 179
Processing 179
Environment 179
Managing System-Managed Tape Library Volumes: EDGLCSUX 179
Input 180
Output 181
Processing 183
Environment 192
Processing Fetch and Mount Messages: EDGMSGEX 192
Input 192
Output 192
Processing 192
Environment 192
Processing JES3 Messages: EDG3X71 192
Input 192
Output 193
Processing 193
Environment 193

Chapter 10. Using DFSMSrmm Installation Exits 195
Using the DFSMSrmm EDGUX100 Installation Exit 195
Planning to Manage Scratch Pools with EDGUX100. 195
Using EDGUX100 to Ignore Duplicate or Undefined Volume Serial Numbers 197
Using Vital Record Specification Management Values to Retain Tape Volumes 199
Managing Scratch Pools 201
Using the EDGUX100 Installation Exit from Pre-ACS Processing 204
Creating Sticky Labels. 204
Modifying DFSMSrmm Label Output 205
Controlling Tape Volume Data Set Recording 206
Changing Location Information with EDGUX100 207
EDGUX100 Exit Routine Processing 208
Environment 214
Installing the EDGUX100 Routine 214
Writing the EDGUX100 Routine 216
EDGUX100 Installation Exit Return Codes 220
Using the DFSMSrmm EDGUX200 Installation Exit 220
EDGUX200 Exit Routine Processing 221
Environment 221
Installing the EDGUX200 Exit Routine 221
Writing the EDGUX200 Exit Routine 223
EDGUX200 Installation Exit Return Codes 224

Chapter 11. Running DFSMSrmm with DFSMShsm 225
Authorizing DFSMShsm to DFSMSrmm Resources 225
Authorizing ABARS to DFSMSrmm Resources. 226
Setting DFSMSrmm Options When Using DFSMShsm 226
Setting DFSMShsm Options When Using DFSMSrmm 227
Setting DFSMShsm System Options 227
Setting DFSMShsm Dump Definitions 227
DFSMSrmm Support for DFSMShsm Naming Conventions 228
DFSMSrmm Support for Retention and Pooling 228
Retaining DFSMShsm Tapes Using Expiration Dates 228
Defining Vital Record Specifications to Manage DFSMShsm Tapes 229
Retaining All DFSMShsm Tapes 230
Retaining Open Data Sets 230
Retaining Single File Format Migration Tapes 231
Retaining Multifile Format Migration Tapes 231
Retaining Single File Format Backup Tapes 232
Retaining Multifile Format Backup Tapes 232
Retaining and Moving TAPECOPY Tapes or DUPLEX Tapes 232
Retaining and Moving Dump Tapes 233
Retaining and Moving Tapes Written by ABARS 236
Retaining and Moving ABARS Accompany Tapes 237
Retaining DFSMShsm Control Data Set Backup Tapes. 237
Using Old Data Set Naming Conventions to Retain and Move DFSMShsm Tapes 238
Retaining Cycles of Dump Tapes 238
Retaining DFSMShsm Tapes Extra Days Retention 240
Disaster Recovery Using DFSMShsm Alternate Tapes With DFSMSrmm . . . 240
Securing Tapes When Running DFSMShsm and DFSMSrmm 241
Recommendations 241

Chapter 12. Running DFSMSrmm with JES3 243
Preventing JES3 from Validating Volumes 243

Updating JES3 Fetch and Mount Messages 243
Using the EDG3UX71 USERMOD 244
Using the EDG3IIP1 USERMOD 244
Using the EDG3LVVR USERMOD 244
Enabling the Use of No Label Tapes 245

Chapter 13. Performing Inventory Management 247
Scheduling DFSMSrmm Utilities 247
Running Inventory Management 248
Inventory Management Considerations. 249
Allocating Data Sets for Inventory Management 251
Assessing DASD Space and Placement for the Extract Data Set 252
JCL for EDGHSKP 253
EXEC Parameters for EDGHSKP 253
How Inventory Management Works 257
Running DFSMSrmm Catalog Synchronization. 257
DFSMSrmm Catalog Processing 258
JCL for Catalog Synchronization 259
Synchronizing the DFSMSrmm Control Data Set with User Catalogs in a Fully Shared Catalog Environment 259
Synchronizing the DFSMSrmm Control Data Set with User Catalogs when Catalogs Are Not Fully Shared 260
Running Vital Record Processing. 260
JCL for Vital Record Processing 261
Using the Vital Records Retention Report 262
Using the Inventory Management ACTIVITY File 266
How Vital Record Processing Works 267
Running Storage Location Management Processing 271
JCL for Storage Location Management Processing 272
How Storage Location Management Processing Works 272
Running Expiration Processing 274
JCL for Expiration Processing 274
How Expiration Processing Works 274
Confirming Global Volume Movement 276
Confirming Global Release Actions 277
Backing Up the Control Data Set 278
JCL for Backing Up the Control Data Set 278
Customizing the DSSOPT DD Statement 279
How Backup Processing Works 280
Creating an Extract Data Set 280
JCL for Creating an Extract Data Set 280
How Report Extract Processing Works. 281
Return Codes for EDGHSKP 281

Chapter 14. Creating Reports with DFSMSrmm 283

Chapter 15. Creating Reports and Commands with DFSORT's ICETOOL 285

Chapter 16. Maintaining the Control Data Set 287
Backing Up and Restoring the Control Data Set: EDGBKUP. 287
JCL for EDGBKUP 288
EXEC Parameters for EDGBKUP 288
Backing Up the DFSMSrmm Control Data Set and Journal 289
Automating Control Data Set Backup and Journal Clearing 290
Restoring the Control Data Set With Forward Recovery 290
Restoring the Control Data Set Without Forward Recovery 292

Forward Recovering the Control Data Set . . . 292
Reorganizing the Control Data Set . . . 293
Return Codes for EDGBKUP . . . 293
Recovering from Control Data Set Update Failures . . . 294
Recovery Processing . . . 294
Handling of DFSMSrmm Subsystem Requests . . . 295
Moving the Control Data Set and Journal to a Different Device . . . 295
Moving the Control Data Set and Journal Using DFSMSrmm Utilities . . . 295
Moving the Control Data Set Using Non-DFSMSrmm Utilities . . . 298
Creating and Verifying the Contents of the Control Data Set: EDGUTIL . . . 299
JCL for EDGUTIL . . . 299
EXEC Parameters for EDGUTIL . . . 300
Creating or Updating the Control Data Set Control Record . . . 303
Verifying the Contents of the Control Data Set . . . 305
Verifying the Control Data Set and Tape Configuration Database . . . 306
Mending the Control Data Set . . . 306
Synchronizing the Contents of the Control Data Set . . . 307
Setting up DFSMSrmm Stacked Volume Support . . . 307
How EDGUTIL Processing Works . . . 307
Return Codes for EDGUTIL . . . 308
Sharing the DFSMSrmm Control Data Set . . . 309
Running DFSMSrmm Inventory Management When Sharing the Control Data Set . . . 309
Running EDGINERS When Sharing the Control Data Set . . . 309
Defining Volume Information When Sharing the Control Data Set . . . 309
Confirming Volume Movement When Sharing the Control Data Set . . . 310
Returning Volumes to Scratch When Sharing the Control Data Set . . . 310

Chapter 17. Initializing and Erasing Volumes . . . 311
Replacing IEHINITT with EDGINERS . . . 312
Using EDGINERS . . . 312
JCL for EDGINERS . . . 313
Using EDGINERS with System-Managed Tape Libraries . . . 321
Controlling Access to EDGINERS . . . 324
How EDGINERS Processing Works . . . 324
Return Codes for EDGINERS . . . 325
EDGINERS Examples . . . 325
Example 1: Write IBM Standard Labels on Three Tapes . . . 326
Example 2: Write an ISO/ANSI Label on a Tape . . . 326
Example 3: Place Two Groups of Serial Numbers on Six Tape Volumes 326
Example 4: Place Serial Numbers on Eight Tape Volumes . . . 327
Example 5: Relabel a Volume . . . 327
Example 6: Automatically Initialize or Erase 3480 Volumes . . . 328
Example 7: Initialize and Erase Volumes in a System-Managed Library 328
Example 8: Initialize 50 Scratch Enhanced Capacity Cartridges . . . 328
Example 9: Erase a Volume . . . 329

Chapter 18. Customizing DFSMSrmm . . . 331
Changing the Initial Entry Point to the DFSMSrmm Dialog . . . 331
Adding Local Dialog Extensions . . . 332
Changing the ADD Product Volume Defaults . . . 333
Customizing DFSMSrmm Messages . . . 333
Customizing DFSMSrmm Report Titles . . . 333
Customizing Notification Messages and Notes . . . 334
Managing VM Tape Volumes . . . 339
Replenishing Scratch Volumes in a System-Managed Library . . . 340

Automating Backup 341
Using the LABEL Procedure 341
Processing NL Label Tapes: EDG019VM 342
Input 342
Output 342
Processing 342
Environment 342

Chapter 19. Using the Problem Determination Aid Facility 343
Planning to Use the PDA Facility 343
Determining How Long to Keep Trace Information 344
Short-Term Trace History 344
Long-Term Trace History 344
Problem Determination Aid (PDA) Log Data Set Size Requirements 344
Controlling the Problem Determination Aid (PDA) Facility 344
Allocating the Problem Determination Aid (PDA) Log Data Sets 345
Archiving the Problem Determination Aid (PDA) Log Data Sets 345
Copying the Problem Determination Aid (PDA) Log Data Sets to Tape 346
Printing the Problem Determination Aid (PDA) Log Data Sets 346

Chapter 20. Setting Up DFSMSrmm Disposition Processing 347
Implementing DFSMSrmm Disposition Control File Processing 347
Modifying the Contents of the Disposition Control File 348
Label Processing 350
Labels 351

Chapter 21. Running DFSMSrmm with Tivoli OPC 353
Considerations When Running DFSMSrmm with Tivoli OPC 353
Setting Up DFSMSrmm to Use Tivoli OPC 354
Descriptions of DFSMSrmm Jobs to Run with Tivoli OPC 354
Tivoli OPC Applications for DFSMSrmm 356
Customizing Tivoli OPC Batch Loader Statements 358
Setting Up Tivoli OPC Workstations 358
Event Triggered Tracking 358

Appendix A. DFSMSrmm Installation Verification Procedures 359
Preparing to Run the IVP 359
Running the IVP 361

Appendix B. DFSMSrmm Mapping Macros 365
General-use Programming Interface Mapping Macros 365
OAM Interface: EDGLCSUP 365
EDGLCSUP Cross Reference 369
Product-sensitive Programming Interface Mapping Macros 371
Installation Exit Mapping Macro: EDGPL100 372
EDGPL100 Cross Reference 375
Installation Exit Mapping Macro: EDGPL200 377
EDGPL200 Cross Reference 378
Sticky Label Data: EDGSLAB 379
EDGSLAB Cross Reference 381

Appendix C. Using DFSMSrmm Samples 385

Appendix D. DFSMSrmm System and User Completion Codes 389
System Completion Codes 389
User Completion Codes 390

Appendix E. Evaluating Removable Media Management Needs 407

Appendix F. Problem Determination Aid Log Data Set Size Work Sheet for Long-Term Trace History 409

Appendix G. Problem Determination Aid Log Data Set Size Work Sheet for Short-Term Trace History 411

Notices 413
Programming Interface Information 414
Trademarks. 414

Glossary 415

Index 427

Figures

1. Example of the DFSMSrmm DELETEVOLUME Syntax Diagram . . . xxiv
2. Defining a Vital Record Specification Chain . . . 7
3. Example of a List of Volumes Owned by a Single User . . . 15
4. DFSMSrmm Librarian Menu . . . 22
5. Defining DFSMSrmm to MVS through IEFSSNxx With Subsystem Inactive . . . 25
6. Updating IKJTSOxx to Authorize RMM Commands . . . 26
7. Updating IKJTSOxx to Call DFSMSrmm through TSO . . . 27
8. Converting the SYSTEMS Enqueue to a Local SYSTEM Enqueue . . . 28
9. Converting the RESERVE to a SYSTEMS Enqueue . . . 28
10. Updating SCHEDxx . . . 29
11. Creating a Procedure in SYS1.PROCLIB . . . 30
12. Allocating DASD Space for the Control Data Set . . . 37
13. Allocating DASD Space for the Control Data Set when DASD Cache Is in Use . . . 38
14. Initializing the Control Data Set . . . 39
15. Allocating Space for the Journal . . . 41
16. Adding DFSMSrmm to ISPF . . . 43
17. Updating the TSO Logon Procedure . . . 44
18. Starting DFSMSrmm . . . 45
19. Starting DFSMSrmm with Additional Parameters . . . 46
20. Stopping DFSMSrmm . . . 46
21. Disabling the DFSMSrmm Subsystem Interface . . . 47
22. Quiescing the DFSMSrmm Subsystem Interface . . . 48
23. Defining Minimum Volume Information . . . 50
24. Defining Volumes in a System-managed Library . . . 50
25. Defining Volumes in a Manual Tape Library . . . 50
26. Changing SYS1.PARMLIB IEFSSNxx . . . 52
27. Restarting the DFSMSrmm Subsystem . . . 53
28. Message EDG0103D . . . 53
29. Default VLPOOL Command . . . 58
30. Defining Pools with the DFSMSrmm EDGRMMxx Parmlib VLPOOL Command . . . 64
31. Sample Management Class Routine . . . 65
32. Storage Group Routine Sample . . . 65
33. Defining Pools with VLPOOL Commands . . . 66
34. Defining Vital Record Specifications for Non-System-Managed Volumes . . . 69
35. Sample Management Class Routine for Managing Non-System-Managed Volumes . . . 70
36. Assigning Management Class to Data Sets on Tape . . . 72
37. Special Date 99000 Vital Record Specification . . . 72
38. Managing Management Classes Using a Data Set Name Mask . . . 73
39. Specifying a Library Name for a Volume . . . 78
40. Requesting the Eject of a Volume . . . 80
41. Changing Volume Type . . . 86
42. Setting the Required Location for Logical Volumes . . . 90
43. Confirming Volume Moves for Exported Volumes . . . 91
44. Building a List of Stacked Volumes to be Imported from a Single Stacked Volume . . . 92
45. Building a List of Logical Volumes to be Imported from a Single Stacked Volume . . . 92
46. Building a List of Logical Volumes to be Imported from Multiple Stacked Volumes . . . 92
47. Creating a Volume Export List . . . 93
48. Confirming Volume Moves for Exported Volumes . . . 94
49. Creating a Volume Import List . . . 95
50. Converting A Logical Volume to a Physical Volume . . . 97
51. Reusing Volume Information for a Recovered Volume . . . 97
52. Sample JCL to Return Volumes to Scratch . . . 106
53. Using Media Name to Control Volume Movement . . . 112

© Copyright IBM Corp. 1992, 2001

54. Identifying an Installation Defined Storage Location . . . 113
55. Keeping Volumes On-site . . . 114
56. Sending a Volume to Another System . . . 114
57. Returning a Volume from Another System . . . 114
58. Parmlib Member EDGRMMxx LOCDEF Command Example . . . 115
59. Parmlib Member EDGRMMxx LOCDEF Command for Defining Storage Locations . . . 116
60. Parmlib Member EDGRMMxx LOCDEF Command for Defining Shelf and System-Managed Libraries . . . 116
61. Using a Medianame Not Defined in the LOCDEF Command . . . 117
62. Parmlib Member EDGRMMxx MNTMSG Command Examples for 4-digit Devices . . . 120
63. Parmlib Member EDGRMMxx MNTMSG Command Syntax . . . 120
64. Parmlib Member EDGRMMxx OPTION Command Examples . . . 123
65. Parmlib Member EDGRMMxx OPTION Command Syntax . . . 123
66. Parmlib Member EDGRMMxx REJECT Command Examples . . . 144
67. Parmlib Member EDGRMMxx REJECT Command Syntax . . . 144
68. Parmlib Member EDGRMMxx SECCLS Command Examples . . . 146
69. Parmlib Member EDGRMMxx SECCLS Command Syntax . . . 146
70. Parmlib Member EDGRMMxx VLPOOL Command Examples . . . 148
71. Parmlib Member EDGRMMxx VLPOOL Command Syntax . . . 149
72. Creating a RACF Profile. . . . 155
73. Creating a RACF Profile with Audit Options . . . 155
74. Limiting the Use of IEHINITT . . . 164
75. Creating a Tape Profile . . . 167
76. Using the REJECT Parmlib Option . . . 168
77. Creating an ACEE for a User Defined to RACF . . . 171
78. Creating an ACEE for a User Not Defined to RACF . . . 171
79. Checking Authorization When a Single RACROUTE Is Issued . . . 171
80. Checking Authorization When Multiple RACROUTEs are Issued . . . 172
81. Checking Authorization to Ignore Volumes . . . 172
82. Checking Authorization to Create Labels and No Label Volumes . . . 172
83. Checking for EDGRESET Usage . . . 173
84. Checking for DATASET Class Resource . . . 173
85. Checking for TAPEVOL Class Resource . . . 174
86. Defining a TAPEVOL Class . . . 174
87. Defining TAPEVOL When TAPEDSN is Active . . . 174
88. Adding a Tape Volume . . . 175
89. Deleting a TAPEVOL Profile . . . 175
90. Deleting a DATASET Profile . . . 175
91. Checking Authorization . . . 176
92. Managing Special Date 99000 with Vital Record Management Value . . . 200
93. Specifying Data Set Masks for Vital Record Management Values . . . 200
94. Defining Pools for a Specific Application . . . 202
95. Sample EDGUX100 Installation Exit Sticky Label Support . . . 205
96. Sample Table for Controlling Data Set Recording . . . 207
97. Checking Authorization to Ignore a Volume . . . 209
98. Sample EDGUX100 Pool Selection Table . . . 212
99. Sample EDGUX100 Installation Exit System Name Table . . . 213
100. Pool Selection Table for System 3 . . . 214
101. Building an SMP/E USERMOD to Apply the Updated EDGUX100 Exit . . . 215
102. Building an SMP/E USERMOD to Apply the Updated EDGUX200 Exit . . . 222
103. DFSMShsm System Options . . . 227
104. DFSMShsm Dump Definitions . . . 228
105. Specifying the DFSMShsm Startup Option . . . 228
106. Retaining DFSMShsm Tapes Requiring No Movement . . . 230
107. Retaining DFSMShsm Tapes with the DFSMShsm and ABARS Procedure Name . . . 230
108. Keeping All Single File Format Migration Tapes . . . 231

109. Keeping Multifile Format Migration Tapes . . . 231
110. Keeping Single File Format Backup Tapes . . . 232
111. Keeping Multifile Format Backup Tapes . . . 232
112. Keeping Tapes Created by the DFSMShsm TAPECOPY Command and DUPLEX Tape Feature 233
113. Keeping Tapes Used for Dump . . . 234
114. Managing Cycles of Dumps . . . 234
115. Retaining and Moving Volumes by Cycles . . . 235
116. Keeping ABARS Tapes . . . 236
117. Keeping ABARS Accompany Tapes . . . 237
118. Keeping DFSMShsm Control Data Set and Journal Backup Tapes . . . 237
119. Managing Cycles of Dumps . . . 238
120. Moving Dumps to Storage Locations . . . 239
121. Keeping ABARS Backup Tapes Using GDG Names . . . 239
122. Adding New Shelf Locations . . . 250
123. DFSMSrmm Messages Issued during Processing . . . 250
124. Resume Adding New Shelf Locations . . . 250
125. Defining a Vital Record Specification . . . 250
126. JCL for Adding a DD Statement to the EDGHSKP Job Step . . . 251
127. JCL for Specifying the Extract Data Set . . . 253
128. Example of JCL for EDGHSKP . . . 253
129. EDGHSKP EXEC Parameters . . . 254
130. Example of JCL for Catalog Synchronization Processing . . . 259
131. Example of JCL for Trial Run Catalog Synchronization Processing . . . 259
132. Example of JCL for Vital Record Specification Processing . . . 261
133. Example of JCL for Trial Run Vital Record Specification Processing . . . 261
134. Sample Vital Records Retention Report . . . 262
135. Example of JCL for Storage Location Management Processing . . . 272
136. Automatically Ejecting Volumes from System-managed Libraries . . . 273
137. Example of JCL for Expiration Processing . . . 274
138. Expiration Processing Report . . . 276
139. Example of JCL for Backing Up the Control Data Set . . . 278
140. DFSMSdss Commands Issued by DFSMSrmm . . . 279
141. Changing DFSMSdss Commands for Backing up to Tape . . . 279
142. JCL for Creating an Extract Data Set . . . 280
143. JCL Example for EDGBKUP . . . 288
144. EDGBKUP EXEC Parameters . . . 288
145. Restoring the Control Data Set . . . 290
146. Concatenating Journal Data Sets for BACKUP(AMS) . . . 291
147. Concatenating Journal Data Sets for BACKUP(DSS) . . . 291
148. JCL Example for Forward Recovering the Control Data Set . . . 292
149. JCL Example for Forward Recovering the Control Data Set . . . 292
150. JCL Example for Reorganizing the CDS with Journal Backup . . . 293
151. JCL Example for Reorganizing the CDS without Journal Backup . . . 293
152. JCL Example for Moving the Control Data Set and Journal . . . 296
153. JCL Example for Restoring the Control Data Set Backup. . . . 296
154. JCL Example for Restoring the Control Data Set Backup Using the DSSOPT DD Statement 296
155. JCL Example for Backing Up the Control Data Set and Journal . . . 297
156. JCL Example for Restoring the Back Ups . . . 297
157. JCL Example for Backing Up the Control Data Set and Journal . . . 298
158. Creating the Control Data Set . . . 300
159. Updating the Control Data Set . . . 300
160. Verifying the Contents of the Control Data Set . . . 300
161. Mending the Control Data Set . . . 300
162. EDGUTIL EXEC Parameters . . . 301
163. EDGUTIL SYSIN Commands . . . 303
164. Example of JCL for VERIFY(STORE) . . . 305

165. Sample JCL for Verifying the Control Data Set and the TCDB 306
166. Changing Volume Type and Volume Location 307
167. Sample EDGUTIL SYSPRINT Output 308
168. JCL for EDGINERS Automatic Processing 313
169. JCL for EDGINERS Manual Processing 313
170. JCL for Initializing Volumes with ISO/ANSI Version 4 VOL1 and HDR1 Labels 314
171. EDGINERS EXEC Parameters 315
172. EDGINERS SYSIN Commands 319
173. Defining Scratch Volumes to be Initialized 323
174. Changing the Initialization Action for a Volume 323
175. Using IEBGENER 325
176. Writing IBM Standard Labels on Three Tapes 326
177. Writing an ISO/ANSI Label on a Tape 326
178. Numbering Tape Volumes 327
179. Placing Serial Numbers on Eight Tape Volumes 327
180. Relabeling a Volume 328
181. Automatically Initialize or Erase 3480 Volumes 328
182. Initialize and Erase Volumes in a System-Managed Library 328
183. Initialize 50 Scratch Enhanced Capacity Cartridges 329
184. Erase a Volume 329
185. RMMISPF Exec Syntax Diagram 331
186. Adding DFSMSrmm Librarian Option to ISPF 332
187. Before Modifying the Trailer 1 for EDGRPTD 334
188. After Modifying the Trailer 1 for EDGRPTD 334
189. Notify Owner Messages 335
190. Default Notification Text 335
191. Modified Messages 336
192. Modified Notification Text 336
193. Notifying Product Owner 337
194. Notify Product Owner Messages. 338
195. EDGXPROC Procedure 340
196. Example BACKUPPROC procedure 341
197. Sample Label Procedure 342
198. Sample JCL Job that Allocates and Catalogs the PDA Log Data Sets 345
199. Sample JCL Job that Defines the GDG Name for the Archived PDA Log Data Set 346
200. Sample JCL Job that Copies the Inactive PDA Log Data Set to Tape 346
201. Disposition Control File Record Format 348
202. Sample JCL to Request Disposition Processing 350
203. Default Label Format for a Tape Cartridge 351
204. Default Label Format for a Round Tape 351
205. Overriding Vital Record Specification Management Processing with the RMM CHANGEDATASET TSO Subcommand 354
206. DFSMSrmm Primary Option Menu 362
207. DFSMSrmm Volume Menu 362
208. DFSMSrmm Add Scratch Volumes Panel 363
209. Sample Data Set Information 364
210. JCL for Allocating and Cataloging PDA Log Data Sets 411

Tables

1. Character Sets xxv
2. Special Characters Used in Syntax xxv
3. DFSMSrmm Movement Priority 7
4. How the DFSMSrmm Running Mode Affects Tape Mount Validation 17
5. DFSMSrmm Resource Symbolic Names 28
6. Data Sets Requiring Access by the DFSMSrmm RACF User ID 33
7. Creating DFSMSrmm Parmlib Definitions 34
8. DFSMSrmm Control Data Set DASD Space Requirements 36
9. DFSMSrmm Journal DASD Space Requirements 40
10. Default Libraries to Concatenate 44
11. DFSMSrmm Volumes in a Pool Determined by Pool Prefix 59
12. SMS Read-only Variables Set by DFSMSrmm 64
13. SMS Read-only Variables Set by DFSMSrmm 69
14. DFSMSrmm Entry Processing Decisions 86
15. Differences between Built-in and Installation Defined Storage Locations 108
16. Storing Media of the Same Shape 111
17. Storing Media of Different Shapes 111
18. How OPMODE Honors the Settings of Various Options 135
19. How OPMODE Value Affects System-Managed Tape Library Support 135
20. Resources You Protect with RACF Profiles 153
21. Authorized Functions 155
22. Suggested Resource Access 158
23. General User Functions 159
24. Storage Administrator Functions 159
25. System Programmer Functions 160
26. Librarian Functions 160
27. Inventory Management Functions 161
28. Operator Functions 161
29. RACF Processing Performed by DFSMSrmm 165
30. Installation Exits Used by DFSMSrmm 177
31. OAM Installation Exits 180
32. EDGLCSUX Return and Reason Codes Returned in Register 15 and Register 0 181
33. EDGLCSUX Return and Reason Codes Based on DFSMSrmm Reason Code Setting 182
34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List 184
35. Processing for the Change Use Attribute Parameter List 189
36. Processing for the Cartridge Entry Parameter List 189
37. Processing for the Cartridge Eject Parameter List 189
38. Processing for the Volume-Not-In-Library Parameter List 190
39. DFSMSrmm OAM Return Codes from EDGLCSUX Register 15 191
40. EDGUX100 Installation Exit Return Codes 220
41. EDGUX200 Installation Exit Return Codes 224
42. Authorization Required to Use Scratch Tapes with DFSMShsm 225
43. Authorization Required to Use DFSMShsm with a DFSMShsm Scratch Pool 226
44. Authorization Required to Use DFSMSrmm with ABARS 226
45. Scheduling DFSMSrmm Utilities 247
46. DFSMSrmm EDGHKSP Data Sets 251
47. DFSMSrmm Extract Data Set DASD Space Requirements 252
48. DFSMSrmm Movement Priority Default Values 270
49. EDGHSKP Return Codes 281
50. EDGBKUP Return Codes 293
51. EDGUTIL Return Codes 308
52. EDGINERS Return Codes 325
53. Customizing Report Titles 334

© Copyright IBM Corp. 1992, 2001

54. Setting the Message Route Code 348
55. Coding Sticky Label Text 349
56. Tivoli OPC Applications 357
57. SAMPLIB and SMPSTS Members 385
58. Evaluating Removable Media Management Needs 407

About This Book

This book is intended for storage administrators and system programmers who are responsible for implementing and customizing DFSMSrmm™.

Before using this book, you should read *z/OS DFSMS Migration* for detailed planning and installation information for DFSMSrmm as well as other DFSMS™ functional components. Additionally, you should have installed DFSMSrmm with SMP/E using the directions in *z/OS Program Directory*.

Required Product Knowledge

You should be familiar with several products before using this book:

- RACF®, for defining resources and creating access lists
- ISPF, for using and customizing the DFSMSrmm ISPF dialog
- DFSMShsm™, for customizing the interaction between DFSMShsm and DFSMSrmm
- OAM, for customizing the interface between DFSMSrmm and OAM
- DFSMSdss™, for backing up the DFSMSrmm control data set and journal

Referenced Publications

The following publications have additional information about DFSMSrmm:

Publication Title	Order Number
z/OS DFSMSrmm Application Programming Interface	SC26-7403
z/OS DFSMSrmm Command Reference Summary	SX26-6022
z/OS DFSMSrmm Diagnosis Guide	SY27-7619
z/OS DFSMSrmm Guide and Reference	SC26-7404
z/OS DFSMSrmm Reporting	SC26-7406

This book also refers to the following publications:

Publication Title	Order Number
Basic Tape Library Support Version 1 Release 1 User's Guide and Reference	SC26-7016
Data Facility Removable Media Manager for MVS/DFP Version 3 Program Offering	SC26-7011
DFSORT Application Programming Guide R14	SC33-4035
IBM 3590 High Performance Tape Subsystem Introduction and Planning Guide	GA32-0330
Magstar 3494 Tape Library Introduction and Planning Guide	GA32-0279
Magstar 3494 Tape Library Operator Guide	GA32-0280
MVS Batch Local Shared Resources	GC28-1469
z/OS DFSMS Installation Exits	SC26-7396
z/OS DFSMS Migration	GC26-7398

© Copyright IBM Corp. 1992, 2001

Publication Title	Order Number
z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries	SC35-0427
z/OS DFSMS: Using Data Sets	SC26-7410
z/OS DFSMS: Using Magnetic Tapes	SC26-7412
z/OS DFSMSdfp Diagnosis Reference	GY27-7618
z/OS DFSMSdss Storage Administration Reference	SC35-0424
z/OS DFSMShsm Data Recovery Scenarios	GC35-0419
z/OS DFSMShsm Implementation and Customization Guide	SC35-0418
z/OS DFSMShsm Storage Administration Guide	SC35-0421
z/OS JES3 Initialization and Tuning Guide	SA22-7549
z/OS MVS JCL Reference	SA22-7597
z/OS MVS Planning: Global Resource Serialization	SA22-7600
z/OS MVS System Commands	SA22-7627
z/OS MVS System Management Facilities (SMF)	SA22-7630
z/OS MVS System Messages, Vol 1	SA22-7631
z/OS MVS System Messages, Vol 2	SA22-7632
z/OS MVS System Messages, Vol 3	SA22-7633
z/OS MVS System Messages, Vol 4	SA22-7634
z/OS MVS System Messages, Vol 5	SA22-7635
z/OS MVS System Messages, Vol 6	SA22-7636
z/OS MVS System Messages, Vol 7	SA22-7637
z/OS MVS System Messages, Vol 8	SA22-7638
z/OS MVS System Messages, Vol 9	SA22-7639
z/OS MVS System Messages, Vol 10	SA22-7640
z/OS MVS Using the Subsystem Interface	SA22-7642
OS/390 Program Directory	
z/OS SecureWay Security Server RACF Security Administrator's Guide	SA22-7683
z/OS SecureWay Security Server RACF System Programmer's Guide	SA22-7681
z/OS TSO/E Customization	SA22-7783
z/OS V1R1.0 ISPF User's Guide Vol I	SC34-4822
ServerPac: Installing Your Order	

How To Use This Book

This book explains how to implement DFSMSrmm for users with no existing media management system. Refer to the following chapters to implement DFSMSrmm:

"Chapter 1. Introducing DFSMSrmm" on page 1
"Chapter 2. Implementing DFSMSrmm" on page 23
"Chapter 3. Organizing the Removable Media Library" on page 55
"Chapter 4. Running DFSMSrmm with System-Managed Tape Libraries" on page 77
"Chapter 5. Running DFSMSrmm with BTLS" on page 103

"Chapter 6. Managing Storage Locations" on page 107
"Chapter 7. Using the Parmlib Member EDGRMMxx" on page 115
"Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security" on page 153
"Chapter 9. Using DFSMSrmm Programming Interfaces" on page 177
"Chapter 10. Using DFSMSrmm Installation Exits" on page 195
"Chapter 11. Running DFSMSrmm with DFSMShsm" on page 225
"Chapter 12. Running DFSMSrmm with JES3" on page 243
"Chapter 13. Performing Inventory Management" on page 247
"Chapter 16. Maintaining the Control Data Set" on page 287
"Chapter 17. Initializing and Erasing Volumes" on page 311
"Appendix A. DFSMSrmm Installation Verification Procedures" on page 359

To set up and run DFSMSrmm utilities, refer to:

"Chapter 13. Performing Inventory Management" on page 247
"Chapter 16. Maintaining the Control Data Set" on page 287
"Chapter 17. Initializing and Erasing Volumes" on page 311

To customize DFSMSrmm, refer to:

"Chapter 9. Using DFSMSrmm Programming Interfaces" on page 177
"Chapter 10. Using DFSMSrmm Installation Exits" on page 195
"Chapter 18. Customizing DFSMSrmm" on page 331
"Chapter 19. Using the Problem Determination Aid Facility" on page 343
"Chapter 20. Setting Up DFSMSrmm Disposition Processing" on page 347
"Chapter 21. Running DFSMSrmm with Tivoli OPC" on page 353

How to Find Samples in this Book

Throughout this book, when a task has an available sample, we point you to the sample using a figure like the one that follows:

DFSMSrmm Sample Provided in SAMPLIB
CBRUXENT Programming Interface to EDGLCSUX

See "Appendix C. Using DFSMSrmm Samples" on page 385 for a list of the DFSMSrmm supplied samples.

Notational Conventions

This section explains the notational conventions used in this book.

How to Read Syntax Diagrams

Throughout this library, diagrams are used to illustrate the programming syntax. Keyword parameters are parameters that follow the positional parameters. Unless otherwise stated, keyword parameters can be coded in any order. The following list tells you how to interpret the syntax diagrams:

- Read the diagrams from left-to-right, top-to-bottom, following the main path line. Each diagram begins on the left with double arrowheads and ends on the right with two arrowheads facing each other.

- If a diagram is longer than one line, each line to be continued ends with a single arrowhead and the next line begins with a single arrowhead.



- Required keywords and values appear on the main path line. You must code required keywords and values.

  If several mutually exclusive required keywords or values exist, they are stacked vertically in alphanumeric order.



- Optional keywords and values appear below the main path line. You can choose not to code optional keywords and values.



  If several mutually exclusive optional keywords or values exist, they are stacked vertically in alphanumeric order below the main path line.

- An arrow returning to the left above a keyword or value on the main path line means that the keyword or value can be repeated. The comma means that each keyword or value must be separated from the next by a comma.

- An arrow returning to the left above a group of keywords or values means more than one can be selected, or a single one can be repeated.



- A word in all uppercase is a keyword or value you must spell exactly as shown. In this example, you must code ***KEYWORD***.

  If a keyword or value can be abbreviated, the abbreviation is discussed in the text associated with the syntax diagram.
- If a diagram shows a character that is not alphanumeric (such as parentheses, periods, commas, and equal signs), you must code the character as part of the syntax. In this example, you must code ***KEYWORD=(001,0.001)***.



- If a diagram shows a blank space, you must code the blank space as part of the syntax. In this example, you must code ***KEYWORD=(001 FIXED)***.

- Default keywords and values appear above the main path line. If you omit the keyword or value entirely, the default is used.

- A word in all lowercase italics is a *variable*. Where you see a variable in the syntax, you must replace it with one of its allowable names or values, as defined in the text.



- References to syntax notes appear as numbers enclosed in parentheses above the line. Do not code the parentheses or the number.



  Notes:

  1 An example of a syntax note.
- Some diagrams contain *syntax fragments*, which serve to break up diagrams that are too long, too complex, or too repetitious. Syntax fragment names are in

mixed case and are shown in the diagram and in the heading of the fragment. The fragment is placed below the main diagram.

Syntax Fragment:



The following figure shows an example of a syntax diagram.



Notes:

1 Must be specified if the owner owns one or more volumes.

Figure 1. Example of the DFSMSrmm DELETEVOLUME Syntax Diagram

The possible valid versions of the RMM DELETEOWNER command are:

```
RMM DELETEOWNER owner
RMM DO          owner
RMM DELETEOWNER owner NEWOWNER(new_owner)
RMM DO          owner NEWOWNER(new_owner)
```

How to Abbreviate Commands and Operands

The TSO abbreviation convention applies for all DFSMSrmm commands and operands. The TSO abbreviation convention requires you to specify as much of the command name or operand as is necessary to distinguish it from the other command names or operands.

Some DFSMSrmm keyword operands allow unique abbreviations. All unique abbreviations are shown in the command syntax diagrams.

How to Use Continuation Characters

The symbol **-** is used as the continuation character in this book. You can use either **-** or **+**.

- Do not ignore leading blanks on the continuation statement

+ Ignore leading blanks on the continuation statement

Delimiters

When you type a command, you must separate the command name from the first operand by one or more blanks. You must separate operands by one or more blanks or a comma. Do not use a semicolon as a delimiter because any character you enter after a semicolon is ignored.

Character Sets

To code job control statements, use characters from the character sets in Table 1. Table 2 lists the special characters that have syntactical functions in job control statements.

Table 1. Character Sets

Character Set	**Contents**	
Alphanumeric	Alphabetic Numeric	Capital A through Z 0 through 9
National (See note)	“At” sign Dollar sign Pound sign	@ (Characters that can be $ represented by hexadecimal # values X'7C', X'5B', and X'7B')
Special	Comma Period Slash Apostrophe Left parenthesis Right parenthesis Asterisk Ampersand Plus sign Hyphen Equal sign Blank	, . / ' ( ) * & + - =
EBCDIC text	EBCDIC printable character set	Characters that can be represented by hexadecimal X'40' through X'FE'
Note: The system recognizes the following hexadecimal representations of the U.S. National characters; @ as X'7C'; $ as X'5B'; and # as X'7B'. In countries other than the U.S., the U.S. National characters represented on terminal keyboards might generate a different hexadecimal representation and cause an error. For example, in some countries the $ character may generate a X'4A'.		

Table 2. Special Characters Used in Syntax

Character	**Syntactical Function**
,	To separate parameters and subparameters
=	To separate a keyword from its value, for example, BURST=YES
( )	To enclose subparameter list or the member name of a PDS or PDSE
&	To identify a symbolic parameter, for example, &LIB
&&	To identify a temporary data set name, for example, &&TEMPDS, and, to identify an in-stream or sysout data set name, for example, &&PAYOUT
.	To separate parts of a qualified data set name, for example, A.B.C., or parts of certain parameters or subparameters, for example, nodename.userid
*	To refer to an earlier statement, for example, OUTPUT=*.name, or, in certain statements, to indicate special functions: //label CNTL * //ddname DD * RESTART=* on the JOB statement
’	To enclose specified parameter values which contain special characters
(blank)	To delimit fields

Accessing z/OS DFSMS® Books on the Internet

In addition to making softcopy books available on CD-ROM, IBM provides access to unlicensed z/OS softcopy books on the Internet. To find z/OS books on the Internet, first go to the z/OS home page: **http://www.ibm.com/servers/eservers/zseries/zos**

From this Web site, you can link directly to the z/OS softcopy books by selecting the Library icon. You can also link to IBM Direct to order hardcopy books.

Accessing Messages Using LookAt

LookAt is an online facility that allows you to look up explanations for z/OS messages and system abends.

Using LookAt to find information is faster than a conventional search because LookAt goes directly to the explanation.

LookAt can be accessed from the Internet or from a TSO command line.

You can use LookAt on the Internet at:

`www.ibm.com/servers/eserver/zseries/zos/bkserv/lookat/lookat.html`

To use LookAt as a TSO command, LookAt must be installed on your host system. You can obtain the LookAt code for TSO from the LookAt Web site by clicking on **News and Help** or from the *z/OS Collection*, SK3T-4269.

To find a message explanation from a TSO command line, simply enter: **lookat** *message-id* as in the following example:

```
lookat iec192i
```

This results in direct access to the message explanation for message IEC192I.

To find a message explanation from the LookAt Web site, simply enter the message ID. You can select the release if needed.

Note: Some messages have information in more than one book. For example, IEC192I has routing and descriptor codes listed in *z/OS MVS Routing and Descriptor Codes*. For such messages, LookAt prompts you to choose which book to open.

How to Send Your Comments

Your feedback is important in helping to provide the most accurate and high-quality information. If you have any comments about this book or any other DFSMS documentation:

- Send your comments by e-mail to:
  - IBMLink from US: starpubs@us.ibm.com
  - IBMLink from Canada: STARPUBS at TORIBM
  - IBM Mail Exchange: USIB3VVD at IBMMAIL
  - Internet: starpubs@us.ibm.com

  Be sure to include the name of the book, the part number of the book, version and product name, and if applicable, the specific location of the text you are commenting on (for example, a page number or a table number).

- Fill out one of the forms at the back of this book and return it by mail or by giving it to an IBM representative. If the form has been removed, address your comments to IBM Corporation, RCF Processing Department M86/050, 5600 Cottle Road, San Jose, California 95193-0001, U.S.A.

Chapter 1. Introducing DFSMSrmm

DFSMSrmm™ is an z/OS® feature. In your enterprise, you probably store and manage removable media in several types of media libraries. For example, in addition to your traditional tape library, a room with tapes, shelves, and drives, you might have several automated, virtual, and manual tape libraries. You probably also have both on-site libraries and off-site storage locations, also known as vaults or stores.

With DFSMSrmm, you can manage your removable media as one enterprise-wide library across systems. DFSMSrmm manages your installation's tape volumes and the data sets on those volumes. DFSMSrmm also manages the shelves where volumes reside in all locations except in automated tape library dataservers.

DFSMSrmm manages all tape media, such as cartridge system tapes and 3420 reels, as well as other removable media you define to it. For example, DFSMSrmm can record the shelf location for optical disks and track their vital record status; it does not manage the objects on optical disks.

This chapter discusses basic tape management concepts and introduces terminology used throughout the DFSMSrmm publications and in the DFSMSrmm Interactive System Productivity Facility (ISPF) dialog. This chapter also discusses tape management tasks you can perform with DFSMSrmm.

What Libraries and Locations Can DFSMSrmm Manage?

You decide where to store your removable media based on how often you access the media and for what purpose you retain the media. For example, you might keep volumes that are frequently accessed in an automated tape library dataserver. You probably use at least one storage location to retain volumes for disaster recovery and audit purposes. You might also have locations to which you send volumes for further processing. These locations might be other data centers within your company or at your customers and vendors locations.

DFSMSrmm can manage:

- A removable media library, which incorporates all other libraries, such as:
  - System-managed tape libraries; for example, the automated IBM® 3494 Tape Library Dataserver and IBM Magstar® 3494 Virtual Tape Servers
  - Non-system-managed tape libraries or traditional tape libraries
- Storage locations that are on-site and off-site

What Is in a Removable Media Library?

A *removable media library* contains all the tape and optical volumes that are available for immediate use, including the shelves where they reside. A removable media library usually includes other libraries: *system-managed libraries* such as *automated* or *manual tape libraries*; and *non-system-managed libraries*, containing the volumes, shelves, and drives not in an automated or a manual tape library.

In the removable media library, you store your volumes in shelves, where each volume occupies a single *shelf location*. This shelf location is referred to as a *rack number* in the RMM TSO subcommands and in the DFSMSrmm ISPF dialog. A rack number matches the volume's external label. DFSMSrmm uses the external volume serial number to assign a rack number when adding a volume, unless you specify

© Copyright IBM Corp. 1992, 2001

otherwise. The format of the volume serial you define to DFSMSrmm must be one to six alphanumeric characters. The rack number must be six alphanumeric or national characters.

What Is in a System-Managed Tape Library?

A *system-managed tape library* consists of tape volumes and tape devices that are defined in the tape configuration database. The tape configuration database is an integrated catalog facility user catalog marked as a volume catalog (VOLCAT) containing tape volumes and tape library records. A system-managed tape library can be either automated or manual.

You can have several automated tape libraries or manual tape libraries. You use an installation-defined library name to define each automated tape library dataserver or manual tape library to the system. DFSMSrmm treats each system-managed tape library as a separate location or destination. See *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries* for additional information.

Automated Tape Library Dataservers

An *automated tape library dataserver* is a device consisting of robotic components, cartridge storage areas (or shelves), tape subsystems, and controlling hardware and software, together with the set of tape volumes that reside in the library and can be mounted on the library tape drives. DFSMSrmm provides support for the automated IBM 3494 Tape Library Dataserver and also the IBM 3495 Tape Library Dataserver. The IBM 3494 Tape Library Dataserver supports 3490E and 3590 tape subsystems. The IBM 3495 Tape Library Dataserver supports 3490, 3490E, and 3590 tape subsystems. The IBM 3494 Tape Library Dataserver can also include the Virtual Tape Server subsystem. DFSMSrmm supports the IBM Peer-to-Peer VTS by ensuring that you cannot use the names of distributed VTS libraries with DFSMSrmm. You must only use the names of consolidated libraries with DFSMSrmm.

DFSMSrmm can automatically replenish the scratch volumes in an automated tape library dataserver when the supply of volumes becomes low. See “Replenishing Scratch Volumes in a System-Managed Library” on page 340 for information about how DFSMSrmm reclaims volumes that are eligible for returning to scratch.

DFSMSrmm has a cartridge entry installation exit that you can use to help partition volumes in a single system-managed tape library across multiple systems. Use the installation exit for support for sharing between Multiple Virtual Storage (MVS) and other systems and also for partitioning between MVS™ systems and SMS complexes. When using the cartridge entry installation exit, consider these factors.

- DFSMSrmm supports partitioning when you use the DFSMSrmm parmlib options to identify volumes that you want to partition. Volumes can be identified based on volume naming conventions and as individual volumes defined to DFSMSrmm on MVS.
- With a single tape configuration database across multiple MVS systems and complexes, you also need a single DFSMSrmm control data set. All volumes can be used on any or all systems with no partitioning possible.

Manual Tape Libraries

A *manual tape library* is a set of tape drives and the set of system-managed volumes the operator can mount on those drives. The manual tape library provides more flexibility, enabling you to use various tape volumes in a given manual tape

library. This support allows volumes to be associated with manual tape libraries so that only those volumes defined for a specific manual tape library can be mounted on drives in that library.

Unlike the automated tape library dataserver, the manual tape library does not use the library manager. With the manual tape library, a human operator responds to mount messages that are generated by the host and displayed on a console. This manual tape library implementation completely replaces the IBM 3495-M10 implementation. IBM no longer supports the 3495-M10.

See “Setting Up DFSMSrmm for the System-Managed Tape Library” on page 98 for implementation details for these scenarios.

What Is in a Non-System-Managed Tape Library?

A *non-system-managed tape library* is all the volumes, shelves, and drives not in an automated tape library dataserver or manual tape library. You might know this as the traditional tape library in a data center or as an automated environment that is not system-managed. DFSMSrmm provides complete tape management functions for the volumes and shelves in this traditional tape library. Volumes in a non-system-managed library are defined by DFSMSrmm as being *shelf-resident* volumes.

All tape media and drives supported by z/OS are supported in this environment. Use DFSMSrmm to fully manage all types of tapes in a non-system-managed tape library, including 3420 reels, 3480, 3490, and 3590 cartridge system tapes.

You can also use DFSMSrmm to manage volumes in any automated tape library that has special software including an IBM Tape Library Data server that is managed using Basic Tape Library Support (BTLS).

What Is in a Storage Location?

Storage locations are not part of the removable media library because the volumes in storage locations are not generally available for immediate use. A storage location is comprised of shelf locations that you define to DFSMSrmm. A shelf location in a storage location is identified by a *bin number*. Storage locations are typically used to store removable media that are kept for disaster recovery or vital records. DFSMSrmm manages two types of storage locations: installation-defined storage locations and DFSMSrmm built-in storage locations.

You can define an unlimited number of installation-defined storage locations, using any eight-character name for each storage location. Within the installation-defined storage location, you can define the type or shape of the media in the location. You can also define the bin numbers that DFSMSrmm assigns to the shelf locations in the storage location. You can request DFSMSrmm shelf-management when you want DFSMSrmm to assign a specific shelf location to a volume in the location.

You can also use the DFSMSrmm built-in storage locations which are LOCAL, DISTANT, and REMOTE. Although the names of these locations imply their purpose, they do not mandate their actual location. All volumes can be in the same or separate physical location. For example, an installation could have the LOCAL storage location on-site, as a vault in the computer room, the DISTANT storage location could be a vault in an adjacent building, and the REMOTE storage location could be a secure facility across town or in another state. DFSMSrmm provides shelf-management for storage locations so that storage locations can be managed at the shelf location level.

Although DFSMSrmm automatically shelf-manages built-in storage locations, you must first define the bins you want to use to DFSMSrmm. For bin numbers in built-in storage locations, the numbers are fixed in range, starting at bin number 000001. For installation-defined storage locations, you can use any alphanumeric characters.

How Does DFSMSrmm Manage These Libraries and Locations?

DFSMSrmm records the complete inventory of the removable media library and storage locations in the DFSMSrmm control data set which is a VSAM key-sequenced data set. DFSMSrmm records all changes made to the inventory, such as adding or deleting volumes, and also keeps track of all movement between libraries and storage locations.

DFSMSrmm manages the movement of volumes among all library types and storage locations. This lets you control where a volume, and hence a data set, resides and how long it is retained.

DFSMSrmm helps you manage the movement of your volumes and retention of your data over their full life, from initial use to the time they are retired from service. Among the functions DFSMSrmm performs for you are:

- Automatically initializing and erasing volumes.
- Recording information about volumes and data sets as they are used.
- Expiring volumes based on controls you define.
- Identifying volumes with high error levels that require replacement.

To use all of the DFSMSrmm functions, you specify installation setup options and define retention and movement policies. DFSMSrmm provides you with utilities to implement the policies you define. The following sections describe options, policies, and utilities.

Setting Up Your Installation Options

The DFSMSrmm parmlib member EDGRMMxx includes many options for setting up DFSMSrmm, such as:

- Defining system options, such as the date format for reports and messages, default retention periods, and notification to volume owners when their volumes are ready to be released.
- Preventing a range of tapes from being used on specific systems.
- Specifying if a pool has tape profile processing as provided by RACF, a component of the SecureWay® Security Server for z/OS.
- Tailoring mount messages with either the volume's shelf location or the pool identifier.
- Defining security classes for data sets and volumes.
- Defining the DFSMSrmm running mode to determine when DFSMSrmm records volume usage and performs tape validation as described in "How Does DFSMSrmm Validate Tape Mounts?" on page 17.
- Defining how DFSMSrmm bypass label processing is performed.
- Defining storage locations to DFSMSrmm.

Your system programmer or storage administrator defines your DFSMSrmm installation options during implementation. For information on the options that can be set in EDGRMMxx, see "Chapter 7. Using the Parmlib Member EDGRMMxx" on page 115.

Defining Retention and Movement Policies

The retention and movement policies you define to DFSMSrmm are known as *vital record specifications*. You use them to specify how long and where you want to keep data sets or volumes. You also use them to define how volumes are to be moved among the libraries DFSMSrmm supports and to define the storage locations for vital records and disaster recovery purposes.

Use vital record specifications to control retention requirements for production data in accordance with the service level agreement and known requirements.

Use the DFSMSrmm parmlib member EDGRMMxx to set expiration and retention defaults for your installation. See *z/OS DFSMSrmm Guide and Reference* for information about using the parmlib OPTION VRSEL operand to select vital record processing. When users are allowed to specify expiration and retention period to override vital record specifications, use the parmlib OPTION MAXRETPD operand to set a maximum retention period for your installation. See “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115 for information.

You can define policies, or vital record specifications, for data sets and volumes. You can also define name vital record specifications to provide retention information for data sets and volumes that must be moved through multiple locations before they expire.

Defining Home Location and Target Destinations

DFSMSrmm records the starting location for a volume when the volume is initially defined to DFSMSrmm or when volume information is changed. This starting location is known to DFSMSrmm as a *home* location. Home is the location where volumes start from and are returned to when the identified retention and movement actions have been completed. A non-system-managed library identified as SHELF can only be used as a home location and not as a target location in a vital record specification. SHELF can be used as a target location when a volume is moved by issuing a command.

You can give any system-managed library or storage location as a target destination for a volume move.

You can also use the DFSMSrmm-reserved location name CURRENT to avoid moving a volume from its current location.

Defining Retention Policies

Use data set names and data set name masks to define retention policies for data sets. Use job names and job name masks to define retention policies to further qualify the criteria for applying retention and movement policies. For data sets, you can request the following types of retention:

Retention by cycles
: You can use retention by cycles for generation data groups (GDGs), pseudo-GDG data set names, or data sets with the same name. For non-GDG data sets, DFSMSrmm considers each occurrence of a data set to be a cycle.

Retention by cycles by days
: You can use retention by cycles by days when you want DFSMSrmm to manage all copies of a data set created on a single calendar day as a single cycle.

Retention by number of elapsed days
: You can retain a data set specifying a number of days since it was created.

Retention for a number of extra days
You can retain a data set for a number of days beyond the date when the data set is no longer retained by the previous vital record specification in a vital record specification chain.

Retention by days since last referenced
You can retain each copy of a data set produced for a set number of days since the data set was read or written.

Retention while data set is cataloged
You can retain any data set as long as it remains cataloged.

Retention to a specific date
You can set a deletion date for a vital record specification. When that date is reached, the vital record specification is deleted. All data sets and volumes that would match the vital record specification become eligible for release processing, or might match a less specific vital record specification that might specify different retention and movement information.

Retention by expiration date
You can retain the data set on a volume as long as the volume expiration date has not yet been reached.

Retention of open data sets
You can specify a separate policy to apply to all data sets that are currently open.

Retention of data sets closed by abend processing
You can specify a separate policy to apply to all data sets that were open at the time of an application or system abend.

You can also use a *vital record specification management value* instead of a data set name to define retention policies. A vital record specification management value assigns management and retention policies to tape data sets and is defined by your installation. You can define data set vital record specifications for vital record specification management values to provide support for special JCL-specified expiration dates. You can use the sample installation exit contained in SYS1.SAMPLIB, EDGUX100, to assign vital record specification management values.

You can use management class names when you are managing data sets. See “Managing Volumes with Special Dates” on page 70 for information on assigning management class names and vital record specification management values using EDGUX100.

Defining Vital Record Specification Chains

You can combine retention types and movements within a vital record specification to manage data sets and volumes by defining vital record specifications chains. A vital record specification chain can be one or more vital record specifications linked together using NEXTVRS and ANDVRS operands. The first vital record specification in the chain is a data set or volume vital record specification. You can link vital record specifications to the first vital record specification to add additional retention types and movement policies for a data set or volume. When combining retention types, you can include the WHILECATALOG operand and the UNTILEXPIRED operand with one other retention type in a single vital record specification. To combine more retention types together so that all must be true concurrently, you link multiple vital record specifications using the ANDVRS operand. To combine different retention types to be implemented consecutively or to move a data set or volume through multiple locations consecutively, you link multiple vital record

specifications using the NEXTVRS operand. An exception is that when the EXTRADAYS operand is used as a retention type. EXTRADAYS must be the only retention type at that point in the vital record specification chain. Do not link to or from the vital record specification that specifies the EXTRADAYS operand using the ANDVRS operand.

See *z/OS DFSMSrmm Guide and Reference* for information about chaining vital record specifications.

Figure 2 is an example of creating a vital record specification chain. The data set name vital record specification moves a data set from the installation media library to the REMOTE storage location. The name vital record specification, MOVE2, moves the volume from the REMOTE storage location to the DISTANT storage location.

```
RMM ADDVRS DSNAME(STEGO.SAURUS) COUNT(1855) DAYS LOCATION(REMOTE) -
     STORENUMBER(30) NEXTVRS(MOVE2)
RMM ADDVRS NAME(MOVE2) LOCATION(DISTANT) STORENUMBER(1825)
```

Figure 2. Defining a Vital Record Specification Chain

You can define retention and movement policies for specific volumes and volumes that match a generic volume serial number. If you use a specific volume serial number, DFSMSrmm retains the volume that matches that volume serial number. If you use a generic volume serial number, DFSMSrmm retains a number of volumes matching the generic volume serial number based on the number you specify.

When multiple vital record specifications retain a volume, and each vital record specification contains a different destination, DFSMSrmm decides where to move the volume based on priority number. Lower priority numbers have higher priorities. Table 3 shows the movement priority DFSMSrmm uses if you do not assign movement priority numbers. For example, if you define both REMOTE and DISTANT as the destination for the volume, DFSMSrmm selects the REMOTE storage location as the destination. The selection is based on the REMOTE priority number of 100 which has a higher priority selection value than the DISTANT priority number of 200.

Table 3. DFSMSrmm Movement Priority

Priority Number	Location Name or Location Type
100	REMOTE DFSMSrmm built-in storage location name
200	DISTANT DFSMSrmm built-in storage location name
300	LOCAL DFSMSrmm built-in storage location
2000	Installation defined storage locations
4800	AUTO automated tape libraries
4900	MANUAL manual tape libraries
5000	SHELF location name

Running DFSMSrmm Utilities

DFSMSrmm provides utilities to manage your inventory, create reports, maintain the DFSMSrmm control data set, and erase and initialize volumes.

Use the EDGHSKP utility to run inventory management activities.

- Vital record processing determines which data sets to retain and what volume moves are required based on the retention and movement policies you define to DFSMSrmm.

  DFSMSrmm supports trial run and production run vital record processing. Trial run vital record processing does not change data set and volume information in the DFSMSrmm control data set. Use trial run vital record processing to analyze the effect that your movement and retention policies will have. Based on your analysis, you can then determine if you need to change vital record specifications before performing production run vital record processing. This is helpful when you are defining your initial set of policies and when you need to make changes as you gain more experience with DFSMSrmm.
- Expiration processing identifies volumes ready to be released and returned to scratch.
- Storage location management processing assigns shelf locations to volumes being moved to storage locations.
- DFSMSrmm control data set functions back up the control data set and the journal, reset the journal data set when the control data set and journal are backed up, and create an extract data set.

Use the EDGAUD and EDGRPTD utilities and the EDGRRPTE exec to get information about your removable media library and storage locations. You can also get security trail information about volumes and data sets defined to DFSMSrmm and audit trail information about volumes, shelf assignments, and user activity.

Use the EDGUTIL utility to create, update, mend, and verify the control data set.

Use the EDGBKUP utility to back up and recover the control data set and journal.

Use DFSMSrmm backup utilities instead of other backup utilities, such as access method services EXPORT, because DFSMSrmm provides the necessary serialization and forward recovery functions using the journal data sets. DFSMSrmm backup utilities check whether the control data set is in use and tell the DFSMSrmm subsystem that backup or recovery is in process.

Use the EDGINERS utility to erase and initialize tape volumes either automatically or manually. You can use EDGINERS instead of the DFSMSdfp™ utility IEHINITT. See “Replacing IEHINITT with EDGINERS” on page 312 for details on the differences between the utilities and for information on controlling the use of IEHINITT.

You can schedule these utilities to run at the time and frequency that are best for your installation. Use a scheduling system such as Tivoli OPC™ for this purpose.

What Resources Does DFSMSrmm Manage?

The following sections describe how DFSMSrmm helps you manage shelf locations, volumes, data sets, information about volume owners, and software products in all libraries and storage locations.

Shelf Locations

DFSMSrmm automatically:

- Assigns a rack number to a volume that matches the volume serial number you specify except when:

  - You already specified a rack number or pool ID when you first defined a volume to DFSMSrmm.
  - There is no rack number that matches the volume.
  - The volume is a logical volume.
- Assigns bin numbers for the shelf locations in shelf-managed storage locations
- Provides a specific rack number or pool information in the fetch/mount message to help the operator respond to mount requests

DFSMSrmm also helps you delete rack or bin numbers for obsolete, empty shelf locations. You can create lists containing information about the shelf locations in your removable media library and in storage locations.

You can have more control over where volumes reside and how they are managed by defining your removable media into pools. A pool is a group of shelf locations defined by a common prefix or a group of volumes that require DFSMSrmm pool management functions. For example, based on your pool definitions, DFSMSrmm can ensure that RACF profiles exist for all volumes in a pool. You could also request that all volumes in a pool that are protected with an expiration date are processed automatically. See “Organizing the Library by Pools” on page 55 for information about defining your pools in parmlib member EDGRMMxx. If you do not define any pools, DFSMSrmm considers all volumes part of one default pool.

In DFSMSrmm, there are two categories of pools:

Rack pool
A *rack pool* is shelf space that can be assigned to hold any volumes. Although you can add scratch volumes to these pools, you cannot normally use these volumes to satisfy non-specific mount requests.

Each rack pool can contain private volumes and scratch volumes:

- Private volumes
  - Are not generally available for use because the data on them is not yet expired
  - Can have a master status or user status

    A master status indicates that the volume contains data that can only be overwritten based on criteria set by the EDGRMMxx MASTEROVERWRITE operand.

    A user status indicates that the volume contains data that can be overwritten even when a data set name does not match.
- Scratch volumes
  - Are available for use because they are either unused volumes or they contain expired data
  - Are used to satisfy scratch requests.

    With scratch volumes in rack pools, you can provide a user or group-based pool of volumes that is selected using the RMM GETVOLUME subcommand or with the EDGUX100 installation exit. Scratch volumes in a rack pool cannot be used where DFSMSrmm system-based pooling is in use.

Scratch pool
A *scratch pool* is shelf space assigned to hold volumes for use with the DFSMSrmm system-based scratch pooling or exit-based pooling. The volumes assigned to this shelf space can be used to satisfy scratch requests as long as

the volumes are in scratch status. Once the volume has been written to, it becomes a volume with master status, until the volume is returned to scratch status.

Pools within system-managed libraries are based on the external volume serial number, which is also used as the rack number. Most volumes in a system-managed library either belong to a general scratch pool or they can be separated into multiple scratch pools, one for each media type. For example, volumes can be divided into one pool for cartridge system tape and one pool for enhanced capacity cartridge system tapes. If volumes from other data centers are entered into a system-managed library for processing, a rack pool can be defined to allow you to take advantage of DFSMSrmm pool management functions.

Pools in non-system-managed libraries are logical sections of shelf space. The shelf space is divided based on rack number, logical groups of volumes based on volume prefix, or logical groups of volumes with the same storage group name. You can control shelf location assignment by specifying a pool ID when you define a volume to DFSMSrmm. DFSMSrmm automatically assigns the volume to the next available rack number in that pool. If you do not specify a shelf location or pool ID for a volume, DFSMSrmm attempts to assign the rack number that matches the volume serial number.

Volumes

DFSMSrmm provides support for the following volumes.

- DFSMSrmm provides full support for all types of physical volumes, tracking their use and the data they contain, and providing vaulting and retention services according to policies assigned to the data sets on the volumes.
- Logical volumes reside in a Virtual Tape Server(VTS) or on exported stacked volumes. Applications can access the data on these volumes only when they reside in a VTS. The data in a VTS is accessed in its tape volume cache or after the data has been copied to a physical volume through the use of special utilities. DFSMSrmm tracks the use of logical volumes and the data that resides on the volumes. Retention services are provided according to policies assigned to the data sets on the volumes. DFSMSrmm supports exporting of logical volumes on stacked volumes and provides vaulting services for these stacked volumes based on the policies assigned to the data sets on the contained logical volumes. Logical volumes can be removed from a VTS using export processing described in the “Using DFSMSrmm with the IBM Virtual Tape Server” on page 85.
- Stacked volumes have a one-to-one association with physical tape media and are used in a VTS to store logical volumes. Stacked volumes are not used by MVS applications but by the VTS and its associated utilities. Stacked volumes can be removed from a VTS to allow transportation of logical volumes to a vault or to another VTS. DFSMSrmm can be used to track stacked volumes and automatically records the logical volumes contained on stacked volumes during export processing when stacked volume support is enabled. DFSMSrmm provides support for importing logical volumes on stacked volumes either into the VTS from which it was exported or into a different VTS.

DFSMSrmm automatically validates volumes to ensure that only valid scratch volumes are mounted for non-specific mount requests and that the right volume is mounted for a specific mount request. This eliminates unintentionally overwriting a valid master volume or a volume retained for disaster recovery or vital record management.

When a data set on a volume is opened and closed, DFSMSrmm automatically:

- Changes the volume status from scratch to master for non-specific mount requests at open time
- Sets an expiration date for the volume and ensures that the maximum expiration date is not exceeded at open time
- Records information about data sets on the volume (the data set name is recorded at open time; all other information is recorded at close time)
- Counts the number of times a volume is used since the volume was last in scratch status at open time
- Counts the number of temporary and permanent errors encountered at close time only
- Sets a security classification based on the data sets that reside on the volume at open time
- Prevents reading of data on a volume in scratch status when DFSMSrmm is running in protect mode at open time

DFSMSrmm automatically controls the movement of volumes within the removable media library and the built-in or installation-defined storage locations, based on criteria you specify in vital record specifications.

When volumes no longer reside in the removable media library or storage locations, you can define loan locations where these volumes can be found. DFSMSrmm does not, however, manage the movement of volumes residing in loan locations.

DFSMSrmm automatically releases volumes that have reached their expiration date. Any non-scratch volume defined to DFSMSrmm has an expiration date indicating when the volume is to be considered for release. The volume expiration date can be:

- An expiration date or retention period, given in the JCL by the user when writing a data set to the volume.
- The date specified by the user when a scratch volume is requested using the RMM GETVOLUME subcommand or when information about the volume is manually added or changed.
- A default retention period for data sets set by your installation with the RETPD option in parmlib member EDGRMMxx in SYS1.PARMLIB.
- The expiration date that is set using the DFSMSrmm EDGUX100 installation exit. If the exit sets a zero date, the installation default retention period is used.

Your installation can also set a maximum retention period in parmlib member EDGRMMxx. An expiration date or retention period set for a volume cannot exceed this value.

You can retain a volume beyond its expiration date by using a vital record specification to define a retention policy. You can also manually override an expiration date and release a volume before the expiration date is reached.

When a volume is eligible for release, DFSMSrmm can perform *release actions* for the volume based on information you provide. Examples of release actions include:

- Returning a volume to scratch status
- Initializing a volume
- Erasing a volume
- Notifying a volume's owner of the volume's release

- Returning a volume to its owner and deleting the volume record in the DFSMSrmm control data set

See *z/OS DFSMSrmm Guide and Reference* for information about setting release actions and how processing is performed.

DFSMSrmm tracks the number of I/O errors recorded for a volume. For permanent errors, DFSMSrmm automatically marks the volumes for replacement before returning them to scratch. This occurs during expiration processing.

You can get additional information to help you analyze volumes with temporary errors from these tools and services:

- DFSMSrmm records volume use and temporary I/O errors. You can obtain this information through the extract data provided by EDGHSKP.
- The Environmental Record Editing and Printing Program (EREP) uses LOGREC records to identify tapes with unacceptably high error conditions.
- Service Director™ identifies volumes with high error levels. See your IBM service representative for information about using this tool.
- System management facilities (SMF) records, produced by DFSMSdfp, track information on volume use, such as how much data is written to a volume. You can use this information to analyze volumes with errors.

You can then use this information to identify volumes you want replaced or managed by DFSMSrmm. Use the RMM CHANGEVOLUME RELEASEACTION(REPLACE) subcommand or the dialog change volume function when you want DFSMSrmm to manage the replacement.

DFSMSrmm provides support for using RACF standard tape volume security protection. You can use any combination of RACF TAPEVOL and TAPEDSN options.

DFSMSrmm allows you to use volumes with duplicate volume serial numbers as well as volumes undefined to DFSMSrmm. You can request DFSMSrmm to ignore a volume so it can be used, even if another volume with the same volume serial number is already defined in the DFSMSrmm control data set. If DFSMSrmm ignores a volume, it does not track volume use. If the volume is not defined to DFSMSrmm, DFSMSrmm cannot provide any management functions for the volume.

DFSMSrmm Tape Label Support

DFSMSrmm supports the following tape label types:

- IBM standard labels (SL)
- ISO/ANSI labels (AL)
- Both IBM standard and user header or trailer labels (SUL)
- Both ISO/ANSI and user header or trailer labels (AUL)
- No labels (NL)

You can explicitly use AL, SL, and NL label types when you define volumes to DFSMSrmm. Although a tape is defined to DFSMSrmm as SL or AL, a user can still process it as SUL or AUL. A user could ask for a non-specific volume by specifying LABEL=(,SUL) and create an SL volume or SUL volume without affecting DFSMSrmm. DFSMSrmm records the value specified in the JCL.

DFSMSrmm provides support for ISO/ANSI Version 3 and ISO/ANSI Version 4 labels. You can provide the current ISO/ANSI label version of a volume that you

define to DFSMSrmm. Then you can use the DFSMSrmm EDGINERS utility to initialize the tape with either ISO/ANSI Version 3 or ISO/ANSI Version 4 labels.

DFSMSrmm supports no label (NL) for private volumes and for scratch tapes in a system-managed automated tape library and private volumes in a non-system-managed tape library. If you use the IFG019VM volume mount installation exit, DFSMSrmm supports no label (NL) for scratch tapes in a non-system-managed tape library. All other scratch tapes must be standard label tapes. DFSMSrmm allows the creation of no label tapes from standard label scratch volumes by changing the volume to master status and setting the initialize release action so that the tape is relabeled as a standard label tape when returned to scratch. DFSMSrmm also overrides the logical volume serial number generated by OPEN for NL output to scratch tapes, so that the correct volume serial number is used for cataloging data sets. Nonstandard labels (NSL) can be used but only if the volume is not defined to DFSMSrmm. “How Does DFSMSrmm Validate Tape Mounts?” on page 17 describes how DFSMSrmm validates volume usage and does not allow the processing of certain label types.

DFSMSrmm also supports the use of bypass label processing (BLP) for:

- Volumes that are either not defined to DFSMSrmm or volumes that DFSMSrmm should ignore.
- Non-scratch (user and master status) volumes that are used for input processing, and only those user status volumes that are used for output processing. You can select this system option in the EDGRMMxx parmlib member using the OPTION BLP(RMM) command.
- Non-scratch (user and master status) volumes that are used for input processing, or user, master and scratch tapes that are used for output processing. You can select this option in the EDGRMMxx parmlib member using the OPTION BLP(NORMM) command.

  When BLP is used with scratch tapes, DFSMSrmm changes the volume to master status. DFSMSrmm also sets the initialize volume release action to ensure that the volume has a valid standard label before it returns to scratch status. When a volume is written with BLP, DFSMSrmm can no longer perform the 44-character data set name check for the files on the volume.

  For BLP output to a non-specific volume, DFSMSrmm does not check the file sequence number. For example, LABEL=(2,BLP) can be used. For non-BLP requests, DFSMSrmm restricts the use to LABEL=(1,label_type).

  The data set information for files processed with BLP is only updated for output to first file on a volume. All other types of BLP requests change only the volume information such as the date last read and the date last written. Also for BLP output requests, the data set information is only updated in the DFSMSrmm control data set when the data set is closed.

Data Sets

DFSMSrmm automatically records information about a data set when the data set is opened. DFSMSrmm can automatically record information when you request data set recording and;

1. The data set is the first file on the volume.
2. Or you already processed all files preceding it on the volume.
3. Or you have previously defined the data sets on the volume to DFSMSrmm.

Data class, management class, storage class, and storage group are included in the information that DFSMSrmm records for system-managed data sets.

You can manually add information about a data set if the volume on which the data set resides is already defined to DFSMSrmm and the volume has not been already processed as a result of open processing and close processing. There are some limitations on the information that you can change if it was originally recorded by DFSMSrmm during open, close, and end-of-volume processing.

DFSMSrmm supports generic data set names as filter criteria for searching the control data set which makes it easier to create lists of resources.

Year 2000 Support

DFSMSrmm provides support for dates beyond the 20th century by ensuring that DFSMSrmm stores and displays all dates using a 4-digit year. DFSMSrmm also allows you to specify dates using the 4-digit year. DFSMSrmm provides the same support for dates as DFSMSdfp™.

Software Products

You can also define software products to DFSMSrmm and associate volumes with the products.

Owner Information

DFSMSrmm can help you keep track of volume owners. It provides functions to electronically notify owners when their volumes are being considered for release. DFSMSrmm automatically records owner IDs as volumes are used. If you want DFSMSrmm to use owner information to automatically notify owners, you must manually define the owner's electronic address to DFSMSrmm. Additionally, the notify action must have been requested for the volume.

DFSMSrmm ensures that there is an owner ID for each volume. If a job is started and does not have a known RACF user ID, DFSMSrmm uses the job name as the owner ID.

DFSMSrmm also provides for notification to product owners when new volumes are added for a product.

DFSMSrmm keeps track of volume ownership. To delete a record for a user who still owns volumes, DFSMSrmm optionally allows you to transfer ownership of those volumes before deleting the owner record.

How Does DFSMSrmm Help You Create Reports?

You can obtain information and create reports using:

- DFSMSrmm ISPF dialog or RMM TSO commands
- EDGAUD and EDGRPTD report utilities
- DFSMSrmm EDGRRPTE exec shipped in SAMPLIB
- The DFSORT™ ICETOOL utility
- The DFSMSrmm application programming interface

Using DFSMSrmm ISPF Dialog and RMM TSO Subcommands

You can search on-line using either the DFSMSrmm ISPF dialog or RMM TSO subcommands to create lists of resources and display information recorded in the DFSMSrmm control data set. Here are some examples:

- Operators can create lists of scratch volumes to be pulled for use.

- Tape librarians and system programmers can create lists of software products and the volumes on which they reside.
- General users can create lists of volumes they own, such as the example in Figure 3:

```
Volume Owner    Rack   Assigned   Expiration Location Dsets St Act   Dest.
                       date       date
------ -------- ------ ---------- ---------- -------- ----- -- ----- --------
VOL600 AMYW01   RAC500 06/11/2000 11/11/2000 SHELF    0     UR SI
VOL601 AMYW01   RAC501 06/11/2000 11/11/2000 SHELF    0     UR SI
VOL603 AMYW01   RAC502 06/11/2000 11/11/2000 SHELF    0     UR SI
EDG3011I 3 ENTRIES LISTED
```

Figure 3. Example of a List of Volumes Owned by a Single User

With DFSMSrmm, you can use the RMM TSO SEARCH subcommands with the CLIST operand to create a data set of executable subcommands. For example, you can create subcommands to confirm volume movement for volumes identified during a SEARCHVOLUME request.

Using the EDGAUD and EDGRPTD Report Utilities

You can create several types of reports using two DFSMSrmm report utilities. Use EDGRPTD to create movement and inventory reports and EDGAUD to create security and audit reports. EDGRPTD uses the DFSMSrmm extract data set as input. EDGAUD uses SMF records as input.

You can use the reports to:

- Identify volumes that should be moved between the removable media library and storage locations.
- Determine your volume inventory in the removable media library and storage locations.
- Identify volumes that are in transit or that should be marked as moved.
- Identify all accesses to volumes and changes to information recorded in the DFSMSrmm control data set.
- Separate volumes that are waiting to return to scratch from those that are private or have other release actions pending.

Using the DFSMSrmm EDGRRPTE Exec

Use the DFSMSrmm-supplied EDGJRPT JCL to run the EDGRRPTE exec to produce reports using the extract data set as input. See *z/OS DFSMSrmm Reporting* for more information.

Using the DFSORT ICETOOL Utility

You can use DFSORT™ or a similar program to generate a formatted report using the information in the extract data set created by the EDGHSKP utility. For example, you could produce an extract data set listing all volumes to be used on VM with information about volume owners. Then use the DFSORT ICETOOL utility to sort the information by volume and produce a report, complete with title and header information.

Using the DFSMSrmm Application Programming Interface

You can use the DFSMSrmm application programming interface to obtain information about resources defined to DFSMSrmm. See the *z/OS DFSMSrmm Application Programming Interface* publication for information about how to use the DFSMSrmm application programming interface.

How Does DFSMSrmm Authorization and Security Work?

You can choose the authorization levels of users for all DFSMSrmm functions. DFSMSrmm uses MVS System Authorization Facility (SAF) for its authorization checking. You define DFSMSrmm resources to RACF for use during authorization checking. DFSMSrmm can create volume profiles, change them, and delete them on registration, expiration, or release of volumes. DFSMSrmm provides an access list you can use to set the access list in RACF. You can use the DFSMSrmm access list for authorization checking on non-RACF systems. Use the RMM LISTVOLUME subcommand or the DFSMSrmm ISPF dialog to display the DFSMSrmm access list. You can also view the access list in the volume records in the report extract data set.

DFSMSrmm provides automatic security classification through installation-specified criteria based on data set names. DFSMSrmm security includes these elements.

- An audit trail of access and change of status through SMF. This audit trail produces information about RACF user IDs, groups, and job names.
- Required operator confirmation prior to using certain volumes.
- Erasure of data when a volume is released prior to the volume returning to scratch status.

DFSMSrmm provides the following ways of optionally keeping an audit trail for volumes defined to it.

- Control data set information
- SMF audit records
- RACF audit information

For more information about DFSMSrmm authorization and security, see the “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.

What Tape Usage Does DFSMSrmm Support?

DFSMSrmm supports the following tape usage.

- Using BLP to read any private volume.
- Using BLP to write to any volume.
- Using nonstandard label volumes that are not defined to DFSMSrmm.
- Using both AL and SL scratch tapes.
- Using no label (NL) processing for any private volume.
- Performing no label (NL) output to any system-managed scratch volume or standard label scratch volume.
- Using no label (NL) for private volumes and for scratch tapes in a system-managed automated tape library and private volumes in a non-system-managed tape library.
- Using no label (NL) also for scratch tapes in a non-system-managed tape library if you use the IFG019VM volume mount installation exit.

- Overwriting a volume that is in master status. For volumes in master status, DFSMSrmm allows the overwriting of data based on criteria set by the EDGRMMxx MASTEROVERWRITE operand.
- Overwriting a volume that is in user status no matter what the data set name is.
- Using volumes not defined to DFSMSrmm.
- Using duplicate volumes if you use the DFSMSrmm EDGUX100 installation exit.
- Automatically labeling scratch tapes in an automated tape library dataserver.
- Reusing 36-track recorded scratch tapes on 18-track drives and 256-track recorded scratch tapes on 128-track drives.
- Using multifile and multivolume data sets.
- Recording and validating only the first file on the volume.
- Creating checkpoint data sets on scratch volumes in an automated system-managed tape library.
- Creating non-checkpoint data sets on scratch volumes in an automated system-managed library, where the scratch volumes were previously a checkpoint secure volume.
- Exploiting high-speed cartridge tape positioning when an application does not exploit it.

How Does DFSMSrmm Validate Tape Mounts?

DFSMSrmm performs validation for all data sets on a volume that have been recorded by DFSMSrmm when a data set is opened. DFSMSrmm validates tape volumes as follows:

- For specific tape requests, DFSMSrmm checks that the correct private volume is mounted.
- For non-specific tape requests, DFSMSrmm checks that a scratch volume is mounted and that the volume is from an acceptable rack, scratch pool, or storage group.
- For volumes where DFSMSrmm has recorded the first file creation at open time, DFSMSrmm checks that the last 17 characters of the data set name from the tape volume HDR1 label match the first file data set name known to DFSMSrmm.
- For specific requests to overwrite data on a master volume, DFSMSrmm allows the overwriting of data based on criteria set by the EDGRMMxx OPTION MASTEROVERWRITE operand. DFSMSrmm checks that the data set name used matches the data set name that DFSMSrmm has recorded. For generation data group data (GDG) sets, DFSMSrmm removes the GDG suffix before checking the data set name.
- At open time for the file being referenced, DFSMSrmm checks that the data set name used matches the one DFSMSrmm has recorded. If only the first file on a volume is being recorded, DFSMSrmm only validates the first file on the volume.

  If DFSMShsm is reading a tape volume, only the last 17 characters of the data set name need to match the data set information in the tape header label.
- For scratch tapes mounted in a fully functional automated tape library dataserver, that have incorrect or missing VOL1 labels, DFSMSrmm checks the external and internal volume serial numbers. DFSMSrmm ensures that both the external volume serial number and internal volume serial number, if one exists, are either defined as scratch to DFSMSrmm or are not defined to DFSMSrmm.

DFSMSrmm performs tape mount validation based on the DFSMSrmm running mode set in the parmlib member EDGRMMxx with the OPTION command and OPMODE operand as shown in Table 4 on page 18.

Table 4. How the DFSMSrmm Running Mode Affects Tape Mount Validation

DFSMSrmm Running Mode	Tape Validation
Manual	DFSMSrmm does not validate volume usage.
Record-only	DFSMSrmm does not validate volume usage.
Warning	DFSMSrmm validates tape volume usage and issues warnings if errors are encountered. DFSMSrmm does not reject volume usage.
Protect	DFSMSrmm validates tape volume usage and rejects volume usage under certain conditions.

Note: Use warning mode as you perform testing during conversion from another tape management system. When you are running DFSMSrmm in warning mode, DFSMSrmm validates your tape volumes but does not prevent their use. See the “Defining System Options: OPTION” on page 122 for information about setting options in the DFSMSrmm parmlib member.

Why Does DFSMSrmm Reject Tape Volumes?

In addition to validation, there are a number of reasons why a tape can be rejected when you are running DFSMSrmm in protect mode. Volumes can be rejected based on installation-controlled parmlib options and volume definitions or based on DFSMSrmm and system rules.

Rejects Caused by Installation Controls

With DFSMSrmm you can define conditions such as where volumes should reside, ranges of shelf locations that should not be used, and volumes that can only be used on certain systems. If you are running DFSMSrmm in protect mode, the volume is rejected if:

- You have defined the REJECT option for a range of shelf locations, preventing a volume from being used on a particular system. The REJECT option is in parmlib member EDGRMMxx.
- The volume mounted for a scratch request has not been defined to DFSMSrmm.
- The volume mounted for a scratch request is not in a scratch pool associated with this system or does not match installation-defined requirements.
- The volume mounted for a scratch request is from a scratch pool associated with another system.
- The volume is not to be used on MVS systems.
- The volume is not defined to DFSMSrmm and your REJECT options request that all non-defined volumes are to be rejected.
- A user asks for the use of a volume to be ignored, but is not authorized to do so for that volume.
- A volume in an automated tape library dataserver is not defined to DFSMSrmm and cannot be defined to DFSMSrmm for some reason.

Rejects Caused by Validation Failure

DFSMSrmm performs validity checking on volumes when you read or write to them if DFSMSrmm is recording information about the data sets on the volumes. If you are running DFSMSrmm in protect mode the volume is rejected if:

- The wrong volume is mounted for a specific volume request.

- An attempt is made to use a specific scratch volume. In DFSMSrmm, when you want a specific volume, you must request a specific, non-scratch volume, and when you want a scratch volume, you must request a non-specific mount.
- A private volume (master or user) is mounted in response to a scratch request.
- The data set information for the first file on the volume that DFSMSrmm has recorded during open, close, or end-of-volume processing does not match the information on the volume.
- An attempt is made to overwrite a data set on a master volume and the specified data set name does not exactly match the data set name that DFSMSrmm has recorded. You can control the overwriting of data sets on master volumes using the EDGRMMxx OPTION MASTEROVERWRITE operand. If both the data set being written, and the data set DFSMSrmm has recorded are generation data group data sets, DFSMSrmm ignores the generation data group suffix when comparing the data set names.

  If the volume is part of a multivolume sequence containing multiple data sets, DFSMSrmm uses only the first volume, first file data set name for validation; for all other volumes the sequence of volumes is validated to prevent overwrite.
- An attempt is made to read a data set that DFSMSrmm has not recorded, and the volume information was previously recorded by DFSMSrmm.
- An attempt is made to automatically label a non-scratch volume in an automated tape library dataserver.

Rejects Caused by DFSMSrmm Rules

DFSMSrmm checks that volumes are labeled correctly and that the volume status and intended usage is acceptable to DFSMSrmm. If you are running DFSMSrmm in protect mode the volume is rejected if:

- An attempt is made to read a scratch volume.
- An attempt is made to read a volume obtained using the RMM GETVOLUME subcommand and the volume has not yet been written to. You use the RMM GETVOLUME subcommand to request a scratch volume and assign it to an owner defined to DFSMSrmm.
- Bypass label processing (BLP) is being used to write to a scratch or master volume unless you requested BLP processing through EDGRMMxx in the parmlib.
- An attempt is made to read or write to a volume using nonstandard labels, and the volume is defined to DFSMSrmm.
- An attempt is made to overwrite standard labels on a master volume, and the user is not authorized to do so.
- An attempt is made to write standard labels on a master volume that has no labels, and the user is not authorized to do so.
- An attempt is made to overwrite standard labels on a scratch volume by a user that is not authorized to do so.
- A scratch volume is requested for a nonstandard label request. In DFSMSrmm, scratch volumes must have standard labels.
- A volume is in an automated tape library dataserver and is defined to DFSMSrmm, but it is defined as not having a standard label or has different internal and external volume labels.
- An attempt is made to read or write to a volume that is waiting to be initialized.
- An attempt is made to read or write to a volume that is pending release.
- An attempt is made to write to a data set on the scratch volume other than the first one.

- An attempt is made to write to a data set that was specified with a sequence number that is not the next in the sequence from the last file DFSMSrmm has recorded. This applies only if DFSMSrmm is recording information about all the data sets on the subject volume.

Who Can Use DFSMSrmm and How?

The following sections describe DFSMSrmm users and the tasks they can perform.

General User

General users need only limited access to DFSMSrmm functions. They might want to manage volumes they own and request information about resources defined to DFSMSrmm.

General users can use DFSMSrmm to:

- Manually request a scratch volume
- Change information about an owned volume or data set
- Update information about your owner ID
- Manually release an owned volume
- Create lists of resources and display information about most resources defined to DFSMSrmm

See *z/OS DFSMSrmm Guide and Reference* for a quick description of these basic tasks.

Tape Librarian

Tape librarians can use DFSMSrmm to:

- Define new volumes
- Add shelf locations to the removable media library and to storage locations
- Add, change, and delete information about resources defined to DFSMSrmm
- Manually release any volume
- Confirm volume movements and actions
- Create lists of resources and display information about any resource defined to DFSMSrmm

Storage Administrator

Storage administrators can use DFSMSrmm to:

- Define retention and storage policies for data sets and volumes
- Change information about any volume they own, their owner ID, and any vital record specification
- Manually request a scratch volume
- Manually release a volume they own
- Delete a vital record specification
- Create lists of resources and display information about resources defined to DFSMSrmm

System Programmer

System programmers can use the DFSMSrmm support menu to:

- Display parmlib options and control data set control information
- Add, change, and delete information about any volume owner

- Manually request a volume and manually release a volume they own
- Create a list of software products and display information about any resource defined to DFSMSrmm

Operator

Operators can use DFSMSrmm to:

- Fetch and mount tapes from specific pools or shelf locations, as specified in mount messages
- Manually erase and initialize tapes
- Manually request a scratch volume
- Manually release a volume they own
- Create lists of scratch tapes available for use

See *z/OS DFSMSrmm Guide and Reference* for a complete description of operator procedures.

Using DFSMSrmm

You define RACF profiles to establish the authorization scheme for using DFSMSrmm functions. The basic authorization scheme recognizes there are different types of users and each user type will request common DFSMSrmm functions. See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for information on how authorization is set up for each user type.

In DFSMSrmm, you can use either the DFSMSrmm ISPF dialog or the set of TSO subcommands to request DFSMSrmm functions. The RACF profiles control whether or not DFSMSrmm responds to requests for functions. If you request a function you are not authorized to use, your request will fail. For descriptions of the TSO subcommands available within DFSMSrmm, see *z/OS DFSMSrmm Guide and Reference*.

DFSMSrmm offers menus in the DFSMSrmm ISPF dialog that are tailored specifically to a user group’s needs and level of access authorization. For example, only tape librarians are authorized to add software products to DFSMSrmm, so only the DFSMSrmm Librarian Menu includes an option to add software products. DFSMSrmm provides a specific menu for general users, storage administrators, tape librarians, and system programmers. It does not provide a menu for operators.Figure 4 on page 22 shows the menu designed for tape librarians:

```
  Panel  Help
------------------------------------------------------------------------------
EDGP@LIB                   DFSMSrmm Librarian Menu
Option ===>

0  OPTIONS    - Specify dialog options and defaults
1  VOLUME     - Display or Change volume information
2  ADDPP      - Add a Product
3  PRODUCTS   - Search for Products
4  OWNER      - Display or Change owner information
5  RACKS      - Manipulate Library Racks and Storage Location Bins
6  ADDVOL     - Add a volume to the library
7  SCRATCH    - Add SCRATCH volumes to the library
8  RELEASE    - Release volumes
9  CONFIRM    - Confirm librarian/operator actions
A  REQUEST    - Assign a user volume to an owner


Enter selected option or END command.  For more info., enter HELP or PF1.
```

Figure 4. DFSMSrmm Librarian Menu

Chapter 2. Implementing DFSMSrmm

This chapter describes tasks you need to perform to implement DFSMSrmm. We have identified some optional tasks that might not need to be performed for your installation. We recommend that you review all the steps in this chapter as well as information in the *z/OS DFSMS Migration* book before you begin implementing DFSMSrmm. The *z/OS DFSMS Migration* book describes steps required before you install DFSMSrmm.

If you are converting to DFSMSrmm from another tape management product, refer to the IBM Redbook *Converting to Removable Media Manager: A Practical Guide*, SG24-4998. This redbook helps customers understand the correspondence between DFSMSrmm terminology and strategy and that of their current tape management software product. If you have multiple MVS images or a shared-DASD complex, you must repeat several of these steps for each MVS image or complete. We provide recommendations for steps that should be repeated for each image.

Step 1: Preparing to Implement DFSMSrmm

Before using this book, you should have installed DFSMSrmm, along with the other DFSMS components, using SMP/E. Refer to the *z/OS Program Directory* you received with the product tape for complete installation instructions.

Recommendation: After you have installed DFSMSrmm using SMP/E, IPL your system without performing any DFSMSrmm implementation tasks and have DFSMSrmm take no part in removable media management. This is especially helpful if you are running another tape management product in production.

See “Appendix E. Evaluating Removable Media Management Needs” on page 407 for a checklist to help you plan for implementing DFSMSrmm.

Step 2: Running the IVP (Optional)

If this is the first time you are implementing DFSMSrmm, we recommend you use the supplied IVP to verify that DFSMSrmm has installed correctly. You can run the IVP at any time, for example, after installing maintenance on your system.

See “Appendix A. DFSMSrmm Installation Verification Procedures” on page 359 for the IVP procedures.

Step 3: Updating JES3 (Optional)

DFSMSrmm Samples Provided in SAMPLIB

- EDG3IIP1 Sample to Update IATIIP1
- EDG3LVVR Sample to Update IATLVVR
- EDG3UX29 Sample to Update IATUX29
- EDG3UX62 Sample to Update IATUX62
- EDG3UX71 Sample to Update IATUX71

© Copyright IBM Corp. 1992, 2001

If you use DFSMSrmm and have JES3-managed tape devices that are not in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver, continue with this step. Otherwise, skip this step because allocation and DFSMSdfp handle all mount and volume verification.

DFSMSrmm provides SMP/E USERMODs that you can apply to the standard supplied JES3 user exits and other JES3 modules. The USERMODs can be used to prevent JES3 from validating certain volume mounts, to update JES3 fetch and mount messages, and to enable the use of no label tape volumes with JES3. If you have installed DFSMSrmm on a JES3 system, you might want to apply the JES3 USERMODs as described in “Chapter 12. Running DFSMSrmm with JES3” on page 243. You must consider how applying a USERMOD might affect any locally-developed user exits.

Step 4: Updating Installation Exits

DFSMSrmm Samples Provided in SAMPLIB

- EDGUX100 Sample to Use the Installation Exit EDGUX100
- EDGUX200 Sample to Use the Installation Exit EDGUX200

DFSMSrmm Samples Provided in AEDGSRC1 or SMPSTS

- CBRUXCUA Programming Interface to EDGLCSUX
- CBRUXEJC Programming Interface to EDGLCSUX
- CBRUXENT Programming Interface to EDGLCSUX
- CBRUXVNL Programming Interface to EDGLCSUX
- EDGCVRSX Sample to Use the Installation Exit EDGUX100
- IGXMSGEX Programming Interface to EDGMSGEX

DFSMSrmm provides two sample installation exits, EDGUX100 and EDGUX200. You must install EDGUX100 and EDGUX200 if you want to use them. “Chapter 10. Using DFSMSrmm Installation Exits” on page 195 describes the functions that the DFSMSrmm installation exits provide and how to use the exits.

The installation exits that DFSMSrmm provides for IGXMSGEX and the OAM exits are implemented when DFSMS/MVS is installed. The installation exits that are installed for IGXMSGEX or the OAM exits replace any exits you had previously installed. You might need to modify your DFSMSrmm installation exits to provide the functions available in the exits you are currently using as well as provide functions required by DFSMSrmm. We recommend that you convert your code to run when called by the DFSMSrmm exits and that you modify the supplied exits to call your code.

Refer to:

- “Processing Fetch and Mount Messages: EDGMSGEX” on page 192 for details about the DFSMSrmm programming interface that you use with IGXMSGEX.
- “Managing System-Managed Tape Library Volumes: EDGLCSUX” on page 179 for details about the DFSMSrmm programming interface that you use with the OAM installation exits.

Step 5: Updating SYS1.PARMLIB Members

Update the following SYS1.PARMLIB members: IEFSSNxx and IKJTSOxx. Optionally, you can update SMFPRMxx, GRSRNLxx, and SCHEDxx. You should also ensure that IFAPRD00 is updated correctly during installation of DFSMS.

Perform this step once for each MVS image.

Updating IEFSSNxx

There are two changes to make in IEFSSNxx:

- Define a DFSMSrmm subsystem name to MVS
- Add the name of the subsystem interface initialization program, EDGSSSI, to fully enable DFSMSrmm

We recommend that you implement the changes in two steps. Define the DFSMSrmm system at this time as described in "Defining DFSMSrmm to MVS". Then you can add the name of the subsystem interface later as described in "Step 22: Initializing the DFSMSrmm Subsystem and Tape Recording" on page 52. If you make only this first change at this time, you can choose whether to start the DFSMSrmm procedure and choose a time to best suit your particular situation. If you implement both changes at once, DFSMSrmm rejects all tape mounts until the subsystem procedure is active or you use the EDGRESET utility to disable the interface.

Defining DFSMSrmm to MVS

Add an entry to IEFSSNxx to define the DFSMSrmm subsystem to MVS. Specify the DFSMSrmm subsystem name shown in Figure 5. Figure 5 shows where to place the subsystem name. Place the DFSMSrmm entry after the JES2 or JES3 entry and before the NetView® entry to ensure that NetView automation receives the write-to-operator messages once DFSMSrmm has updated them. Additionally, if you have any software identified as a subsystem that is dependent on open/close/end-of-volume processing, place the names after the DFSMSrmm entry. DFSMSrmm has no other dependencies on the sequence of subsystem names.

```
SUBSYS SUBNAME(JES2)              /* JES2 PRIMARY SUBSYSTEM START   */
  PRIMARY(YES)  START(YES)
SUBSYS SUBNAME(DFRM)              /* Name of the DFSMSrmm subsystem */
SUBSYS SUBNAME(AOPA)              /* Netview                        */
```

Figure 5. Defining DFSMSrmm to MVS through IEFSSNxx With Subsystem Inactive

where:

DFRM
Specifies the subsystem name. You can use any unique subsystem name, one to four characters long.

Although the subsystem name can be one to four characters long, the subsystem name must be four characters and must match the first four characters of the procedure name if:

- You have not added EDGSSSI, as described in "Step 22: Initializing the DFSMSrmm Subsystem and Tape Recording" on page 52, and you want DFSMSrmm to perform the EDGSSSI processing when it starts by replying RETRY to message EDG0103D.

  or

- You use the EDGRESET utility or

  ```
  S DFRMM,OPT=RESET
  ```

  and plan to restart DFSMSrmm without an IPL.

Run DFSMSrmm as a subsystem started under the JES2 or JES3 subsystem, rather than under the master subsystem. When choosing the DFSMSrmm subsystem name, the subsystem name must not exactly match the DFSMSrmm procedure name, unless you specify SUB=JES2 or SUBJ=JES3 on each START command. For example, if you use DFRM as the subsystem name, use DFRMM as the procedure name.

You must run DFSMSrmm under the JES2 or JES3 subsystem to:

- Use the DFSMSrmm NOTIFY function which automatically notifies volume and product owners when the volumes they own become eligible for release or when product volumes are added.
- Use the SYSOUT facilities like //SORTOUT DD SYSOUT=*.

Dynamically Adding the DFSMSrmm Subsystem

You can dynamically add the DFSMSrmm subsystem without an IPL. Use the MVS system command SETSSI to add the DFRM subsystem. Issue the SETSSI command from a console that has master authority or a console that has sufficient RACF authority.

To activate the DFSMSrmm subsystem, issue:

```
SETSSI ADD,SUBNAME=DFRM
```

Enabling DFSMSrmm and Tape Recording

You enable DFSMSrmm later, in “Step 22: Initializing the DFSMSrmm Subsystem and Tape Recording” on page 52. Refer to this section now if you are interested in the changes you will make later to IEFSSNxx to enable the DFSMSrmm tape recording interface.

Updating IKJTSOxx to Authorize DFSMSrmm Commands

Update IKJTSOxx to authorize RMM commands and utilities. Refer to *z/OS TSO/E Customization* if you use the TSO CSECT facility rather than IKJTSOxx for these updates.

To authorize the TSO command RMM, make the specifications as shown in Figure 6:

```
AUTHCMD NAMES(RMM)
```

Figure 6. Updating IKJTSOxx to Authorize RMM Commands

To authorize the DFSMSrmm utilities that you can use within TSO or call through the TSO Service Facility, make the specifications as shown in Figure 7 on page 27:

```
AUTHTSF NAMES(EDGHSKP
              EDGUTIL
              EDGRPTD
              EDGAUD)
AUTHPGM NAMES(EDGHSKP
              EDGUTIL
              EDGRPTD
              EDGAUD)
```

Figure 7. Updating IKJTSOxx to Call DFSMSrmm through TSO

To dynamically obtain the updated version of the IKJEFTxx member, use the TSO PARMLIB UPDATE(**) command in your TSO session.

Updating SMFPRMxx (Optional)

If you want DFSMSrmm security or audit SMF records, update the SMFPRMxx member to ensure that the DFSMSrmm SMF records are generated. You define the SMF record numbers in the DFSMSrmm parmlib member EDGRMMxx using the OPTION command SMFAUD operand for auditing records and SMFSEC operand for security records. For more information on these commands, see “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115.

Select two SMF record numbers in the range 128 through 255 that your installation is not currently using. Add your record numbers to the member as described in *z/OS MVS System Management Facilities (SMF)*.

Updating GRSRNLxx (Optional)

If you are not using global resource serialization (GRS) to control enqueues among sharing systems, you can skip updating GRSRNLxx.

If you have multiple systems connected with global resource serialization, decide now how you want GRS to handle the reserve on the control data set. Our recommendations for updating GRSRNLxx depend on the volume where the control data set resides, and if the volume contains critical data.

Recommendation: Convert the associated SYSTEMS enqueue to a local SYSTEM enqueue, while leaving the hardware reserve in effect, if the volume does not contain other critical data and if real reserves will not cause any shared DASD contention problems. This method gives slightly better DFSMSrmm performance.

Recommendation: Convert the RESERVE to a SYSTEMS enqueue if the volume contains other critical data and real reserves could impact other systems or cause DASD contention problems. If you do not change your GRSRNLxx parmlib member, DFSMSrmm still functions correctly; but any performance gain from using the real hardware reserve feature is negated by the additional unnecessary overhead of sending the global SYSTEMS enqueue around the GRS ring.

Use the same method for the SYSZVVDS resources. The SYSZRMM MASTER.RESERVE and SYSZVVDS resources must be treated the same to avoid potential lockouts between systems on these resources.

Converting the SYSTEMS Enqueue to a Local SYSTEM Enqueue

Add the reserve name to the global resource serialization exclusion list. This leaves the real hardware reserve in effect, and causes the associated SYSTEMS enqueue to be converted to a local SYSTEM one. Converting to a local SYSTEM enqueue can avoid the delay associated with sending the additional unnecessary enqueue

around the global resource serialization ring. Figure 8 shows how to implement this method.

```
RNLDEF RNL(EXCL) TYPE(SPECIFIC)
QNAME(SYSZRMM)
RNAME(MASTER.RESERVE)
```

Figure 8. Converting the SYSTEMS Enqueue to a Local SYSTEM Enqueue

Converting the RESERVE to a SYSTEMS Enqueue

Add the reserve name to the global resource serialization reserve conversion list. This will leave the global SYSTEMS enqueue in effect, and remove the real hardware reserve. Figure 9 shows how to convert the RESERVE to a SYSTEMS enqueue.

```
RNLDEF RNL(CON) TYPE(SPECIFIC)
QNAME(SYSZRMM)
RNAME(MASTER.RESERVE)
```

Figure 9. Converting the RESERVE to a SYSTEMS Enqueue

You must specify both the QNAME and RNAME as shown in Table 5 when converting the reserve. If you only specify the QNAME, *all* enqueues used by DFSMSrmm are converted and you will be unable to run DFSMSrmm on multiple systems.

Table 5. DFSMSrmm Resource Symbolic Names

Major Name	Minor Name	Resource	Scope
SYSZRMM	MASTER.RESERVE	DFSMSrmm control data set serialization	SYSTEMS
SYSZRMM	MHKP.ACTIVE	Serialize inventory management functions on the same DFSMSrmm subsystem	SYSTEM
SYSZRMM	RMM.ACTIVE	Ensure only one system run per MVS image	SYSTEM
SYSZRMM	BUFFER.CONTROL	Buffer management	STEP
SYSZRMM	EDGINERS.volser	Serialize volume labeling	SYSTEMS
SYSZRMM	SHUTDOWN	Serialize DFSMSrmm shutdown and refresh processing	SYSTEM
SYSZRMM	INACTIVE	Serialize DFSMSrmm activation enabling only a single WTOR to be issued to the operator	SYSTEM
SYSZRMM	EXIT_IS_ACTIVE	Exit recovery serialization	SYSTEM
SYSZRMM	EXIT_id_UNAVAIL	Exit recovery serialization; where id is the exit name	SYSTEM

See *z/OS MVS Planning: Global Resource Serialization* for additional information about global resource serialization.

Updating SCHEDxx (Optional)

Recommendation: Do not perform this step. If you update SCHEDxx, the DFSMSrmm started procedure is not enqueued on any of the data sets it allocates. Someone who is authorized to use these data sets could scratch them while DFSMSrmm is running without DFSMSrmm knowing about it. For example, DFSMSdss DEFRAG could move the journal while DFSMSrmm is active. If you specify NODSI on a PPT entry for a DFSMSrmm program, you must also take steps such as making the journal unmovable, to prevent the DFSMSrmm data sets from being moved while DFSMSrmm is active. See “Step 8: Updating the Procedure Library” on page 30 for information about the DD statements to include in the RMM started procedure. If you already have used SCHEDxx for DFSMSrmm, consider removing it.

Update SCHEDxx if you want to ensure that the parmlib data set named in the DFSMSrmm started procedure does not cause enqueue contention while DFSMSrmm is running. Update the Program Properties Table in SCHEDxx, as shown in Figure 10.

```
PPT   PGMNAME(EDGMAIN)
   NODSI
PPT   PGMNAME(EDGRESET)
   NODSI
```

Figure 10. Updating SCHEDxx

To update the SCHEDxx member dynamically, enter the following command from an MVS system console.

```
SET  SCH=xx
```

Ensuring DFSMSrmm is Enabled

IBM supplies a tailored SYS1.PARMLIB member, IFAPRD00, that enables the elements and features you ordered. Before you can use them, you must copy the contents of IDAPRD00 to an active IFAPRDxx member that you establish through the PROD parameter in IEASYSxx or the SET PROD operator command. The IFAPRD00 member is not active by default.

To update the IFAPRDxx member dynamically, use the following MVS system command.

```
SET  PROD=xx
```

For more information on IDAPRDxx, see *z/OS MVS Initialization and Tuning Reference*.

Step 6: Using the Problem Determination Aid Facility (Optional)

Perform this step once for each MVS image. You only need to perform this step if you want an external DASD record of trace data.

The problem determination aid (PDA) facility gathers DFSMSrmm processing information to enable analysis to pinpoint module flow and resource usage that is related to DFSMSrmm problems. The PDA facility is required for IBM service because it traces module and resource flow. The PDA facility consists of in-storage trace, optional DASD log data sets, EDGRMMxx parmlib member options, and operator commands to control tracing. See “Chapter 19. Using the Problem Determination Aid Facility” on page 343 for information about setting up the PDA facility.

Step 7: Setting Up DFSMSrmm Disposition Processing (Optional)

DFSMSrmm disposition processing is optional and provides support for:

- Providing operators with information to assist them in performing tasks like moving a tape to a specific location
- Generating sticky labels
- Updating the location where a volume resides

See “Chapter 20. Setting Up DFSMSrmm Disposition Processing” on page 347 for information about setting up DFSMSrmm disposition processing.

Step 8: Updating the Procedure Library

DFSMSrmm Sample Provided in SAMPLIB

- EDGDFRMM Sample to Create a Procedure in SYS1.PROCLIB

Perform this step once for each MVS image.

Create a procedure in SYS1.PROCLIB to start the DFSMSrmm subsystem address space. Figure 11 shows sample JCL.

```
//DFRMM PROC M=00,OPT=MAIN
//IEFPROC EXEC PGM=EDG&OPT.,PARM='&M',TIME=1440,REGION=4096K
//IEFPROC EXEC PGM=EDG&OPT.,PARM='&M',TIME=1440,REGION=40M
//PARMLIB DD   DDNAME=IEFRDER
//IEFRDER DD   DISP=SHR,DSN=SYS1.PARMLIB
//MASTER  DD   DISP=SHR,DSN=RMM.CONTROL.DSET
//JOURNAL DD   DISP=SHR,DSN=RMM.JOURNAL.DSET
//EDGPDOX DD   DISP=SHR,DSN=?UID..?HOSTID..RMMPDOX
//EDGPDOY DD   DISP=SHR,DSN=?UID..?HOSTID..RMMPDOY
//dispdd  DD   OUTPUT DEST=SYSTEMX,FORMS=LABEL,CLASS=L
```

Figure 11. Creating a Procedure in SYS1.PROCLIB

where:

DFRMM
Specifies the procedure name. You can use any procedure name, one to eight characters long, subject to the restriction documented under IEFSSNxx parmlib member.

M Allows you to specify a parmlib member suffix. `M=00` tells DFSMSrmm to use member EDGRMM00.

OPT

Allows you to specify:

`OPT=RESET` to disable the subsystem interface

`OPT=MAIN` to execute the DFSMSrmm subsystem

REGION

When you are determining the REGION size for the DFSMSrmm started procedure, the amount of virtual storage DFSMSrmm uses depends on the resources you have defined. DFSMSrmm might be affected by any REGION size controls or restrictions your systems might have. The sample DFRMM procedure specifies REGION=40M. This normally provides for all the private region below 16MB and 40MB above 16MB. Use the information provided here along with the known region size of your DFRMM started procedure to decide if you need to make any changes to the REGION size. You might need to change the value you specify on the DFRMM procedure for the REGION size.

PARMLIB DD

PARMLIB is an optional statement. Use the PARMLIB DD statement to identify the data set that contains DFSMSrmm startup parameters when you do not use the system parmlib data set 'SYS1.PARMLIB' or the system parmlib concatenation. If you do not code the PARMLIB DD statement, then do not code the IEFRDER DD statement because it is not required. See "Step 19: Starting DFSMSrmm" on page 45 for parameters you can specify with the START command if you specify the PARMLIB DD statement.

If you specify the parmlib data set in the DFSMSrmm procedure, the data set remains allocated while DFSMSrmm is active. If you do not specify the parmlib data set name, DFSMSrmm dynamically allocates PARMLIB to 'SYS1.PARMLIB'.

DFSMSrmm supports the use of the concatenated parmlib function of the MVS system.

Recommendation: Do not specify the PARMLIB or IEFRDER DD statement in the DFRMM procedure. Let DFSMSrmm dynamically allocate the PARMLIB to 'SYS1.PARMLIB' or use the concatenated parmlib support.

IEFRDER DD

IEFRDER is an optional statement. Use the IEFRDER DD statement to enable operators to specify PARMLIB DD keywords on the START command for the DFRMM procedure. If you do not code the IEFRDER DD and code the PARMLIB DD, you will not be able to specify a different parmlib data set name when starting the DFRMM procedure. If you do not code PARMLIB, it is not necessary to code the IEFRDER DD statement.

MASTER DD

MASTER is an optional statement that identifies the DFSMSrmm control data set name. If you code the MASTER DD statement to name the DFSMSrmm control data set, you cannot easily change the control data set name by switching to a different parmlib member. You must supply the control data set name in the DFSMSrmm EDGRMMxx parmlib member if you do not code the MASTER DD statement.

JOURNAL DD

JOURNAL is an optional statement. If you code the JOURNAL DD statement to name the DFSMSrmm journal data set, you cannot easily change the journal

name by switching to a different parmlib member. You must supply the journal data set name in the DFSMSrmm EDGRMMxx parmlib member if you do not code the JOURNAL DD statement and if you require journaling. You must catalog the journal.

EDGPDOX and EDGPDOY DD
EDGPDOX and EDGPDOY DD are required statements for external trace output recording. If you do not specify these DD statements, no logging of the PDA trace output is performed. ?UID. is the user id and ?HOSTID. is the MVS system image ID.

dispdd
dispdd is an OUTPUT JCL statement you code when you want to create label output data. The name of the output statement must match the name you specified in the DFSMSrmm EDGRMMxx parmlib OPTION DISPDDNAME operand as described in “Defining System Options: OPTION” on page 122. You can use any JCL keywords supported on the OUTPUT statement as described in *z/OS MVS JCL Reference*.

When you are determining the REGION size for the DFSMSrmm started procedure, the amount of virtual storage DFSMSrmm uses depends on the resources you have defined. DFSMSrmm might be affected by any REGION size controls or restrictions your systems might have. The sample DFRMM procedure specifies REGION=40M. This normally provides for all the private region below 16 MB and 40 MB above 16 MB. Use the information provided here along with the known region size of your DFRMM started procedure to decide if you need to make any changes to the REGION size. You might need to change the value you specify on the DFRMM procedure for the REGION size.

- The VSAM LSR buffer pool built by the DFSMSrmm subsystem for the control data set is obtained above 16 MB.

  DFSMSrmm builds an LSR buffer pool for the DFRMM started procedure, and also for the EDGUTIL utility batch address space, which has a pre-determined size. The LSR buffer pool is 800*data CISZ + 200*index CISZ. Assuming 10 240 for CDS data CISZ and 4096 for CDS index CISZ, this is 800*10 240+200*4 096=8.6 MB. If you use larger CI sizes more buffer space is required. For example, using a 24K CISZ, requires a 19.5 MB buffer size. We recommend that you calculate your required buffer space. If the buffer space is larger then 8.6 MB, add the difference to the 40 MB region size used by DFSMSrmm and use this value as the REGION size for the DFRMM started procedure.
- DFSMSrmm uses DFSORT during inventory management. Increasing the DFSMSrmm REGION size allows DFSORT to use storage rather than SORTWKxx DASD files. Using storage rather than DASD files can potentially decrease the time needed to run DFSMSrmm inventory management. If you decide to change the REGION size, we suggest 1 additional MB for every 2 000 data sets on private volumes.

If you decide to use EDGLABEL or EDGXPROC, you must update the procedure library to include them as well. See “Using the LABEL Procedure” on page 341 for information on the supplied EDGLABEL procedure. See “Replenishing Scratch Volumes in a System-Managed Library” on page 340 for information on the supplied EDGXPROC procedure.

Step 9: Assigning DFSMSrmm a RACF User ID

Perform this step once for each MVS image.

When running on a system with RACF installed, assign DFSMSrmm a RACF user ID by adding a definition to the RACF started procedures table, ICHRIN03, or in the RACF STARTED class. The RACF user ID can be the name of the DFSMSrmm procedure you created in “Step 8: Updating the Procedure Library” on page 30 or any installation-selected RACF user ID you specify. As data sets are created for use by the DFSMSrmm procedure, add the RACF user ID to the access list for the data sets. Table 6 lists the data sets to which DFSMSrmm requires access.

Table 6. Data Sets Requiring Access by the DFSMSrmm RACF User ID

DDNAMES	Access Required
ACTIVITY	Update
EDGPDOX	Alter
EDGPDOY	Alter
MASTER	Control
Parmlib member	Read
JOURNAL	Update
MESSAGE	Update
REPORT	Update
REPTEXT	Update

If you plan to use the DFSMSrmm procedures EDGXPROC, BACKUPPROC, or LABEL, you must define the procedures in ICHRIN03 or the STARTED class. For more information on updating ICHRIN03 or the RACF STARTED class, see *z/OS SecureWay Security Server RACF System Programmer's Guide*.

The DFSMSrmm procedures EDGXPROC and EDGBKUP require READ access to STGADMIN.EDG.HOUSEKEEP and ALTER access to the data sets specified in the BACKUP and JRNLBKUP DD statements. The LABEL procedure requires UPDATE access to STGADMIN.EDG.OPERATOR. If you are using the EDGRESET utility, you should make sure it has ALTER access to the STGADMIN.EDG.RESET.SSI access list. For additional information on authorization needed for the DFSMSrmm user ID, see “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.

To run DFSMShsm, ABARS, or Tivoli® Storage Manager with DFSMSrmm, you must define DFSMShsm, ABARS, and Tivoli Storage Manager procedure names to RACF. Add the name of the DFSMShsm procedure to the started procedures table ICHRIN03 or with the STARTED class. Also add the name of the ABARS procedure. See *z/OS DFSMShsm Storage Administration Guide* for information about defining the DFSMShsm and ABARS procedure names.

Note: Any user ID that requires RMM services and makes use of OPERATIONS or privileged attributes must be defined to RACF.

If you are using an equivalent security product, review the RACF-related information to determine the changes that might be required to run DFSMSrmm with the equivalent security product.

Step 10: Defining Parmlib Member EDGRMMxx

Perform this step once for each MVS image.

Create a parmlib member EDGRMMxx definition for DFSMSrmm. The member name is in the form EDGRMMxx, where xx is a two character alphanumeric suffix of your choice. The default is EDGRMM00. A sample parmlib member is available as EDGIVPPM in SAMPLIB.

Parmlib member EDGRMMxx contains the installation options for DFSMSrmm. See "Chapter 7. Using the Parmlib Member EDGRMMxx" on page 115 for information about the options you can define in the parmlib member. Using EDGRMMxx, you can:

- Define system options, such as the date format for reports and messages, and the mode in which DFSMSrmm runs
- Prevent a range of tapes from being used on specific systems
- Define pools, such as the range of shelves to use for a pool and whether a pool has RACF tape profile processing
- Tailor mount messages, such as the position of the volume serial number and identifier
- Define security classes for data sets and volumes
- Control the use of bypass label processing for tape volumes
- Define storage locations
- Define controls for running DFSMSrmm vital record processing to apply retention and movement policies

The RACF ID associated with the DFSMSrmm started procedure requires READ access to the parmlib member EDGRMMxx data set.

Table 7 shows several ways to define the parmlib member. We recommend specifying the parmlib member EDGRMMxx as a member of SYS1.PARMLIB or the PARMLIB concatenation. If you follow this recommendation you can use the DFSMSrmm startup parameters to avoid stopping and restarting DFSMSrmm. For example, you can use the modify command (F DFRMM,M=xx) to implement updates to the data set and avoid stopping and restarting DFSMSrmm. You can also restart DFSMSrmm using another data set with parameters to implement changes.

Table 7. Creating DFSMSrmm Parmlib Definitions

Way to Define	Example
Member of SYS1.PARMLIB	SYS1.PARMLIB(EDGRMMxx)
Member of PARMLIB concatenation	SYSC.PARMLIB(EDGRMMxx)
Member of separate data set	MY.PARMLIB(EDGRMMxx)
Separate sequential data set	USER.PARMLIB

Step 11: Tailoring Parmlib Member EDGRMMxx

Perform this step once for each MVS image.

Tailor the options for parmlib member EDGRMMxx. To see the options and parmlib member examples, see “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115.

Step 12: Creating the DFSMSrmm Control Data Set

DFSMSrmm Sample Provided in SAMPLIB

- DFSMSrmm EDGJMFAL Sample JCL for Allocating the Control Data Set

Perform this step once for each shared-DASD complex, or for each MVS image.

Create the DFSMSrmm control data set, a VSAM key-sequenced data set that contains the complete inventory of the removable media library. DFSMSrmm records all changes made to the inventory, such as adding or deleting volumes, in the control data set.

You can create the control data set for each shared-DASD complex or for each MVS image. We recommend that you create one for each shared-DASD complex. Sharing the control data set across systems allows DFSMSrmm to keep all tape usage information in one place.

If you have a control data set for each MVS image, each control data set only records information for that system. DFSMSrmm cannot track tapes that are accidentally moved to another system that has a different control data set.

For each shared-DASD complex, create one control data set on the main, or most active, system in your complex. Multiple systems that share DASD can use the same control data set.

DFSMSrmm requires CONTROL access to the control data set.

Note:

- The control data set cannot be a SYS1. data set if the control data set is to be shared.
- Batch LSR cannot be used with the DFSMSrmm control data set.

To create the control data set on the system, perform the following steps:

1. Calculate DASD space for the control data set.
2. Place the control data set.
3. Allocate space for the control data set.
4. Protect the control data set.
5. Initialize the control data set for DFSMSrmm subsystem use by running the EDGUTIL utility.
6. Plan to back up the control data set.

Calculating DASD Space for the DFSMSrmm Control Data Set

Table 8 helps you to calculate DASD space requirements for the DFSMSrmm control data set. To determine the number of resources in the library, such as the number of software products you have, see your answers to “Appendix E. Evaluating Removable Media Management Needs” on page 407.

Table 8. DFSMSrmm Control Data Set DASD Space Requirements

Control Data Set Content	DASD Space
Control record	1 MB (MB equals approximately 1 000 000 bytes)
Data sets	420 KB (KB equals approximately 1000 bytes) for every 1000 data sets
Shelf locations in the library that do not contain volumes	140 KB for every 1000 shelf locations
Shelf locations in storage locations	140 KB for every 1000 shelf locations
Owners	38 KB per 1000 volumes
Software products, average five volumes per product	420 KB for every 1000 software products
Volumes	1 MB for every 1000 volumes
Vital record specifications	212 KB for every 1000 vital record specifications

After calculating the previous figures, increase the total by approximately 50% for free space in the VSAM key-sequenced data set. For example, if the calculated size is 3000 KB, increase it by 50% to 4500 KB to allow for free space. Use this value in the access method services KILOBYTES parameter on the DEFINE CLUSTER command shown in Figure 12 on page 37.The maximum size for the journal is 65535 tracks.

Placing the DFSMSrmm Control Data Set

If the volume where you place the control data set is system-managed, select a storage class name that has the GUARANTEED SPACE attribute, and substitute it in the example for the STORAGECLASS parameter in Figure 12 on page 37. If it is not system-managed, remove the STORAGECLASS parameter.

If you are running DFSMSrmm on more than one system, create the control data set on a shared volume, ensuring that all systems have access to it. The control data set must be cataloged in a shared user catalog. Put the control data set on a different volume than the journal, which is also shared. Separating the two data sets optimizes data integrity, since the journal is a copy of changes made to the control data set.

If you plan to use DFSMSdss to back up the control data set, place the control data set on a concurrent copy capable volume.

Note: To avoid a potential deadlock on the volume where the DFSMSrmm control data set is placed, you should consider the other data that you place on the volume. A deadlock can occur when a program other than DFSMSrmm reserves the volume where the control data set resides and requests DFSMSrmm for service. If the DFSMSrmm control data set requires additional extents because of the request, then a deadlock can occur.

DFSMSrmm uses RESERVE/RELEASE to control access to the control data set and ensure interity. If your installation is using global resource serialization, see “Step 4: Updating Installation Exits” on page 24 and “Updating GRSRNLxx (Optional)” on page 27.

Place the DFSMSrmm control dataset and journal on the highest performing DASD in your installation. DFSMSrmm can benefit from features like caching and DASD fastwrite and support for concurrent copy. Consider using the storage class attribute AVAILABILITY=CONTINUOUS for the control data set. This does not remove the need for journaling in DFSMSrmm, however, as the journal is required when reconstructing the control data set from backups.

Allocating Space for the Control Data Set

When you allocate the DFSMSrmm control data set index and data components, the index and data components must be on the same volume because DFSMSrmm does not support them being allocated on separate volumes.

Use JCL similar to that shown in Figure 12 to allocate space for the control data set on the master system:

```
//IDCAMS   EXEC PGM=IDCAMS,REGION=1M
//SYSPRINT DD   SYSOUT=*
//DASD     DD   DISP=SHR,UNIT=SYSDA,VOL=SER=8E5U04
//SYSIN    DD   *
 DEFINE CLUSTER(NAME(RMM.CONTROL.DSET) -
                FILE(DASD) -
                FREESPACE(20 20) -
                KEYS(56 0) -
                REUSE -
                RECSZ(512 9216) -
                SHR(3 3) -
                KILOBYTES(4500 1500) -
                STORAGECLASS(gspace) -
                VOLUMES(8E5U04)) -
           DATA(NAME(RMM.CONTROL.DSET.DATA) -
                CISZ(10240)) -
          INDEX(NAME(RMM.CONTROL.DSET.INDEX) -
                CISZ(2048) -
                REPLICATE)
/*
```

Figure 12. Allocating DASD Space for the Control Data Set

Figure 13 on page 38 shows the JCL you can use for allocating DASD space for the control data set when DASD cache is in use. Calculate the size of the index using 10% of the space you calculated for the control data set. Calculate the data size using 90% of the control data set size.

```
//IDCAMS   EXEC PGM=IDCAMS,REGION=1M
//SYSPRINT DD   SYSOUT=*
//DASD     DD   DISP=SHR,UNIT=SYSDA,VOL=SER=8E5U04
//SYSIN    DD   *
 DEFINE CLUSTER (NAME(RMM.PX11.CDS) -
                 FILE(DASD) -
                 FREESPACE(20 20) -
                 KEY(56 0) -
                 REUSE -
                 RECSZ(512 9216) -
                 SHR(3 3) -
                 STORCLAS(gspace) -
                 VOLUMES(8E5U04)) -
        DATA     (NAME(RMM.PX11.CDS.DATA) -
                 KILOBYTES(14381 1438) -
                 CISZ(10240) -
                 FILE(DASD)) -
        INDEX    (NAME(RMM.PX11.CDS.INDEX) -
                 CISZ(2048) -
                 KILOBYTES(1412 141) -
                 FILE(DASD))

/*
```

Figure 13. Allocating DASD Space for the Control Data Set when DASD Cache Is in Use

where:

KILOBYTES
Is the space value you calculated in “Calculating DASD Space for the DFSMSrmm Control Data Set” on page 36. Choose a secondary space value that allows the control data set to grow in the future.

NAME()
Specifies the name of the control data set. Use the same name you assigned in the parmlib member EDGRMMxx under OPTION DSNAME(name) or in the MASTER DD statement in the DFSMSrmm procedure.

FREESPACE
Specifies how much free space VSAM reserves in the data set for future additions. For more information on changing the FREESPACE values, see *z/OS DFSMS: Using Data Sets*.

We recommend that you do not specify REPLICATE if DASD cache is in use.

Protecting the Control Data Set

Protect the control data set by ensuring that a RACF DATASET profile protects it. To prevent inadvertent updates to the control data set, specify a RACF universal access of NONE. Give CONTROL access only to users authorized to perform functions independent of the subsystem, such as restoring and reorganizing the control data set and using program EDGUTIL. Give CONTROL access to the RACF user ID assigned to the DFSMSrmm procedure in “Step 9: Assigning DFSMSrmm a RACF User ID” on page 33.

Initializing the Control Data Set

To initialize the control data set, run the DFSMSrmm EDGUTIL utility. Figure 14 on page 39 is sample JCL you can use to create the control data set.

```
//EDGUTIL EXEC PGM=EDGUTIL,PARM='CREATE'
//SYSPRINT DD SYSOUT=*
//MASTER   DD DSN=RMM.CONTROL.DSET,DISP=SHR
//SYSIN    DD *
CONTROL
/*
```

Figure 14. Initializing the Control Data Set

See “Creating or Updating the Control Data Set Control Record” on page 303 for additional information on SYSIN values you can use.

Backing Up the Control Data Set

Plan to use the DFSMSrmm utilities EDGBKUP and EDGHSKP to back up the control data set. You can automatically back up the control data set as part of inventory management if you use EDGHSKP which also clears the journal. You can also use the parmlib OPTION command JOURNALFULL operand threshold value to start a backup procedure.

Back up the control data set to DASD. You can also back up the control data set to tape using DFSMSdss. Once the backup is complete, you can move or copy the backup file to any storage medium. We recommend that you keep the latest backup available on DASD to provide the fastest recovery time for the control data set.

See “Backing Up the Control Data Set” on page 278 for more information.

Step 13: Creating the Journal

DFSMSrmm Sample Provided in SAMPLIB

- EDGJNLAL Sample JCL for Allocating the Journal

To create the journal:
1. Calculate DASD space for the journal.
2. Place the journal.
3. Allocate space for the journal.
4. Protect the journal.
5. Plan to back up the journal.

Perform Step 13 once for each shared-DASD complex or MVS image, depending on how you created the control data set. We recommend that you create one control data set and one journal for each shared-DASD complex.

The journal contains a record of all changes made to the control data set since the last backup. We recommend that you create it and use it to forward recover changes made since the last backup. Each time the control data set is backed up successfully using the EDGHKSP utility, the journal data set is cleared.

DFSMSrmm requires UPDATE access to the journal. The journal cannot be an extended sequential data set.

You should plan to back up the journal and maintain multiple generations of it. See “Chapter 13. Performing Inventory Management” on page 247 for additional information.

Calculating DASD Space for the Journal

Table 9 helps you to calculate DASD space requirements for the journal. To determine the number of resources in your library, such as the number of scratch mounts that you have, see your answers to “Appendix E. Evaluating Removable Media Management Needs” on page 407. Base the following calculations on your requirements from one backup to the next. To ensure that the journal has enough space when there is an unexpected increase in tape activity, we recommend that you increase the calculated amount by 50% or more.The maximum journal size is 65 535 tracks.

Table 9. DFSMSrmm Journal DASD Space Requirements

Journal Content	DASD Space
Changes by users	1.5 KB for each change made
Data sets	1.5 KB for each data set retained by a vital record specification
Data sets no longer retained by a vital record specification	1.5 KB for each data set no longer retained by a vital record specification
Expiring volumes	1.5 KB for each expiring volume
Non-scratch mounts	6.7 KB for each mount
Scratch mounts	8.3 KB for each mount
Volumes	1.5 KB for each volume retained by a vital record specification
Volume checked in/out	2.6 KB for each volume in or out of the library
Volumes returned to scratch	3.0 KB for each volume returned to scratch
Volumes to and from storage locations	3.5 KB for each volume moved to or from a storage location
Volumes no longer retained by a vital record specification	1.5 KB for each volume that has not reached its expiration date and is no longer retained by a vital record specification
Volumes that are exported or imported	1.5 KB for each logical volume exported or imported
Vital record specifications	1.3 KB for each vital record specification created

Convert the final figure into a space allocation. The journal has a record format of variable-length blocked records. You do not need to specify the record format information when allocating the journal, because DFSMSrmm sets the correct values when it opens the journal data set.

To calculate the space required, divide the total KB of space by 4, as allocation will be by average record size using a 4 K value. This calculation gives you the number to use in the space allocation (SPACE=) shown in Figure 15 on page 41.

Placing the Journal

Place the journal on a different volume than the DFSMSrmm control data set. If the selected volume is system-managed, use the STORCLAS parameter as shown in Figure 15 on page 41, and select a storage class with the GUARANTEED SPACE attribute. By using the GUARANTEED SPACE attribute, you ensure that the journal

is allocated to a specific volume. This volume is different than the one on which the control data set resides. Remove the STORCLAS parameter if the volume is not system-managed.

Place the DFSMSrmm journal on the highest performing DASD in your installation. DFSMSrmm can benefit from features like caching and DASD fastwrite and support for concurrent copy. Consider using the storage class attribute AVAILABILITY=CONTINUOUS for the journal.

Systems sharing a control data set must also share the same journal.

Care must be used when moving the journal if the NODSI option is specified in SCHEDxx. If the option is used, do not move the journal while DFSMSrmm is active.

Allocating Space for the Journal

Figure 15 shows JCL for allocating space for the journal.

```
//JOURNAL EXEC PGM=IEFBR14
//SYSPRINT DD  SYSOUT=*
//JOURNAL  DD  DISP=(NEW,CATLG),DSN=RMM.JOURNAL.DSET,
//             UNIT=SYSDA,VOL=SER=volser,STORCLAS=store_class,
//             AVGREC=U,SPACE=(4096,(pp))
```

Figure 15. Allocating Space for the Journal

where:

pp Specifies the calculated primary space.

DSN=
Specifies the name of the journal. Use the same name you assigned in the parmlib member EDGRMMxx for OPTION JRNLNAME(name) or in the JOURNAL DD statement in the DFSMSrmm procedure.

SPACE=(4096,(pp))
Specifies the space allocation for the journal. Use the value you calculated in “Calculating DASD Space for the Journal” on page 40.

You must catalog the journal.

You do not have to specify any DCB information for the data set because the required values are set when DFSMSrmm opens the data set. Any conflicting values that you supply are overridden.

You can create the journal in multiple extents, but increases in size are not permitted once DFSMSrmm uses the data set. If you specify a secondary space allocation for the data set, DFSMSrmm ignores it.

Protecting the Journal

Protect the journal by ensuring that a RACF DATASET profile protects it. To prevent inadvertent updates to the journal, specify a RACF universal access of NONE. Give READ access only to users authorized to perform functions independent of the subsystem, such as restoring and reorganizing the control data set. Give UPDATE access to the RACF user ID assigned to the DFSMSrmm procedure in “Step 9: Assigning DFSMSrmm a RACF User ID” on page 33.

Backing Up the Journal

Plan to use the DFSMSrmm utilities EDGBKUP and EDGHSKP to back up the journal. You can automatically back up the journal as part of inventory management if you use EDGHSKP which also clears the journal.You can also use the parmlib OPTION JOURNALFULL to automatically start a backup procedure. DFSMSrmm uses IDCAMS to back up the journal.

Back up the journal to DASD. Once the backup is complete, you can move or copy the backup file to any storage medium. Be sure to maintain multiple generations of the journal.

Step 14: Authorizing Users

Perform this step once for each shared-DASD complex.

Refer to “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 to authorize your users to DFSMSrmm resources.

Step 15: Making the DFSMSrmm ISPF Dialog Available to Users

Modify the ISPF environment so you can run the DFSMSrmm ISPF dialog. Use one of the following techniques to make the dialog available:

- Concatenate the DFSMSrmm target ISPF libraries with your existing ISPF libraries and use one of the following methods:
  1. Add DFSMSrmm to an ISPF dialog as described in “Adding DFSMSrmm to an ISPF Selection Panel”.
  2. Use the method supplied by DFSMS/MVS. DFSMSrmm is selection option ’R’ from the ISMF primary option menu.
  3. Use the RMMISPF EXEC to enter the dialog.
- Use the ISPF LIBDEF facility to make the DFSMSrmm target ISPF libraries available to your users, and use the EDGRMLIB EXEC to enter the dialog.

  If you are using the LIBDEF facility and you are not using the same target library names as listed in the *OS390 Program Directory* and *ServerPac: Installing Your Order*, you must modify the EDGRMLIB EXEC or produce your own similar exec or CLIST.

Adding DFSMSrmm to an ISPF Selection Panel

You can add a selection to an ISPF selection panel so that users can choose DFSMSrmm. To add the selection:

1. Add a selection for DFSMSrmm to the body of the chosen ISPF selection panel. For example, add:

   ```
   R  DFSMSrmm    Invoke DFSMSrmm
   ```

2. Add one of the following statements to the ZSEL processing list in the)PROC section of the chosen ISPF panel:
   - If you are not using LIBDEF:

     ```
     R,'CMD(%RMMISPF) NEWAPPL(EDG)'
     ```

   - If you are using LIBDEF:

     ```
     R,'CMD(%EDGRMLIB)'
     ```

Figure 16 on page 43 shows the ISPF Utility Selection Menu with step 1 and 2 changes made. LIBDEF was not used:

```
%------------------------  UTILITY SELECTION MENU  ---------------------
%OPTION  ===>_ZCMD
%
%    1 +LIBRARY    - Compress or print data set.  Print index listing.
+                     Print, rename, delete, or browse members
%    2 +DATASET    - Allocate, rename, delete, catalog, uncatalog, or
+                     display information of an entire data set
%    3 +MOVE/COPY  - Move, copy, or promote members or data sets
%    4 +DSLIST     - Print or display (to process) list of data set names
+                     Print or display VTOC information
%    5 +RESET      - Reset statistics for members of ISPF library
%    6 +HARDCOPY   - Initiate hardcopy output
%    8 +OUTLIST    - Display, delete, or print held job output
%    9 +COMMANDS   - Create/change an application command table
%   10 +CONVERT    - Convert old format menus/messages to new format
%   11 +FORMAT     - Format definition for formatted data Edit/Browse
%   12 +SUPERC     - Compare data sets (Standard dialog)
%   13 +SUPERCE    - Compare data sets (Extended dialog)
%   14 +SEARCH-FOR - Search data sets for strings of data
%    R +DFSMSrmm   - Invoke DFSMSrmm
)INIT
  .HELP = ISR30000
)PROC
  &ZSEL = TRANS( TRUNC (&ZCMD,'.')
                1,'PGM(ISRUDA) PARM(ISRUDA1)'
                2,'PGM(ISRUDA) PARM(ISRUDA2)'
                3,'PGM(ISRUMC)'
                4,'PGM(ISRUDL) PARM(ISRUDLP)'
                5,'PGM(ISRURS)'
                6,'PGM(ISRUHC)'
                8,'PGM(ISRUOLP)'
                9,'PANEL(ISPUCMA)'
               10,'PGM(ISRQCM) PARM(ISRQCMP)'
               11,'PGM(ISRFMT)'
               12,'PGM(ISRSSM)'
               13,'PGM(ISRSEPRM) NOCHECK'
               14,'PGM(ISRSFM)'
               R,'CMD(%RMMISPF) NEWAPPL(EDG)'
              ' ',' '
               *,'?' )
  &ZTRAIL = .TRAIL
)END
```

Figure 16. Adding DFSMSrmm to ISPF

Modifying an ISPF Selection Panel

You can modify the selection so that only the USER option of the DFSMSrmm dialog is available to the majority of end users.

- If you are not using LIBDEF, add to the)PROC section:

  ```
  R,'CMD(%RMMISPF USER) NEWAPPL(EDG)'
  ```

- If you are using LIBDEF, modify the supplied EDGRMLIB EXEC to include the USER parameter on the RMMISPF EXEC call.

  For example, enter the following REXX statement to replace the one supplied in EDGRMLIB.

  ```
  address "ISPEXEC" "SELECT CMD(%RMMISPF USER) NEWAPPL(EDG) PASSLIB"
  ```

Make the DFSMSrmm panel library, tables, skeletons, messages, and REXX execs available to users. If you are not using LIBDEF, Table 10 on page 44 shows the names of the default libraries that you concatenate to the DD statements in the

TSO logon procedure or a user-supplied start-up CLIST. If you are using LIBDEF, the EDGRMLIB EXEC allocates these default libraries to the user. If you changed the names of the target libraries on your system, modify the EDGRMLIB exec to contain the new library names.

Table 10 lists the DFSMSrmm libraries by the default target names.

Table 10. Default Libraries to Concatenate

DFSMSrmm Data Set Name	DD Statement	Content
SYS1.SEDGEXE1	SYSPROC (or SYSEXEC)	REXX execs
SYS1.SEDGMENU	ISPMLIB	English messages
SYS1.SEDGPENU	ISPPLIB	English panels
SYS1.DGTSLIB	ISPSLIB	Skeletons
SYS1.DGTTLIB	ISPTLIB	Tables

The target library SYS1.SEDGEXE1 has a fixed-block record format. The SYS1.DGTSLIB library and the SYS1.DGTTLIB library are shared with other DFSMS/MVS components.

Use the ISPF ISPPREP facility to build preprocessed versions of the panels. For more information on using ISPPREP, see *z/OS ISPF User's Guide Volume I*

Step 16: Making TSO HELP Information Available to Users

DFSMSrmm provides online help for the RMM TSO command. The help information is, by default, installed into the SYS1.SEDGHLP1 data set, although this can be changed by you during the SMP/E installation process.

To use the help information, copy the contents of SYS1.SEDGHLP1 to SYS1.HELP or concatenate the library to the other help libraries on the SYSHELP DD statement. You can update the TSO logon procedure or use the TSO ALLOCATE command. Figure 17 shows how to update the TSO logon procedure.

```
//SYSHELP  DD DSN=SYS1.HELP,DISP=SHR
//         DD DSN=SYS1.SEDGHLP1,DISP=SHR
```

Figure 17. Updating the TSO Logon Procedure

Step 17: Restarting MVS with DFSMSrmm Implemented

You are ready to start the system with DFSMSrmm implemented. You cannot restart MVS without an IPL. You can, however, avoid an IPL when:

- Changing subsystem name information in IEFSSNxx
- Setting SMF information in SMFPRMxx
- Changing GRS RNL definitions in GRSRNLxx
- Making changes to the PPT in SCHEDxx
- Using the PARMLIB UPDATE command to implement changes to IKJTSOxx

If you performed an IPL during Step 1, described in "Step 1: Preparing to Implement DFSMSrmm" on page 23, you have to re-IPL only if you cannot dynamically implement changes to the MVS system parmlib members or modified installation exits. You must re-IPL with CLPA to include new levels of DFSMSrmm code that have LPALIB as the target library.

Step 18: Tailoring DFSMSrmm Set Up

At this time, you must perform some additional set up for some of the DFSMSrmm functions. See *z/OS DFSMS Migration* for information about steps that you need to perform prior to installing DFSMSrmm.

See these sections for more information.

- Using volumes with special expiration dates, see “Managing Volumes with Special Dates” on page 70.
- Using volumes with duplicate volume serial numbers, see “Managing Duplicate or Undefined Volume Serial Numbers” on page 73.
- Using DFSMSrmm to control tape label types that can be used on volumes, see “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.
- Enabling the use of no label output for scratch volumes with JES3, see “Chapter 12. Running DFSMSrmm with JES3” on page 243.
- Synchronizing the DFSMSrmm control data set and other user catalogs, see “Running DFSMSrmm Catalog Synchronization” on page 257.
- Enabling DFSMSrmm stacked volume support, see “Setting up DFSMSrmm Stacked Volume Support” on page 307.
- Managing volumes using ACS routines, see “Using Storage Groups for DFSMSrmm Scratch Pooling” on page 63.

Step 19: Starting DFSMSrmm

Set the OPMODE operand in parmlib member EDGRMMxx to M to start DFSMSrmm in manual mode. Tape mounts are processed as they were before you began implementing DFSMSrmm. Refer to “Defining System Options: OPTION” on page 122 for information about setting OPMODE. See *z/OS DFSMSrmm Guide and Reference* for information about operator procedures.

Then, issue the MVS START command to start the DFSMSrmm subsystem, as shown in Figure 18:

```
S DFRMM,M=xx,SUB=jesp
```

Figure 18. Starting DFSMSrmm

where:

DFRMM
Specifies the procedure name.

M=xx
Specifies your chosen parmlib member name suffix.

SUB=jesp
This is an optional keyword to identify the name of the job entry subsystem. DFSMSrmm must not run under the MSTR subsystem. If the DFSMSrmm procedure name you use matches the subsystem name in IEFSSNxx as described in “Updating IEFSSNxx” on page 25, you must specify the SUB keyword when starting the DFSMSrmm procedure. jesp is the procedure name of your job entry subsystem and can be specified as SUB=JES3 or SUB=JES2.

If your DFSMSrmm procedure has a PARMLIB DD statement with DDNAME=IEFRDER, there are several other parameters you can specify with the

START command. You can specify keyword parameters that are supported on a DD statement. For example, you can specify DSN= to override the control data set name on the IEFRDER statement, as shown in Figure 19:

```
S DFRMM.name,M=xx,DSN=parmlib_name
```

Figure 19. Starting DFSMSrmm with Additional Parameters

where:

name
Specifies a name other than DFRMM by which you can call the DFRMM procedure. You can then use this name on STOP and MODIFY commands.

M=xx
Specifies a specific parmlib member with which DFSMSrmm should be started instead of the default parmlib member.

DSN=parmlib_name
Specifies an alternative data set name to be used as a parameter for this restart of the DFSMSrmm subsystem.

DFSMSrmm is now running in manual mode.

Stopping DFSMSrmm

You can stop the DFSMSrmm subsystem with the MVS STOP command, as shown in Figure 20:

```
P DFRMM
```

Figure 20. Stopping DFSMSrmm

If the operator defers the reply to the WTORs, DFSMSrmm shutdown might hang until the operator enters a reply. If shutdown is delayed, DFSMSrmm issues message EDG0154I to notify the operator that action is required.

When DFSMSrmm is stopped:

- DFSMSrmm completes any requests being processed at the time DFSMSrmm is stopped.
- DFSMSrmm completes any requests accepted by DFSMSrmm but that are currently waiting to be processed, except for requests to start DFSMSrmm inventory management. DFSMSrmm fails requests to start DFSMSrmm inventory management.
- If DFSMSrmm is already quiesced, DFSMSrmm does not process the waiting requests. DFSMSrmm issues message EDG1105I indicating that the requests are still waiting to be processed. If any of the requests are for catalog activity notifications, DFSMSrmm provides additional message text in message EDG1106I. DFSMSrmm issues a WTOR EDG1107D with options to STOP, QUIESCE, RESTART DFSMSrmm with the same parmlib member or RESTART DFSMSrmm with a new parmlib member.
- DFSMSrmm fails new requests with the RMM not active reason.

To stop DFSMSrmm and still allow tapes to be used, issue the commands shown in Figure 21 to disable the DFSMSrmm subsystem interface until the next time you IPL or start the DFSMSrmm subsystem.

```
S DFRMM,OPT=RESET
P DFRMM
```

Figure 21. Disabling the DFSMSrmm Subsystem Interface

Before DFSMSrmm disables the subsystem interface, it ensures the user who made the request is authorized. To disable the DFSMSrmm subsystem interface using the RESET option, you must have a security profile in place. If your installation does not have RACF or an equivalent security product installed, DFSMSrmm allows the reset request. In order to control the request, you can write a RACROUTE exit to test for the security profile and return an acceptable return code. See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for additional information.

Tell the operator to reply to any DFSMSrmm WTORs issued between issuing the commands shown in Figure 21. The operator must reply to any DFSMSrmm WTORs before entering the STOP command. If the RESET option is used to allow tape usage to continue, the operator should first enter the command:

```
S DFRMM,OPT=RESET
```

The operator should reply to the outstanding WTORs and then enter the STOP command. If the operator defers the reply to the WTORs, DFSMSrmm shutdown might hang until the operator enters a reply. If shutdown is delayed, DFSMSrmm issues message EDG0154I to notify the operator that action is required.

Quiescing DFSMSrmm

When you quiesce DFSMSrmm:

- DFSMSrmm completes requests that are being processed when the quiesce is requested. Note that DFSMSrmm might fail the request if manual recovery is to be performed or if there are I/O errors on the control data set.
- Any requests accepted by DFSMSrmm are left on work queues until DFSMSrmm recovery and refresh is completed.
- DFSMSrmm fails any new requests with an I/O error during manual recovery or RMM not ACTIVE when DFSMSrmm is quiesced by command.
- In a multi-host environment, conditions, which result in an automatic quiesce of DFSMSrmm (such as control data set errors from which DFSMSrmm cannot automatically recover). cause the quiesce on all hosts sharing the control data set. Only after all hosts have successfully quiesced can the control data set be recovered. Manually issuing a DFSMSrmm quiesce affects only the host on which you issue the command. If you want all hosts quiesced, you must issue the command on each host that is sharing the control data set.

To quiesce DFSMSrmm, the operator should issue the command shown in Figure 22 on page 48. Issuing the command quiesces the subsystem, allows DFSMSrmm to deallocate the control data set and the journal, and allows recovery processing to be performed.

```
MODIFY DFRMM,QUIESCE
```

Figure 22. Quiescing the DFSMSrmm Subsystem Interface

Restarting DFSMSrmm

To restart DFSMSrmm after it has been quiesced or to change the DFSMSrmm options, the operator can issue the command specified with a member name.

```
MODIFY DFRMM,M=xx
```

Checking DFSMSrmm Status

To obtain a list of the number of requests waiting to be processed and the number of active requests, and to determine if DFSMSrmm is active or quiesced, the operator can issue the command:

```
F DFRMM,QUERY ACTIVE
```

The operator can also use the abbreviations Q ACT and Q A.

Step 20: Defining Resources

The following sections help you define these resources to DFSMSrmm: shelves, volumes, owners, and vital record specifications. For detailed information about how to perform these tasks, see *z/OS DFSMSrmm Guide and Reference*. If you are migrating to DFSMSrmm, refer to *Converting to Removable Media Manager: A Practical Guide*, SG24-4998 and the DFSMSrmm samplib documentation member, EDGCMM01.

Defining Shelf Locations

Shelf locations in the removable media library are called rack numbers. Shelf locations in storage locations are called bin numbers. To define shelf locations to DFSMSrmm, use RMM ADDRACK or ADDBIN subcommands or the DFSMSrmm ISPF dialog.

You can optionally define a rack number for every volume that you plan to define to DFSMSrmm. You do not have to define all possible shelf locations now because you can add them at any time. If you want to logically divide the library into pools, see “Organizing the Library by Pools” on page 55.

If volumes are designated for use in an automated tape library dataserver, you must define rack numbers for the volumes when the external and internal volume serial numbers are not the same.

You can optionally define a bin number for every shelf location in a storage location. For shelf locations in DFSMSrmm built-in storage locations, LOCAL, DISTANT, and REMOTE, you provide an initial count and DFSMSrmm assigns the bin numbers.

You can use the LOCDEF command in the EDGRMMxx member of parmlib to define additional locations to DFSMSrmm and to further define existing locations. See “Defining Storage Locations: LOCDEF” on page 115 and “Chapter 6. Managing Storage Locations” on page 107. For shelf locations in installation defined storage locations, provide a count and an initial bin number.

Defining Owner Information to DFSMSrmm

Use the RMM ADDOWNER subcommand or the Add Owner Details panel in the DFSMSrmm ISPF dialog to define owner information to DFSMSrmm. You must define owner information to DFSMSrmm before defining owner information for non-scratch volumes, software products, and vital record specifications.

If you plan to define volumes using the RMM ADDVOLUME subcommand and want to assign volume ownership, you must predefine those owners to DFSMSrmm before you add the volumes.

You must also define owners before you use the RMM ADDVRS subcommand or the DFSMSrmm Add Data Set VRS, DFSMSrmm Add Name VRS, or DFSMSrmm Add Volume VRS panel in the DFSMSrmm ISPF dialog.

DFSMSrmm automatically adds owner information to the control data set when volumes are read or data is written to volumes. DFSMSrmm uses the RACF user ID for a job, when available, as the volume owner. When there is no RACF user ID for a job, DFSMSrmm uses the job name as the volume owner ID.

To use DFSMSrmm automatic owner notification, you should include the owner's electronic user ID and node when you define an owner to DFSMSrmm. For example, if you want DFSMSrmm to automatically notify owners when their volumes become eligible for release, DFSMSrmm can send the release notification to the owner's electronic address, an MVS or VM user ID and node, that you have defined.

Defining Volumes

Use the RMM ADDVOLUME subcommand or the DFSMSrmm ISPF dialog to add physical volumes, logical volumes, and stacked volumes to DFSMSrmm. The volume serial number and volume status are the basic information needed for DFSMSrmm to recognize a volume. You can add more information using the subcommand or dialog or use the DFSMSrmm running modes to record information about volumes as they are used.

You can add information about volumes that reside in an automated tape library dataserver before they are entered into the automated tape library dataserver using the RMM ADDVOLUME subcommand or the DFSMSrmm ISPF dialog. For more information about adding volumes to a system-managed tape library and using DFSMSrmm with system-managed tape libraries, see "Chapter 4. Running DFSMSrmm with System-Managed Tape Libraries" on page 77.

You set running modes with the OPMODE operand in the parmlib member EDGRMMxx. See "Defining System Options: OPTION" on page 122 for information about the DFSMSrmm running modes. See *z/OS DFSMSrmm Guide and Reference* for details about adding volume information to DFSMSrmm.

Adding Volumes for a New Removable Media Library

If you have a new removable media library or system with all scratch tapes, define all volume information to DFSMSrmm at once.

1. Use the RMM ADDVOLUME subcommand or the DFSMSrmm ISPF dialog to define volume information to DFSMSrmm. Figure 23 on page 50 shows the minimum information you must add for each volume: volume serial number and volume status.

```
RMM ADDVOLUME volser STATUS(SCRATCH)
```

Figure 23. Defining Minimum Volume Information

To add volumes that are in a system-managed library, use the command as shown in Figure 24. You specify the STATUS(VOLCAT) to obtain volume information from the TCDB.

```
RMM ADDVOLUME volser STATUS(VOLCAT)
```

Figure 24. Defining Volumes in a System-managed Library

To add volumes that are in a manual tape library, use the command as shown in Figure 25. You must specify the MEDIATYPE operand and the RECORDINGFORMAT operand.

```
RMM ADDVOLUME volser LOCATION(mtlname) MEDIATYPE(HPCT) RECORDINGFORMAT(128TRACK) STATUS(SCRATCH)
```

Figure 25. Defining Volumes in a Manual Tape Library

When you are adding a volume to DFSMSrmm, you can specify if the volume is a logical volume, a physical volume, or a stacked volume. The default volume type is physical volume. If a volume resides in a virtual tape server (VTS), the default is either a logical volume or a stacked volume. If you want DFSMSrmm to manage stacked volumes, you must enable stacked volume support as described in “Setting up DFSMSrmm Stacked Volume Support” on page 307.

You can issue the subcommands in batch.

2. Set the DFSMSrmm running mode in the parmlib member EDGRMMxx to record only mode, warning mode, or protect mode. DFSMSrmm records information about the volumes as they are used. When DFSMSrmm is running in warning mode, DFSMSrmm validates magnetic tapes volumes as you use them. If DFSMSrmm discovers errors, it issues error messages instead of rejecting tapes. When DFSMSrmm is running in protect mode, DFSMSrmm validates magnetic tapes volumes as you use them and rejects magnetic tape volume mounts when errors are encountered. Protect mode is the only mode that provides full verification and validation of volumes.

Adding Volumes from an Existing Removable Media Library

If you have an existing removable media library with no record of tape usage, define basic volume information to DFSMSrmm. Set the DFSMSrmm running mode to record-only mode. DFSMSrmm monitors all tape volume mounts and automatically records and updates information about your defined tape volumes when they are used. DFSMSrmm cannot automatically record optical disk information.

1. Define all required tape volumes to DFSMSrmm as private volumes using the RMM ADDVOLUME subcommand. The following example shows the minimum information you should add:

   ```
   RMM ADDVOLUME volser STATUS(USER) EXPDT(yyyy/ddd)
   ```

   DFSMSrmm uses the parmlib RETPD default if you do not use EXPDT or RETPD to define an expiration date for the volumes. Specifying the EXPDT or RETPD operand allows you to define a time period long enough to gather information about the volumes under DFSMSrmm. Use the information to

determine if the volume should be released. Use EXPDT(99/365) if you are unsure how long volumes should be retained. Later, after running DFSMSrmm, defining DFSMSrmm vital record specifications, you should use the information to determine if the volume should be released.

Specifying STATUS(USER) ensures that DFSMSrmm does not change the expiration date when the first file on the volume is re-written.

2. Set the DFSMSrmm running mode to record-only mode. DFSMSrmm records information about the volumes as they are used but does not validate or reject volumes.
3. When you believe DFSMSrmm has recorded enough information, set the DFSMSrmm running mode to warning mode. When DFSMSrmm is running in warning mode, DFSMSrmm validates tape volumes. If DFSMSrmm discovers errors, it issues error messages but does not reject tape usage.
4. After DFSMSrmm has been running for a while, check volume usage to determine if some of the volumes you added can be released.

Adding Known Volumes

DFSMSrmm Sample Provided in SAMPLIB

- EDGCLMS Sample to Convert Volume Information into RMM Commands
- EDGRCSCR Sample to Convert Scratch Pool Information

See the IBM Redbook *Converting to Removable Media Manager: A Practical Guide*, SG24-4998 for information about converting from other products to DFSMSrmm.

1. When you have existing information about your media library, you can build a set of RMM TSO subcommands, one for each volume, and define the information you know. You can also write a REXX exec, CLIST or procedure that converts volume information from your existing tape management system into DFSMSrmm subcommand requests.
2. After adding the information you have available, set the DFSMSrmm running mode to protect mode. Protect mode is the only mode that provides full verification and validation of volumes.

Defining Vital Record Specifications

Vital record specifications are retention and movement policies for data sets and volumes. We suggest that you define vital record specifications to use DFSMSrmm retention and movement management. The only requirement is that you define them before running your first expiration processing, which you should run once a day.

To define vital record specifications, use the RMM ADDVRS subcommand or the DFSMSrmm ISPF dialog. For more information about ADDVRS and the dialog, see *z/OS DFSMSrmm Guide and Reference*. See “Managing Volumes with Special Dates” on page 70 for information about defining vital record specifications for volumes using special expiration dates using the EDGUX100 DFSMSrmm installation exit.

To implement the retention and movement policies you define, you must run DFSMSrmm inventory management vital record processing as described in “Running Vital Record Processing” on page 260. You can control the way vital

record processing runs using the DFSMSrmm parmlib member EDGRMMxx OPTION command as described in “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115.

Step 21: Updating the Operational Procedures

Ensure that operators understand how to use DFSMSrmm by documenting changes in your operational procedures. *z/OS DFSMSrmm Guide and Reference* has an operator procedures section that you should use to educate operators and update your procedures.

Step 22: Initializing the DFSMSrmm Subsystem and Tape Recording

Perform this step once for each MVS image to initialize the DFSMSrmm subsystem interface to enable tape usage.

Enabling the DFSMSrmm Subsystem Interface

Enable the DFSMSrmm subsystem interface to ensure that the interface starts every time you IPL and to ensure that users cannot use tapes before the DFSMSrmm subsystem starts. To enable DFSMSrmm, change the IEFSSNxx member of SYS1.PARMLIB. Add EDGSSSI, as the DFSMSrmm subsystem initialization program, as shown in Figure 26.

```
SUBSYS SUBNAME(JES2)              /* JES2 PRIMARY SUBSYSTEM START   */
  PRIMARY(YES)  START(YES)
SUBSYS SUBNAME(DFRM)              /* Name of the DFSMSrmm subsystem */
  INITRTN(EDGSSSI)                /* RMM initialization routine     */
SUBSYS SUBNAME(AOPA)              /* Netview                        */
```

Figure 26. Changing SYS1.PARMLIB IEFSSNxx

Figure 26 shows the correct relative position of the DFSMSrmm subsystem, updated to include the initialization program.

Changing the DFSMSrmm Running Mode

The DFSMSrmm running modes are set with the parmlib OPTION command OPMODE operand. Each DFSMSrmm running mode provides different levels of information recording and volume validation. If you want to record information about volumes, set the running mode to record-only by setting the OPMODE in the parmlib member EDGRMMxx to R and starting or restarting DFSMSrmm.

Set the running mode to warning mode if you want DFSMSrmm to validate tape volumes. DFSMSrmm issues error messages but does not reject tape usage. If you want to ensure that DFSMSrmm provides full validation and recording functions, set the running mode to protect mode.

After you have verified that DFSMSrmm is providing the required functions, change the DFSMSrmm running mode to protect mode. Protect mode is the only mode that provides full verification and validation of volumes.

If you are converting to DFSMSrmm from another media management system, this step would be part of the final conversion phase. In the final phase, you might be reconverting some data set and volume information. Changing to protect mode ensures that DFSMSrmm controls the management of the volumes defined to it, and controls the use of scratch tapes. When changing to protect mode, we

recommend that you either stop running the current media management system or ensure that the two products do not overlap in their function.

Activating the DFSMShsm Interface

To activate the DFSMShsm interface, follow the directions in “Releasing Tapes: EDGTVEXT” on page 177.

Restarting the DFSMSrmm Subsystem

If you changed the DFSMSrmm running mode as described in “Changing the DFSMSrmm Running Mode” on page 52 and need to activate the DFSMSrmm subsystem interface to implement the change, use the operator MODIFY command shown in Figure 27:

```
F DFRMM,M=xx
```

Figure 27. Restarting the DFSMSrmm Subsystem

where:

M=xx
Specifies the suffix of parmlib member EDGRMMxx.

The subsystem temporarily stops and reinitializes itself with the new OPMODE. Use this command whenever you update DFSMSrmm parameters and want to implement the change.

During this restart, DFSMSrmm issues the message shown in Figure 28, unless you have IPLed the system since adding EDGSSSI to IEFSSNxx in SYS1.PARMLIB, in which case the interface is already initialized.

```
EDG0103D DFSMSrmm SUBSYSTEM INTERFACE IS INACTIVE -
              ENTER "IGNORE", "CANCEL" OR "RETRY"
```

Figure 28. Message EDG0103D

Reply **RETRY** to this message. In response, DFSMSrmm initializes its subsystem interface. If you reply IGNORE, the DFSMSrmm tape recording function is not activated.

Step 23: Setting Up DFSMSrmm Utilities

There are several DFSMSrmm utilities that you should now set up to run. Be sure to run the utilities on the system with the highest level of code to ensure you are taking advantage of DFSMSrmm enhancements and changes to the control data set. Refer to the following for each utility:

- See “Scheduling DFSMSrmm Utilities” on page 247 for a sample schedule of all DFSMSrmm utilities. See “Chapter 21. Running DFSMSrmm with Tivoli OPC” on page 353 for information about setting up Tivoli OPC to manage the scheduling of DFSMSrmm functions.
- See “Chapter 13. Performing Inventory Management” on page 247 for information about EDGHSKP to run inventory management activities.
  - Run vital record processing to determine which volumes to retain and what volume moves are required based on vital record specifications. Vital record

processing can be run to validate vital record specification information without updating volume and data set information in the DFSMSrmm control data set.
  - Run expiration processing to identify volumes that are ready to be released and returned to scratch.
  - Run storage location management processing to assign shelf locations to volumes that are being moved to storage locations.
  - Run backup of the control data set and the journal to ensure the integrity of the control data set and journal.
- See *z/OS DFSMSrmm Reporting* for information about utilities that help you get information about your removable media library and storage locations, security related information about volumes and data sets defined to DFSMSrmm, and audit trail information about volumes, shelf assignments, and user activity. Create movement and inventory reports by producing an extract data set from the control data set and creating a report from the control data set with EDGRPTD.
- See “Chapter 16. Maintaining the Control Data Set” on page 287 for information about using EDGBKUP and EDGUTIL to back up and recover the control data set, back up the journal, and check the integrity of the information contained in the control data set. Use the EDGBKUP utility to back up and recover the control data set and back up the journal, and the EDGUTIL utility to create, update, and verify the control data set.

  Use DFSMSrmm backup utilities rather than other backup utilities, like access method services EXPORT, because DFSMSrmm provides the necessary serialization and forward recovery functions. Use EDGBKUP to backup and recover the DFSMSrmm control data set when DFSMSrmm is inactive, stopped, or quiesced.
- See “Chapter 17. Initializing and Erasing Volumes” on page 311 for information about EDGINERS, the DFSMSrmm utility you use to erase and initialize tape volumes either automatically or manually. You can use EDGINERS to replace the DFSMSdfp utility IEHINITT.

Chapter 3. Organizing the Removable Media Library

To organize your removable media library:

- Create pools of volumes and shelves in your removable media library
- Use Storage Management Subsystem (SMS) management class and storage group to manage volumes in your removable media library
- Use special dates to manage volumes
- Use DFSMSrmm support for using duplicate volume serial numbers

Organizing the Library by Pools

You can set installation-defined policies using DFSMSrmm VLPOOL options to pool volumes based on:

- Systems or subsets of systems
- MVS or VM usage
- Using rack pools to hold foreign tapes
- Media names your installation defines, like 3480, TAPE, CASSETTE
- SMS storage group names

Pooling Overview

DFSMSrmm supports these basic types of pooling:

- Pools of shelf space that are based on rack number prefixes. Each range identifies characteristics like media name and management criteria. You must use shelf space pools to store volumes that do not match your installation selected volume ranges. Define shelf space pools using the DFSMSrmm EDGRMMxx VLPOOL command described “Defining Pools: VLPOOL” on page 148.
- Pools of volumes that are based on the volume serial number prefix. These volumes do not have a rack number or the rack number matches the volume serial number. Each range identifies characteristics like media name and management criteria. Define volume prefix pools using the DFSMSrmm EDGRMMxx VLPOOL command described “Defining Pools: VLPOOL” on page 148.
- Scratch pools can be one or more pools of volumes. Scratch pools can be based on name, SMS storage group, prefix, or system. You define scratch pools using the SYSID, PREFIX, and NAME operands of the DFSMSrmm EDGRMMxx VLPOOL command described “Defining Pools: VLPOOL” on page 148.
- When you pool by storage group and use SMS ACS processing to assign a storage group to a tape data set, or the volume is in a system-managed manual tape library, DFSMSrmm ensures that a volume from the correct storage group is mounted. The storage group can be the same across multiple VLPOOL entries. You can use storage group for scratch pooling for system-managed manual tape libraries and non-system managed tape.

Pools are used as follows:

- Adding shelf space - DFSMSrmm matches the rack number prefix to the most specific VLPOOL prefix. The rack media name is taken from the matching VLPOOL entry.
- Adding volumes - You can optionally specify RACK or POOL operands to override default processing. Default processing matches the volume serial number prefix to the most specific VLPOOL prefix. If a rack number is found that matches the volume serial number and the specified media name, the volume is stored in the matching shelf pool. If no rack number is found, the volume is in a

© Copyright IBM Corp. 1992, 2001

volume pool. When adding a volume you can specify a storage group name so that the volume can be in a specific scratch pool. If no storage group is specified by the command, DFSMSrmm checks to see if the matching VLPOOL NAME is a storage group, and uses that value as the storage group name. In this case, the scratch pool matches the volume pool.

- For system-managed tapes in a manual tape library, DFSMSrmm validates the mounted volume for the requested pool. You can use the installation exit to ignore the storage group pool and use DFSMSrmm system-based scratch pooling described in “Using Storage Group for Manual Tape Library Pooling” on page 214.
- Selecting scratch pools for new tape data sets - For system-managed tape, SMS ACS processing assigns a storage group. DFSMSrmm uses the storage group name to pool the volumes into a scratch pool. For non-system managed tape, DFSMSrmm calls SMS ACS processing to allow a storage group to be assigned. If no storage group is assigned, the DFSMSrmm installation exit EDGUX100 is called to allow a pool prefix to be selected. Otherwise DFSMSrmm system-based scratch pooling selects a pool prefix. For tape volumes in a system-managed manual tape library, DFSMSrmm validates that the mounted volume is from the correct storage group. Alternatively, you can use the EDGUX100 installation exit to ignore the storage group name and use DFSMSrmm-exit selected pooling or DFSMSrmm system-based pooling.

When you pool by pool prefix, selected by EDGUX100 or by SYSID, and the VLPOOL prefix has an associated NAME, DFSMSrmm uses the pool name for mount messages and drive displays but always validates mounted volumes by using the pool prefix and SYSID. Multiple VLPOOL entries can have the same SYSID and NAME values.

Pooling Considerations

If you do not currently use application or user-oriented scratch pools based on job names and data set names, we recommend that you use DFSMSrmm system-based pooling or a general, installation-wide scratch pool. If you currently use application or user-oriented scratch pools based on job names and data set names, we recommend that you use SMS ACS routines to assign storage groups. You can use storage groups to pool volumes based on job names and data set names as described in “Using Storage Groups for DFSMSrmm Scratch Pooling” on page 63. You can also implement DFSMSrmm pooling using DFSMSrmm VLPOOL options.

If you are already using some form of scratch pooling based on information such as job name and data set name, review your current use of these pools in order to plan or change your implementation under DFSMSrmm.

Pool Types

You use scratch pools with DFSMSrmm system-based scratch pooling. You can define scratch volumes in rack pools and use the RMM GETVOLUME subcommand to claim them or assign them to a user. You can also use EDGUX100 to use rack pools or scratch pools for non-specific tape output requests.

When you define pools for use with specific groups of users or applications, you also need to consider how volumes are defined to DFSMSrmm. You can use the DFSMSrmm ISPF dialog or RMM ADDVOLUME subcommand to define volumes. To add a volume to a specific pool, provide the pool prefix when you issue the RMM ADDVOLUME subcommand or use the DFSMSrmm ISPF dialog. You only need to specify a pool prefix if the volume serial number does not start with the

same characters as the pool prefix. When defining scratch volumes you will probably use volume serial numbers that match the rack numbers you include in the pool definition. When adding private volumes which come from another library you will have to specify a pool prefix. You can also use the DFSMSrmm ISPF dialog or RMM TSO CHANGEVOLUME subcommand to move an existing volume to a pool you define, so that the volume becomes part of the pool.

Tape Drive Availability

If you are using specific pools, you need to plan how you set up your scratch tape drives so that a correct scratch tape can be mounted promptly. The benefit of using scratch tapes is that almost any unused tape can be mounted and DFSMSrmm will record new information for the volume. However, as you become more selective about which scratch tapes are used for each non-specific volume request, you gradually erode the benefits of scratch tapes as your requests become more and more specific.

To make mounting tape volumes easier, you might consider setting aside certain tape drives for use with identified scratch pools. When using tape cartridge loaders with DFSMSrmm pooling, you need to load each drive with volumes from a single scratch pool, run them in system mode, and direct only the correct non-specific requests to them. Cartridge loaders must not be run in automatic mode because DFSMSrmm processing depends on the mount message which is not issued when the cartridge loader is in automatic mode and a volume is already loaded. You could consider defining different esoteric unit names for each of the tape drives you choose to load with scratch volumes from a single pool.

You can use the EDGUX100 exit to request DFSMSrmm to disable the tape drive cartridge loader to prevent specific scratch pool requests from emptying the loaders through volume rejection. Alternatively, you can direct requests to the correct drives or run the loaders in a mode that prevents them being automatically indexed when a mount is received. Also DFSMSrmm disables the loader if a volume is rejected for a scratch request to prevent the loader from being emptied.

Operator Messages and Tape Drive Displays

To use ACS routines or exit selected scratch pooling, you must define messages IEC501A, IEF233A, IAT5110, and IAT5210 using the DFSMSrmm MNTMSG commands in parmlib as described in “Defining Mount and Fetch Messages: MNTMSG” on page 119. These messages provide the pool identifiers to the operator, and the job name and data set name information to the EDGUX100 exit.

DFSMSrmm can update mount messages and tape drive displays with the pool prefix, storage group name, or pool name. DFSMSrmm can also provide information to some tape automation software installed on your system through the tape mount messages. DFSMSrmm updates messages IEF233A and IEC501A, and IAT5210 for JES3 to include the pool identifier that you select. You can define BTLS category names so that DFSMSrmm can be used to manage volumes in a BTLS-managed tape library dataserver. If you use BTLS scratch category names as DFSMSrmm pool names, DFSMSrmm can be used to direct which volumes BTLS will use for each scratch mount.

For JES3, to find out which pool was used to satisfy a request, install the USERMOD EDG3UX71, and your users can see mount messages with the pool identifier in the output from their batch jobs. Users allowed to view the SYSLOG can see the updated messages in the SYSLOG.

Defining Pools in Parmlib Member EDGRMMxx

You must define any pool you plan to use with DFSMSrmm in the parmlib member EDGRMMxx using the VLPOOL command. This applies to pools used by DFSMSrmm pooling and by EDGUX100. See “Defining Pools: VLPOOL” on page 148 for information on using VLPOOL command in the parmlib member EDGRMMxx. You also have to consider shelf space and whether volumes are to be segregated based on media names for any scratch pooling method you use.

Define at least one pool using the VLPOOL command in the DFSMSrmm parmlib member. Use the pools to assign a media name for shelf space and volumes based on a prefix. Define a default pool to ensure that volumes and racks which do not match to a more specific VLPOOL are added with correct media name and pool name.

Figure 29 shows a VLPOOL command example of the default pool thatDFSMSrmm assigns if you do not specify any VLPOOL commands. This default pool includes all shelf locations, all volumes in those shelf locations, and all volumes with no defined shelf location.

```
VLPOOL RACF(N) TYPE(S) -
  EXPDTCHECK(O) MEDIANAME(3480) -
  DESCRIPTION('DEFAULT POOL') PREFIX(*)
```

Figure 29. Default VLPOOL Command

RACF(N) specifies whether to provide RACF tape profile processing for this tape pool. The value N indicates that RACF tape profiles are not created, changed, or deleted for tapes in this pool, regardless of the setting of the system-wide option TPRACF.

TYPE(S) specifies the type of pool. The value S means it is a scratch pool.

EXPDTCHECK(O) specifies the processing of expiration date protected tape data sets on volumes in this pool. The value O means that DFSMSrmm takes no action but allows the operator or automated software to reply as necessary to any write-to-operator messages (IEC507D).

MEDIANAME(3480) specifies a media name for all volumes in this pool. DFSMSrmm uses MEDIANAME to determine if a volume should be accepted into a pool. You can specify any name because DFSMSrmm does not check if it is a device type that has been defined to MVS. To allow more flexibility in the media that can reside in a pool, select MEDIANAMES that reflect shelving requirements like size and shape. For example, you can specify CART, ROUND, SQUARE, 3490, 3590, TAPE, OPTICAL, CASSETTE, and so on. If you specify MEDIANAME(3480), DFSMSrmm only accepts media designated as 3480. If you select MEDIANAME(CART), and specify all your 3480, 3490, 3490E, and 3590 tape volumes as CART when you define them to DFSMSrmm, then DFSMSrmm accepts all tape volumes into the same pool. DFSMSrmm accepts media names that have not been generated on the MVS system running DFSMSrmm.

To implement segregating storage locations by media name, any LOCDEF command media names you define, must be the same as the VLPOOL media names or a subset of the media names. See “Defining Storage Locations: LOCDEF” on page 115 for information on defining storage locations.

DESCRIPTION('DEFAULT POOL') describes the pool.

PREFIX(*) specifies a generic shelf location prefix that is used in operator messages, TSO subcommands, and the DFSMSrmm ISPF dialog. A single asterisk defines the default pool that contains all rack numbers or volumes not specifically included in any pool. You also have the option to define a pool name that can be used to update operator messages, displays, and can be used as a storage group.

There is also a SYSID operand on the VLPOOL command. SYSID associates a scratch pool with a particular system. DFSMSrmm matches the value with the SYSID operand of the OPTION command, also in EDGRMMxx. If the VLPOOL SYSID matches the OPTION SYSID then:

- A volume from this pool can be used to satisfy a scratch mount request on this system.
- A volume from any other pool where its SYSID also matches the OPTION SYSID can be used to satisfy a scratch request on this system.

A volume from a pool that has no explicit VLPOOL SYSID can be used to satisfy a scratch request on a system if there are no other VLPOOL definitions that have a SYSID matching the OPTION SYSID. The SYSID values are ignored when a storage group is selected by ACS processing and when a pool is set for a non-specific volume request by EDGUX100 processing. The system level pools can still be used as long as SMS ACS processing does not assign a storage group and the EDGUX100 exit does not set a specific pool to be use.

Calculating Pool Size

When planning the size of your pools, remember that the number of characters in the pool prefix determines the maximum pool size. A pool prefix consists of one to five alphanumeric characters followed by an *, for example, ABADA*. Table 11 shows the maximum number of volumes each range of pool prefixes can contain:

Table 11. DFSMSrmm Volumes in a Pool Determined by Pool Prefix

Pool Prefix	Maximum Number of Volumes
A*	100 000
AA*	10 000
AAA*	1000
AAAA*	100
AAAAA*	10

Note: The maximum numbers in Table 11 are for numeric suffixes. If you use non-numeric suffixes, such as pool prefix A with suffixes A00000 through AZZZZZ, you can increase the maximum number of volumes for that pool. For example, using the suffix AAAAA* with alphanumeric characters, $, #, or @, you can have a maximum of 39 volumes. However, by using non-numeric suffixes, you limit the use of the COUNT operand on RMM TSO rack and volume related subcommands.

Plan ahead when choosing your pool prefixes, ensuring that the pool prefixes can satisfy all future volume quantities. It is not necessary to define all shelf locations to DFSMSrmm at once. Using pool definitions, you can reserve space for library

expansion without taking up space in the control data set. For instance, you could assign a pool prefix ABC*, allowing space for 1000 volumes, but only defining shelves ABC000 - ABC099 initially.

When you use the VLPOOL NAME or SMS storage group name for scratch pooling, you can include multiple VLPOOL PREFIX ranges into the same scratch pool by specifying the same NAME value on multiple VLPOOL definitions or by assigning storage group names for each volume.

Changing Pool Definitions

Use the VLPOOL command in the EDGRMMxx parmlib member to change pool definitions. See “Defining Pools: VLPOOL” on page 148 for information about using the VLPOOL command.

If you change a pool definition that include racks defined to an existing pool, you might need to redefine the shelf locations or volumes to DFSMSrmm. To redefine the shelf locations or volumes when the media name for the new pool does not match the existing pool, you use the RMM subcommands or DFSMSrmm ISPF dialog to change information. For example, to redefine the shelf locations and volumes:

1. Add or alter the VLPOOL statements in parmlib and refresh the DFSMSrmm parameters.
2. Add rack numbers for the new VLPOOL prefixes and those with changed MEDIANAMEs.
3. Issue the RMM CHANGEVOLUME volser MEDIANAME for each volume affected.
4. Delete the old rack numbers specifying the old MEDIANAME.

See *z/OS DFSMSrmm Guide and Reference* for more information about using the RMM subcommands or the DFSMSrmm ISPF dialog to change the pool definitions.

Designing Pools

A *pool* is a group of rack numbers or volumes that share a common prefix. In DFSMSrmm, there are two categories of pools: rack and scratch.

A *rack pool* is shelf space that can be assigned to hold any volumes. Although you can add scratch volumes to these pools, you cannot normally use these volumes to satisfy non-specific mount requests. A rack pool cannot be used with the DFSMSrmm system-based scratch pooling. Rack pools can:

- Hold volumes that are temporarily brought into the library but will be returned to the owner after a period of time
- Hold customer, foreign tapes, and software product volumes
- Contain scratch volumes for use with DFSMSrmm exit-selected scratch pooling

A *scratch pool* is shelf space assigned to hold volumes for use with the DFSMSrmm system-based scratch pooling. The volumes assigned to this shelf space can be used to satisfy scratch requests as long as the volumes are in scratch status. Once the volume has been written to, it becomes a volume with MASTER status, until the volume is returned to scratch status. The volume remains in the same DFSMSrmm system based scratch pool, in that it occupies the same shelf space regardless of status.

The scratch volumes in a system-managed tape library can be from one or more pools. DFSMSrmm does not provide pool selection or validation for volumes in an automated tape library dataserver because ACS routines use storage class and storage group to make allocation decisions, and the Library Manager picks a scratch volume. DFSMSrmm provides pool validation for volumes that reside in a manual tape library. You can pool by storage group, exit-selected pool prefix, or DFSMSrmm system-based pooling when using manual tape libraries.

Designing Rack Pools

If you have several types of media, define pools based on type of media. For example, you can separate your reels and cartridges from each other by placing them in separate pools.

The volumes in these pools have no relationship to any specific device type. Although you can use device type names rather than media type names to define these pools, DFSMSrmm does not associate device type names with devices.

You might want to provide a pool of scratch volumes for a particular group of users or application. With EDGUX100, you can use an exit-selected scratch pool to satisfy non-specific mount requests.

Users can also obtain volumes from a pool using the DFSMSrmm ISPF dialog or the RMM GETVOLUME subcommand. When you use the GETVOLUME subcommand, all tape mounts are specific mounts, which means you cannot use a scratch pool and cartridge loaders.

If you have any volumes that do not meet your chosen volume naming conventions, or have a number of volumes that regularly enter and leave the removable media library, define a pool of empty shelf locations in which you can store these volumes.

When volumes arrive at the installation, define the volume to DFSMSrmm using the chosen pool ID. DFSMSrmm assigns the next available empty shelf location to the volume. Place an external label specifying the rack number on the volume to identify it.

If your removable media library is split across rooms or sites, define pools that allow easy segregation and identification of volumes based on shelf location number.

Designing Scratch Pools

We recommend using one scratch pool for the entire library. You can use a VLPOOL command similar to the default, shown in Figure 29 on page 58. When defining scratch pools, do not use no label tapes in the pool.

You can define scratch pools based on the system where the volumes are used. For example, define a pool prefix A* to cover all volumes in a pool reserved for system MVSA. Define a pool prefix VM* for a pool reserved for volumes used on a VM system.

When you define scratch pools by system, you can only use scratch volumes from those pools on the systems specified for them. If you try to mount a scratch volume on a different system than the one with which it is associated, DFSMSrmm rejects the volume. If a system has no pool defined for it, the system accepts all volumes except those you have defined to a specific system. Leave your scratch volumes for use on all systems if you do not want these limitations.

You can define multiple pools for each system by associating the pools with a system using the DFSMSrmm EDGRMMxx parmlib VLPOOL command with the SYSID operand as described in “Defining Pools: VLPOOL” on page 148. DFSMSrmm accepts a volume from any of the pools defined to that system. DFSMSrmm updates mount messages and drive displays to indicate the pool from which the scratch volume should be pulled. The pools are searched in alphabetical order and the first suitable pool encountered is added to mount and fetch messages. You can assign the same name to multiple pools to make it easier to satisfy mount requests.

When you define multiple scratch pools, DFSMSrmm does not use the media name when selecting the pool to use. If you are not using system based scratch pools, the operator can mount any volume. Operators use local conventions and operator procedures to select a scratch volume. For example, the operator should select a reel tape for a mount on a 3420 drive. For a 3490 drive, the operator should select a cartridge tape. In most cases, scratch tapes are already pulled and are available for immediate mounting.

Within the pool for use on a VM system, you can define each volume for use only on VM, or for use on MVS and VM. DFSMSrmm uses this information to reject non-MVS volumes on MVS. You can use VM volumes on VM systems.

You can design pools at the user, group, or application level by using DFSMSrmm calls to SMS ACS to assign storage group names, or you can make use of the EDGUX100 installation exit to control scratch pool selection. See “Using Storage Groups for DFSMSrmm Scratch Pooling” on page 63 and “Using the DFSMSrmm EDGUX100 Installation Exit” on page 195 for more information about using pool names and implementing exit-selected scratch pools.

Planning to Use Scratch Pools

You can implement DFSMSrmm scratch pooling using different methods and can decide at the individual request level which method to use.

- Use ACS routines for scratch pooling based on tape storage group names. DFSMSrmm provides support for non-system-managed tape and for system-managed manual tape libraries. This support enables pooling at the individual volume level. You assign a storage group name to each volume by
  - Using DFSMSrmm TSO subcommands
  - Using pooling information that you define with the DFSMSrmm EDGRMMxx parmlib VLPOOL command
- Set up DFSMSrmm system-based scratch pooling using the DFSMSrmm VLPOOL command with the SYSID operand. This method allows you to control which scratch pools can be used based on the system on which the volumes are used. This enforces pooling based on VLPOOL prefix pools.
- Use the DFSMSrmm EDGUX100 installation exit described in “Chapter 10. Using DFSMSrmm Installation Exits” on page 195 to select a pool prefix. You can use information in the system to determine which pool to use.
- Use pre-ACS processing to obtain the DFSMSrmm system-based pool or the EDGUX100 installation exit pool prefix as an input value to the ACS routines in the MSPOOL read-only variable. During pre-ACS processing, DFSMSrmm does not make the RMMPOOL environment call to the ACS routine.

For each request for a new scratch tape, a scratch pool can be selected using any of these methods:

- Using ACS processing to set a storage group name, which overrides any other method.
- Customizing the DFSMSrmm EDGUX100 installation exit to determine the pool.
- Using the DFSMSrmm default system-based pooling when no other method is specified.

To support this choice DFSMSrmm processing follows these steps:

1. During pre-ACS processing for new allocations:
   - Use the VLPOOL definitions to select a default DFSMSrmm pool using the DFSMSrmm system-based pooling. DFSMSrmm sets a pool prefix if a specific pool is selected.
   - DFSMSrmm calls the EDGUX100 installation exit to obtain a pool prefix value. If a pool prefix value is returned, the pool prefix value returned by the EDGUX100 installation exit overrides the DFSMSrmm selected pool.
   - Return the selected value in the MSPOOL read-only variable.
2. During mount message or OPEN processing after a device has been allocated:
   - Use the VLPOOL definitions to select a default DFSMSrmm pool using the DFSMSrmm system-based pooling. A pool prefix and a pool name are set if a specific pool is selected.
   - DFSMSrmm calls ACS routines passing environment information, including the pool identified by DFSMSrmm system-based pooling. The ACS routine can optionally set a storage group name, which overrides the DFSMSrmm system-based pool.
   - If a storage group name is not returned from ACS processing, DFSMSrmm calls the EDGUX100 installation exit to request a pool prefix value to be returned. If a pool prefix value is returned, it overrides the DFSMSrmm system-based pool. The pool name is set based on the selected pool prefix.
   - The mount message and drive display are updated with the appropriate pool prefix, pool name or storage group name.
   - During OPEN processing, DFSMSrmm validates the mounted scratch volume against the selected scratch pool prefix, pool name, or storage group.

DFSMSrmm system-based scratch pooling is always active on your system except for automated system-managed tape. To use exit-selected scratch pooling, you must install the sample EDGUX100 installation exit on your system and use the installation exit EDGUX100 to set a specific pool for a non-specific volume request. See “Chapter 10. Using DFSMSrmm Installation Exits” on page 195 for information about the EDGUX100 installation exit.

Using Storage Groups for DFSMSrmm Scratch Pooling

This section describes how to use storage groups for DFSMSrmm scratch pooling.

Making an ACS Storage Group Assignment

To assign a storage group, you must have the SMS subsystem active and have a valid SMS configuration.

You use the ACS routines to process the special calls that DFSMSrmm makes to the SMS subsystem for ACS processing. DFSMSrmm requests that the management class and storage group routines are run. The environment variable is

set to *RMMPOOL* so that you can differentiate allocation requests for system-managed data sets from requests by DFSMSrmm for a storage group name.

Table 12 lists the read-only variables that are set for DFSMSrmm requests:

Table 12. SMS Read-only Variables Set by DFSMSrmm

&ACCT_JOB	&ACCT_STEP	&ACSENVIR	&DD
&DSN	&DSORG	&DSTYPE	&EXPDT
&FILENUM	&GROUP	&HLQ	&JOB
&LABEL	&LIBNAME	&LLQ	&NQUAL
&PGM	&STORGRP	&SYSNAME	&SYSPLEX
&UNIT	&USER	&XMODE	

The &DD, &PGM, &EXPDT, and &FILENUM variables are optional for JES3 mount messages. &LIBNAME is optional for JES3 fetch messages.

1. Define your pools by using the DFSMSrmm EDGRMMxx parmlib VLPOOL command as shown in Figure 30. See “Defining Pools: VLPOOL” on page 148 for information about the VLPOOL command.

```
 ...
VLPOOL PREFIX(123*)   NAME(POOLA) MEDIANAME(CARTS) -
    DESCRIPTION('PART OF POOL A')
VLPOOL PREFIX(99975*) NAME(POOLA) MEDIANAME(REELS) -
    DESCRIPTION('PART OF POOL A')
VLPOOL PREFIX(C0*)    NAME(TEMP) MEDIANAME(CARTS) -
    DESCRIPTION('TEMPORARY POOL')
VLPOOL PREFIX(*)      NAME(DEFAULT) MEDIANAME(CARTS) -
    DESCRIPTION('DEFAULT POOL')
 ...
```

Figure 30. Defining Pools with the DFSMSrmm EDGRMMxx Parmlib VLPOOL Command

2. Code your selection criteria and rules into the management class and storage group ACS routines as shown in Figure 31 on page 65.

```
PROC 1 MGMTCLAS
 ...
 /*************************************************/
 /*   RMM POOLING FILTER LISTS                    */
 /*************************************************/
 ...
FILTLIST POOLA INCLUDE(USERA.**,USERY.KEEP.*) -
               EXCLUDE(USERA.POOLB.**)
 ...
 IF &ACSENVIR = 'RMMPOOL' THEN
 /*************************************************/
 /*   RMM POOLING DECISIONS                       */
 /*************************************************/
   DO
     SELECT (&DSN)
       WHEN (&POOLA) SET &MGMTCLAS = 'POOLA'
       OTHERWISE     SET &MGMTCLAS = 'DEFAULT'
     END
     /* ALLOCATE TEMP POOL FOR TEMPORARY DATA SETS  */
     IF &DSTYPE = TEMP THEN SET &MGMTCLAS = TEMP
 ...
   END
 ...
END
```

Figure 31. Sample Management Class Routine

If your ACS processing does not set the storage group name, DFSMSrmm processing continues without using storage group names.

The processing that the STORGRP ACS routine performs is limited to the variables it can reference. You might want to make your decisions in the MGMTCLAS ACS routine and use the STORGRP routine to set the STORGRP variable to the selected value.

Any management class value that you set during ACS processing for the RMMPOOL ACS environment call is ignored by DFSMSrmm processing.

```
PROC 1 STORGRP
 ...
 IF &ACSENVIR = 'RMMPOOL' THEN
 /*************************************************/
 /*   RMM POOLING DECISIONS                       */
 /*************************************************/
   DO
     SELECT (&MGMTCLAS)
       WHEN ('POOLA')   SET &STORGRP = 'POOLA'
       WHEN ('DEFAULT') SET &STORGRP = 'DEFAULT'
       WHEN ('TEMP')    SET &STORGRP = 'TEMP'
     END
 ...
   END
 ...
 END
```

Figure 32. Storage Group Routine Sample

A Pooling Example

This example describes how pooling might be implemented for an installation that has:

- An automated tape library dataserver and no non-system-managed drives.
- A manual tape library.
- Ranges of scratch tapes using a numbering system with consecutive numbers for volumes spread across a few well identified ranges.

  Volume serial numbers, 210000 - 219999, 710000-719999, and 800000 - 805999.
- Foreign tapes from IBM and other vendors with standard labels and random volume serial numbers that use alphanumeric prefixes, such as DZ1100 or DP3100.
- Tapes sent from another site for input processing. The other site uses a range of tapes numbered 401000 - 401999. The tapes are scratch at the other site, but are private volumes here.

The installation defines pools using the VLPOOL command as shown in Figure 33:

```
VLPOOL PREFIX(21*) TYPE(S) MEDIANAME(CART) RACF(Y) EXPDTCHECK(N) -
   DESCRIPTION('scratch pool of cartridge system tape')
VLPOOL PREFIX(71*) TYPE(S) MEDIANAME(CART) RACF(Y) EXPDTCHECK(N)-
   DESCRIPTION('scratch pool manual tape library') -
   NAME(SGMTL01)
 VLPOOL PREFIX(80*) TYPE(S) MEDIANAME(CART) RACF(Y) EXPDTCHECK(N)-
   DESCRIPTION('scratch pool enhanced capacity cartridge') -
   NAME(TWOTONE)
VLPOOL PREFIX(401*) TYPE(R) MEDIANAME(CART) RACF(Y) EXPDTCHECK(Y) -
   NAME(SITE2) -
   DESCRIPTION('tapes sent from site 2')
VLPOOL PREFIX(*) TYPE(R) MEDIANAME(CART) RACF(Y) EXPDTCHECK(Y) -
   NAME(SITE2) -
   DESCRIPTION('miscellaneous check-in and check-out tapes')
```

Figure 33. Defining Pools with VLPOOL Commands

The installation can now define volumes in the 21*, 71* and 80* pools which DFSMSrmm manages as scratch pools. The storage group SGMTL01 used as a VLPOOL NAME must be defined as a valid storage group name to SMS. The installation can also define some empty racks for the 401* volumes. Each time a foreign volume comes in, it is defined to DFSMSrmm, with RLSE(RETURN) RETPD(nn), labeled with a sticky label, and entered into the system-managed tape library.

RACF and EXPDTCHECK provide the following:

- RACF(Y) is specified for all pools to ensure that tape volume security is managed by DFSMSrmm as described in “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115.
- EXPDTCHECK(N) is used for scratch pools, so DFSMSrmm automatically replies to any IEC507D expiration date protection messages allowing scratch volumes to be reused. DFSMSrmm does not reply to the IEC507D message issued for tape volumes when you use the EDGUX100 installation exit to ignore a volume.
- EXPDTCHECK(Y) is used for all non-scratch volumes to ensure that DFSMSrmm automatically replies to IEC507D to prevent overwrite of expiration date protected data.

For the remainder of the volumes, when a volume comes in, the installation defines a rack number that matches the VOL1 label, and then defines the volume using RLSE(RETURN) RETPD(nnn). This approach should be used since the external and internal volume serial number must be the same.

In this example, all scratch volumes are system-managed. DFSMSrmm validates scratch pools for requests in the manual system-managed library, but does not validate scratch pools for automated tape library dataservers. DFSMSrmm always ensures that a scratch volume is mounted in response to a non-specific mount request. Defining a rack pool is an alternative to using a scratch pool as described here. The rack pool should have a finite size based on known requirements, and accommodate any volume serial number as long as it does not conflict with the installation's naming conventions.

Anytime the installation wants to have more scratch volumes, existing pools can be made larger or new pools reserving a new range of numbers can be defined.

This approach for system-managed libraries differs from the way pools might be used with a non-system-managed library. With a non-system-managed library, you need to have physical shelving. You also have the option of using different internal to external labels.

For installations with mixed environments, a combination of these approaches provides a workable solution.

Managing Pools with Job Name and Data Set Name

Although you can use EDGUX100 to manage scratch pooling with jobname and data set name, we recommend the use of SMS ACS Storage Group assignment. For information, see "Making an ACS Storage Group Assignment" on page 63. You can manage scratch tape pools based on job names and data set names for non-system-managed volumes by using the DFSMSrmm EDGUX100 installation exit. See "Chapter 10. Using DFSMSrmm Installation Exits" on page 195 for information about using the EDGUX100 installation exit.

Use the DFSMSrmm installation exit EDGUX100 to select the correct scratch pool for non-specific requests for non-system-managed volumes and to decide whether the cartridge loader should be used. You can also use EDGUX100 with criteria other than job names and data set names, but you have to modify the supplied EDGUX100 installation exit in order to do this.

Assigning Policies

DFSMSrmm provides these methods for the assignment of retention and management policies.

1. Use ACS routines to assign a management class name that matches a DFSMSrmm data set vital record specification. DFSMSrmm calls ACS routines directly to provide support for non-system-managed tape. This DFSMSrmm processing enables you to use SMS management class to manage system-managed and non-system-managed tape data.
2. Define DFSMSrmm vital record specifications with data set name masks to identify the retention and movement policies.
3. Define a vital record specification management value that DFSMSrmm can use to apply retention and movement policies to datasets. Use the DFSMSrmm EDGUX100 installation exit described in "Chapter 10. Using DFSMSrmm

Installation Exits" on page 195 to select a vital record specification management value. You can use information in the system to determine which vital record specification management value to use.

4. During pre-ACS processing, use the DFSMSrmm EDGUX100 installation exit to obtain information that is used by the ACS routines. The EDGUX100 installation exit can provide a vital record specification management value in the MSPOLICY read-only variable, which is used by the ACS routines. During pre-ACS processing, DFSMSrmm does not make the RMMVRS environment call to the ACS routine.

Using SMS ACS processing you can consolidate policy assignment decisions in a single place whether you use system-managed tape or not. You can use SMS ACS routines to assign management class for your data sets instead of using EDGUX100 exit assigned vital record specification management values. You can assign a management policy by name to either a non-system-managed or a system-managed tape data set.

For non-system-managed tape, DFSMSrmm calls the ACS routines to obtain a management class. The management class is used in place of the vital record specification management value assigned by the DFSMSrmm EDGUX100 installation exit. When a management class name is assigned using ACS routines, the EDGUX100 installation exit is not called for a vital record specification management value. The decision to call the EDGUX100 installation exit is made each time a new data set is created on a tape based on whether a construct is assigned by ACS processing. You have the flexibility to identify one request to be handled by ACS and the next request to be handled by the EDGUX100 installation exit. For compatibility, DFSMSrmm passes vital record specification management value determined by the EDGUX100 installation exit using the pre-ACS interface in the MSPOLICY variable. You might use the vital record specification management value in the MSPOLICY variable as the base for MC assignment for system-managed tape. Even when you use SMS ACS support to assign management class names you can have separate policies for retention and movement by using a primary data set name vital record specification and a secondary management class vital record specification.

Use the ACS routine to assign the management class as the secondary vital record specification and the DFSMSrmm data set name vital record specification to assign the primary vital record specification. You must specify the EDGRMMxx parmlib OPTION VRSEL(NEW) operand to enable this support.

You can still use the EDGUX100 installation exit to check for either EXPDT= or ACCODE= specifying special values and override them to ensure correct retention processing by DFSMSrmm.

Using SMS Management Class to Retain Non-System-Managed Volumes

The DFSMSrmm EDGRMMxx parmlib OPTION VRSEL operand determines how DFSMSrmm assigns retention and movement policies. When VRSEL(NEW) is used, you can define policies using a vital record specification data set name mask, and a management class, or a vital record specification management value can also be assigned to manage a data set.

For each new tape data set, DFSMSrmm processing is done:

1. During pre-ACS processing for new tape data sets:

a. DFSMSrmm calls the EDGUX100 installation exit for a vital record specification management value. The vital record specification management value provides management policy and retention policy information for datasets.
b. DFSMSrmm returns the selected value in the MSPOLICY read-only variable.

2. During OPEN processing:
   a. DFSMSrmm calls ACS routines and passes environment information. Your ACS routine can set a management class name.
   b. If ACS processing does not return a management class name, DFSMSrmm calls the EDGUX100 installation exit to obtain a vital record specification management value.
   c. At OPEN time, DFSMSrmm records the specified management class or vital record specification management value at the data set level.

Making An ACS Management Class Assignment

To assign a management class, you must have the SMS subsystem active and have a valid SMS configuration.

You use the ACS routines to process the special calls that DFSMSrmm makes to the SMS subsystem for ACS processing. DFSMSrmm requests that the management class routine is run. The environment variable is set to *RMMVRS* so that you can differentiate allocation requests for system-managed data sets from requests by DFSMSrmm for a management class name.

Table 13 lists the read-only variables that are set for DFSMSrmm requests:

Table 13. SMS Read-only Variables Set by DFSMSrmm

&ACCT_JOB	&ACCT_STEP	&ACSENVIR	&DD
&DSN	&DSORG	&DSTYPE	&EXPDT
&FILENUM	&GROUP	&HLQ	&JOB
&LABEL	&LIBNAME	&LLQ	&NQUAL
&PGM	&STORGRP	&SYSNAME	&SYSPLEX
&UNIT	&USER	&XMODE	

1. Define vital record specifications for the management class names you plan to use as shown in Figure 34.

```
 ...
RMM ADDVRS DSNAME('CATALOG') WHILECATALOG
RMM ADDVRS DSNAME('ONSITE') DAYS COUNT(31)
RMM ADDVRS DSNAME('OFFSITE') CYCLES COUNT(5) LOCATION(STORE1) -
    NEXTVRS(DAYS90)
RMM ADDVRS NAME(DAYS90) DAYS COUNT(90)
 ...
```

Figure 34. Defining Vital Record Specifications for Non-System-Managed Volumes

2. You code your selection criteria and rules into the management class ACS routine as shown in Figure 35 on page 70.

```
PROC 1 MGMTCLAS
 ...
 /************************************************/
 /*   RMM POLICY FILTER LISTS                    */
 /************************************************/
 ...
 FILTLIST POOLA INCLUDE(USERA.**,USERY.KEEP.*) -
                EXCLUDE(USERA.POOLB.**)
 ...
  IF &ACSENVIR = 'RMMVRS' THEN
 /************************************************/
 /*   RMM VRS ASSIGNMENT DECISIONS               */
 /************************************************/
   DO
     SELECT (&DSN)
       WHEN (&OFFSITE) SET &MGMTCLAS = 'OFFSITE'
       WHEN (&ONSITE)  SET &MGMTCLAS = 'ONSITE'
     END
     /* CATCH EXPDT=99000                       */
     IF &EXPDT = '1999000' THEN SET &MGMTCLAS = 'CATALOG'
 ...
   END
 ...
END
```

Figure 35. Sample Management Class Routine for Managing Non-System-Managed Volumes

If ACS processing does not set the management class name, DFSMSrmm processing continues without using management class names.

When your ACS routine sets a management class, no call is made to the EDGUX100 installation exit to obtain a vital record specification management value. However, EDGUX100 is still called to update the DFSMSrmm copy of the JFCB expiration date if necessary.

Managing Volumes with Special Dates

If your current tape management system allows special expiration dates (such as EXPDT=99000) in JCL to identify management and retention requirements for system-managed volumes, you can manage those volumes by using management class to handle the special dates.

You can also use vital record specification management values to manage both system-managed volumes and non-system-managed tape volumes with JCL expiration dates that are specified with special dates. A vital record specification management value is a one-to-eight character name defined by your installation and used to assign management and retention values to tape data sets.

You define the management policies for management classes and for vital record specification management values using vital record specifications.

Use the DFSMSrmm EDGUX100 installation exit as described in “Chapter 10. Using DFSMSrmm Installation Exits” on page 195 to assign vital record specification management values to new tape data sets.

During inventory management VRSEL processing, DFSMSrmm uses the vital record specification management value as determined by the VRSEL parmlib option.

Using Volumes with Special Expiration Dates

If you have volumes with JCL expiration dates specified with special dates, you can use DFSMSrmm to manage those volumes. You use management classes for system-managed volumes. You use vital record specification management values for both system-managed and non-system-managed tape volumes.

For system-managed tape volumes:

- Define management classes to cover all the special dates used by your installation.
- Update your ACS routine to assign those management classes to data sets on tape.
- Define vital record specifications identifying the management policies for management classes.
- Run DFSMSrmm inventory management vital record processing to identify the volumes that should be retained based on the management classes that you define.

For both system-managed and non-system-managed tape volumes:

- Define vital record specification management values to cover all the special dates used by your installation.
- Tailor the EDGUX100 installation exit to assign the vital record specification management values you define to new tape data sets.
- Define vital record specifications identifying the management policies for vital record specification management values.
- Run DFSMSrmm inventory management vital record processing to identify the volumes that should be retained based on the vital record specification management values that you define.

See “Managing Volumes with Special Dates” on page 70 for more information.

Using Management Class to Retain System-Managed Volumes

This section presents the steps you need to take to use management class to retain system-managed volumes.

Step 1: Define Management Class Names

You need to define management class names that cover all the special dates used by your installation. For example, you can define a management class, M99000, for the special date 99000 and then define a vital record specification using the data set name M99000.

The management class name can be one to eight alphanumeric characters and must begin with an alphabetic character to be acceptable to the MVS data set naming standards that apply to DFSMSrmm vital record specifications.

Step 2: Update ACS Routine

Update your ACS routine to use an appropriate filter list and logic to assign management classes to data sets on tape. When a volume is opened, DFSMSrmm records the management class name you assign to new tape data sets using your ACS routine.

Figure 36 shows a management class ACS routine that maps the expiration date 99000 to a management class name M99000, and the expiration dates 99001 through 99009 to the management class name M990009.

```
PROC 1 &MGMTCLAS
/*******************************************************/
/*  DEFINE FILTER FOR KEEP WHILE CATALOGED  EXPDT=99000 */
/*******************************************************/
  FILTLIST SPECIAL_DATE9 INCLUDE('1999000')
/*******************************************************/
/*  DEFINE FILTER FOR UP TO 9 CYCLES                   */
/*******************************************************/
  FILTLIST SPECIAL_DATEC9 INCLUDE(199900*)
/*******************************************************/
/*  DEFINE FILTER FOR TAPE UNITS                       */
/*******************************************************/
  FILTLIST TAPEUNITS INCLUDE(TAPE*,T3420*,T3480*,T3490*,
                                  '3420','3480','3490',
                                  T3590*,'3590')
/*******************************************************/
/*  SELECT VALID MANAGEMENT CLASS                      */
/*******************************************************/
  SELECT
    WHEN (&EXPDT = &SPECIAL_DATE9 && &UNIT = &TAPEUNITS)
      SET &MGMTCLAS = 'M99000'
    WHEN (&EXPDT = &SPECIAL_DATEC9 && &UNIT = &TAPEUNITS)
      SET &MGMTCLAS = 'M99009'
    OTHERWISE
      SET &MGMTCLAS = 'NORMAL'
  END
END
```

Figure 36. Assigning Management Class to Data Sets on Tape

Step 3: Define Retention Policies for Management Class Names

You define policies for management classes by defining vital record specifications. Use the RMM subcommand ADDVRS with the DSNAME operand, or the DFSMSrmm Add Data Set VRS panel in the DFSMSrmm ISPF dialog to define vital record specifications. Use the data set name masks that match the management class names you have defined. See *z/OS DFSMSrmm Guide and Reference* for more information on defining vital record specifications.

Issue the command shown in Figure 37 to define a vital record specification that manages the special date 99000.

```
RMM ADDVRS DSNAME('M99000') WHILECATALOG
```

Figure 37. Special Date 99000 Vital Record Specification

You can define a vital record specification data set name mask that matches multiple management class names. For example you could define a data set name mask of M99* and use this mask to cover several management classes. Note that because the RMM ADDVRS subcommand with DSNAME operand can also be used to define a vital record specification for an individual data set, the management class name mask you specify for ADDVRS DSNAME is first used to match a data set name before any other mask.

Figure 38 on page 73 uses a data set name mask to define a vital record specification to manage any management class starting with M99. For example,

with this data set name mask you could manage special dates in the range 99001 through 99365.

```
RMM ADDVRS DSNAME('M99*')
```

Figure 38. Managing Management Classes Using a Data Set Name Mask

Step 4: Run DFSMSrmm Inventory Management Vital Record Processing

Run DFSMSrmm inventory management vital record processing to identify the volumes that should be retained based on the management classes you have defined. DFSMSrmm uses the management class assigned to the data set, rather than the data set name to select the appropriate vital record specifications. See “How Vital Record Processing Works” on page 267 for information about vital record processing.

Using the SMS Pre-ACS Interface

Using the SMS pre-ACS calls to DFSMSrmm, you can use any existing DFSMSrmm and EDGUX100 exit scratch pool and EDGUX100 exit policy assignment decisions as input to your SMS ACS logic to enable you to direct new data set allocations to the correct media. You can use SMS ACS to decide if data sets are to be system-managed or not system-managed. For system-managed data sets, you can decide if they are to be DASD or tape. For system-managed tape data sets, you can decide to which library or library type you would like the allocation directed. This can help you with VTS implementation.

To use DFSMSrmm and EDGUX100 decisions within your ACS processing, use the pre-ACS processing. Implement or customize the sample EDGUX100 exit (or the EDGCVRSX sample of EDGUX100) to feed pool and VRS management value information into ACS. Base your ACS processing decisions on the MSPOOL and MSPOLICY values that come from DFSMSrmm scratch pool and EDGUX100 exit processing. You can plan to move the EDGUX100 exit decisions into your SMS ACS routines to enable the EDGUX100 exit processing to be ignored or removed some time in the future.

DFSMSrmm always attempts to pass values for the MSPOOL and MSPOLICY ACS read-only variables. If you do not use an EDGUX100 exit the MSPOOL variable is set to the DFSMSrmm system based scratch pool decision. If you do not use the EDGUX100 exit, there is never a value set for MSPOLICY. DFSMSrmm sets a pre-ACS variable only if the variable has not yet been set using the pre-ACS exit. Since DFSMSrmm gets control after the installation exit, any vendor or customer decisions take precedence.

Managing Duplicate or Undefined Volume Serial Numbers

DFSMSrmm does not support duplicate volume serial numbers. DFSMSrmm cannot manage volumes not defined to it. These types of volumes are also known as foreign tape volumes.

If your removable media library contains duplicate volume serial numbers, you can:

- Change volume serial numbers if you want DFSMSrmm to manage those volumes.

- Use the EDGUX100 installation exit to request that DFSMSrmm ignore the duplicate volume serial numbers if you do not require that DFSMSrmm manage those volumes. This allows you to use the volumes with duplicate volume serial numbers.

If your removable media library contains undefined or foreign tape volumes:

- DFSMSrmm rejects them when they are mounted in response to a request for a scratch tape.

The following sections describe how to change duplicate volume serial numbers, how undefined volumes are ignored, and how to request that DFSMSrmm ignore duplicate and undefined volume serial numbers. See “Chapter 10. Using DFSMSrmm Installation Exits” on page 195 for information about using EDGUX100 to ignore duplicate volume serial numbers.

Using Volumes with Duplicate Volume Serial Numbers

DFSMSrmm does not support volumes with duplicate volume serial numbers but you can request that DFSMSrmm ignore such volumes while you use them. When DFSMSrmm ignores a volume, it records no information about the volume in the DFSMSrmm control data set, and performs no management functions for the volume.

To request that DFSMSrmm ignore a volume:

- Tailor the EDGUX100 DFSMSrmm installation exit which is called each time a volume is opened, to ignore a volume.
- Define a RACF FACILITY class entity, STGADMIN.EDG.IGNORE.TAPE.volser, to check user authorization.
- Authorize users to the STGADMIN.EDG.IGNORE.TAPE.volser resource.

If you want DFSMSrmm to manage a volume with a duplicate volume serial number, you must change volume serial numbers.

DFSMSrmm support for ignoring volumes does not provide for other system components to ignore the volume. Using the DFSMSrmm EDGUX100 installation exit, you can have DFSMSrmm ignore a volume that you use on the system, with the limitation that you cannot ignore a system-managed non-specific request. To ignore a system-managed volume and mount a non-system-managed volume, requires support that DFSMSrmm does not provide.

See “Managing Duplicate or Undefined Volume Serial Numbers” on page 73 for more information.

Changing Duplicate Volume Serial Numbers

If you want DFSMSrmm to manage volumes with duplicate volume serial numbers and you cannot remove one of the duplicate volumes serial numbers, you must change volume serial numbers.

Add the duplicate volume serial number, as follows:

- For volumes with no label (NL), file the duplicate volume serial number under a different unique volume serial number. Assign the volume a volume serial number equal to the shelf location, change its external label, and inform the owners of the change.

- For IBM standard label (SL) volumes, move all data sets on the volume to a different unique volume. Change the external labels and RACF profiles for the new volume. Inform the owners of the change and tell them to catalog the data sets on the new volume if they were cataloged on the original volume.

  You might need to do this step if you have received volumes containing software products.

Ignoring Duplicate or Undefined Volume Serial Numbers

DFSMSrmm ignores volumes that are not defined to DFSMSrmm for specific mount requests. For non-specific requests, DFSMSrmm ensures that a DFSMSrmm-managed scratch volume is mounted in response to the request. When DFSMSrmm ignores a volume, it:

- Does not record information about it in the DFSMSrmm control data set
- Does not validate that the correct volume has been mounted
- Performs no management functions for the volume

You can also request that DFSMSrmm ignore volumes defined to it. In this case, DFSMSrmm does not track volume use and cannot provide management functions you might expect.

If your system includes one of the following conditions, you must use the DFSMSrmm EDGUX100 installation exit to have DFSMSrmm ignore a volume:

- REJECT ANYUSE(*) is used in the parmlib to reject the use of a volume.
- The volume is in an automated tape library dataserver and is automatically defined to DFSMSrmm.
- You want to ignore a volume used for a non-specific output request.

If these conditions are not present, DFSMSrmm automatically ignores all volumes that are not defined to it without the use of the DFSMSrmm installation exit.

When you use the EDGUX100 installation exit, DFSMSrmm calls the exit each time a volume is opened, allowing you to decide if you want to use duplicate or undefined volumes. If you choose to use duplicate or undefined volumes, the installation exit checks the JCL specified EXPDT value for a special date of 98000, meaning that the volume should be ignored. If this special date is found, the exit then uses the installation exit parameter list to request that DFSMSrmm ignore the volume.

Note: 98000 is the special date used by the sample exit provided in SAMPLIB; you can change the sample based on your criteria.

Before DFSMSrmm ignores the volume, it ensures that the user who opened the volume is authorized to request that DFSMSrmm ignore the volume. DFSMSrmm uses a security resource in RACF FACILITY class, and issues a SAF RACROUTE TYPE=AUTH request with an entity name of:

```
STGADMIN.EDG.IGNORE.TAPE.volser
```

where `volser` is the volume serial number of the mounted tape volume.

“Chapter 10. Using DFSMSrmm Installation Exits” on page 195 describes the steps for using EDGUX100 to ignore certain volume serial numbers.

Chapter 4. Running DFSMSrmm with System-Managed Tape Libraries

DFSMSrmm provides the following support for system-managed tape libraries:

- Cartridge entry processing
- Cartridge eject processing
- Expiration management
- Volume-not-in-library support
- Movement between libraries and storage locations
- Partitioning the libraries with other systems
- VTS import/export processing
- Tracking and managing logical, physical, and stacked volumes

If you have volumes in an automated tape library dataserver, you need to reserve shelf space outside the automated tape library dataserver if you plan to eject the volumes and retain them in a manual tape library or non-system-managed tape library at any time. Volumes in a manual tape library can be logically ejected, left in the same shelf location and used as non-system-managed volumes.

DFSMSrmm identifies all volumes including volumes that reside in system-managed tape libraries using the volume serial number and the rack number.

- The volume serial number is the internal volume serial number recorded in VOL1 label on SL and AL type labels.
- The rack number is the external volume serial number

For volumes residing in system-managed tape libraries, a rack number is optional. If you specify a rack number for a volume residing in a system-managed tape library, the volume serial number and the rack number must be the same. You cannot change the rack number for volumes associated with system-managed libraries. You cannot define a rack number for logical volumes.

You can manage volume movement between system-managed libraries and storage locations, between system-managed libraries, and between non-system managed libraries and system-managed libraries by defining vital record specifications.

This chapter describes the support that DFSMSrmm provides for system-managed tape volumes. The functions described are what DFSMSrmm provides when you request that all functions are provided. Refer to the EDGRMMxx OPTION command SMSTAPE operand described in “Defining System Options: OPTION” on page 122 for details about controlling the functions that are provided by DFSMSrmm.

Using DFSMSrmm with System-Managed Tape Libraries

DFSMSrmm automatically adds volumes to the DFSMSrmm control data set during entry processing and when volumes are used. If a volume defined to DFSMSrmm is entered into a system-managed tape library without using the RMM CHANGEVOLUME command to set the volume location to the library name, DFSMSrmm updates the DFSMSrmm control data set volume record with the library name, library type, and volume entry status. DFSMSrmm does not update the home location name for the volume.

If the volume is not defined to DFSMSrmm and is entered into an automated tape library dataserver, DFSMSrmm automatically defines the volume in the DFSMSrmm control data set with information it obtains from the OAM entry user exit parameter

© Copyright IBM Corp. 1992, 2001

list as follows: LOCATION, STATUS, STORGRP, MEDIATYPE, RECORDINGFORMAT, SPECIALATTRIBUTES, COMPACTION, READDATE, WRITEDATE, EXPDT, LIBRARY NAME, TYPE, ENTRY STATUS, and HOME LOCATION. This means that all volumes entered into an automated tape library dataserver must be managed by DFSMSrmm, unless the library is to be partitioned and certain volumes left undefined. See “Partitioning System-managed Tape Libraries” on page 101 for details on partitioning the system-managed tape library.

You can define all volumes to DFSMSrmm before entering them into a library. We recommend you define private volumes prior to entry into the automated tape library dataserver and set the ISMF default cartridge entry status to scratch.

If you are inserting cartridges without predefining them to DFSMSrmm, and the default entry use attribute is private, then DFSMSrmm assigns a default owner. The default owner is set to the RACF Userid associated with the DFRMM started procedure name.

Associating Volumes and System-Managed Libraries

Specify a system-managed tape library name for a volume using the DFSMSrmm ISPF dialog or the RMM ADDVOLUME or RMM CHANGEVOLUME subcommand with the LOCATION operand. Figure 39 shows how to use the ADDVOLUME subcommand to specify the name of an automated tape library dataserver, ATL1, where volume A00001 resides:

```
RMM ADDVOLUME A00001 LOCATION(ATL1)
```

Figure 39. Specifying a Library Name for a Volume

You can provide the library name even if the volume does not yet reside in a system-managed tape library. When you provide a library name, DFSMSrmm checks if the library name is already defined in the TCDB. If the library name is defined in the TCDB, processing continues. If the library name is not defined, then processing fails.

DFSMSrmm records the following information about the library name:
- Library name
- Library type (manual or automated)

DFSMSrmm also records whether the volume is currently in the library.

If the volume is not defined in the TCDB, and the library name specified is an automated tape library dataserver, then DFSMSrmm sets the volume destination to the library name and waits for the volume to be entered. If the volume is not defined in the TCDB, and the library name specified is a manual tape library, then DFSMSrmm uses manual cartridge entry processing so the TCDB is updated for the volume.

Cartridge Entry Processing

DFSMSrmm is called at cartridge entry time by CBRUXENT installation exit which DFSMSrmm supplies. During cartridge entry processing in an automated tape library dataserver, the installation exit passes the external volume serial number. DFSMSrmm checks for the existence of a volume or a rack of the same number. When there is a conflict, the cartridge entry is denied. If a volume is defined to DFSMSrmm as ″not for use on MVS″ or is not defined to DFSMSrmm and matches

the REJECT ANYUSE prefixes, and is entered into a tape library dataserver, DFSMSrmm sets a return code telling OAM not to process the volume on this system.

If a volume is entered into a library that does not match the library name already defined for it, DFSMSrmm updates the library name in the control data set. The home location name is not updated. If a volume is 'intransit' and the destination is different than the library the volume is entering, the cartridge entry is prevented.

Manual Cartridge Entry Processing

DFSMSrmm uses manual cartridge entry processing to add information about a volume residing in a manual tape library into the TCDB. The OAM macro CBRXLCS is used to get the volume information added to the TCDB when a volume is to reside in a manual tape library. The information provided by DFSMSrmm using CBRUXENT, is the same as for automated libraries, and includes: storage group name, recording format, compaction, special attributes, owner name and expiration date.

DFSMSrmm uses the volume's media type as defined to DFSMSrmm when requesting manual cartridge entry; you must ensure that DFSMSrmm has the correct media type to avoid allocation and mount problems when the volumes are later used. You use the RMM ADDVOLUME or CHANGEVOLUME subcommands with the MEDIATYPE operand to set the media type.

When volumes are entered into a manual tape library, DFSMSrmm ensures that both private and scratch volumes meet these DFSMS requirements: that only supported label types are used and that internal volume serial number matches external volume serial number.

Scratch Pool Management

The DFSMSrmm scratch pool function in VLPOOL definitions is not honored for scratch mount requests on automated system-managed library resident drives, even if the storage group assigned matches a VLPOOL name. In an automated system-managed library, DFSMS and the Library Manager control the pooling of scratch volumes with one pool for each media type. There is currently no method to direct mount processing to select a subset of the volumes in a scratch category.

Ejecting Volumes from System-Managed Libraries

You can eject physical volumes from a system-managed library using various methods. One way is to list a number of volumes and then enter eject commands from the list. You normally use export processing to eject logical volumes. For information about export processing, see "Using DFSMSrmm with the IBM Virtual Tape Server" on page 85.

You can also eject volumes from a system-managed library by changing the library name with the RMM CHANGEVOLUME subcommand. When you issue the command, DFSMSrmm requests that the volume is ejected from the original library. Information about the volume is changed in the control data set and the TCDB record is optionally deleted. If the target library is an automated tape library dataserver, the operator must physically transfer the volume. If the source and target libraries are both manual tape libraries, then physical movement is only needed if the volume is to be moved to another shelf location.

You can also mark a volume as ejected from a system-managed library or change the location name to SHELF when the library is not known or offline by using the RMM CHANGEVOLUME subcommand with the FORCE operand. To use the FORCE operand, you must have access to the STGADMIN.EDG.MASTER and STGADMIN.EDG.FORCE RACF profiles. When you use the FORCE operand to update a volume in a system-managed library, DFSMSrmm attempts to update the TCDB but continues processing when it cannot make the update, so that your request to update DFSMSrmm is completed even when the TCDB is not updated.

DFSMSrmm does not automatically eject volumes from system-managed libraries after completing vital record processing and storage location management processing. See “How Storage Location Management Processing Works” on page 272 for information about adding a job step to eject volumes at a time you determine.

The DFSMSrmm control data set is updated even if ejects are not driven by DFSMSrmm. The eject is detected using the OAM eject installation exit and DFSMSrmm can control the disposition of the TCDB volume information. During eject processing, DFSMSrmm checks the setting of the DFSMSrmm EDGRMMxx OPTION SMSTAPE(PURGE) operand to determine whether to request deletion of volume information from the TCDB. This optionally overrides the ISMF default cartridge eject option you might have specified. If the volume record is not deleted, DFSMSrmm sets the volume destination information into the TCDB volume shelf location field.

Figure 40 shows how you can eject a volume from an automatic tape library or from a manual tape library to a convenience output station using the RMM CHANGEVOLUME subcommand or the RMM DELETEVOLUME subcommand.

```
RMM CHANGEVOLUME A12345 EJECT(CONVENIENCE)
RMM CHANGEVOLUME A12345 LOCATION(new_lib)
RMM CHANGEVOLUME A12345 LOANLOC(set_loc)
RMM DELETEVOLUME A12345 REMOVE
RMM DELETEVOLUME A12345 FORCE
```

Figure 40. Requesting the Eject of a Volume

You can specify the EJECT operand on the RMM CHANGEVOLUME and DELETEVOLUME subcommands. Specify the EJECT(BULK) operand to direct the ejected volume to the high capacity input/output station. Specify the EJECT(CONVENIENCE) operand to direct the ejected volume to the convenience output station. If you specify EJECT(BULK) and the high capacity output station is not installed, then the eject is routed to a convenience output station. If there is no convenience output station, the eject is then routed to a single cell facility. In a manual tape library, DFSMSrmm ignores the BULK and CONVENIENCE values and the cartridge is ejected.

Note: The RMM CHANGEVOLUME subcommand with the HOME operand does not cause an eject or a move as it is only used to update the home location name.

Returning Volumes to the System-Managed Library

Normally system-managed volumes remain resident in the system-managed library unless they are removed for movement to an offsite location, for physical inspection, or for error recovery. When volumes are to be returned to an automated system-managed library, enter the volumes using the appropriate entry station.

DFSMSrmm is notified that the move has taken place. When volumes are returned to a manual system-managed library, you must confirm the movement to DFSMSrmm so that DFSMSrmm can initiate entry processing.

There might be times when a volume is not in a system-managed library but is needed for processing to continue. z/OS includes a function called Volume-Not-In-Library (VNL) processing that allows a volume to be identified for re-entry to a system-managed library at various stages of system processing:

- Job step setup
- Device allocation
- Library mount

The CBRUXVNL OAM installation exit provides support so that a volume that is needed for processing to continue can be entered back into the library. Logical volumes that are exported must be imported to enable them to be used for processing.

For volumes defined in the DFSMSrmm control data set, information is provided to determine if the volume can be entered into the library. DFSMSrmm issues messages that provide location, movement, and status information during VNL processing.

If the volume entering the library is marked as “intransit” to other than a system-managed library, ensure that the move for the volume is confirmed as completed. Otherwise the volume entry will be rejected.

Refer to “Managing System-Managed Tape Library Volumes: EDGLCSUX” on page 179 for information on using CBRUXVNL and other OAM installation exits.

Volume-Not-In-Library Processing

When a volume is requested for a job and is not in a system-managed tape library, the DFSMSrmm supplied CBRUXVNL exit is called so the volume can be inserted into a library to prevent job failures from occurring. The CBRUXVNL exit can be modified to suit your requirements.

CBRUXVNL calls DFSMSrmm once to retrieve volume information, and then for a limited set of circumstances, it calls DFSMSrmm a second time to request the operator to enter the volume into a system-managed tape library. The second call is made when:

- CBRUXVNL is called from job setup and the exit determines that the volume needs to be directed to a system-managed tape library.
- CBRUXVNL is called from other than job setup.

CBRUXVNL checks for the requested volume as follows:

- If the volume resides in a loan location and the volume is system-managed, the exit fails the request.
- The exit attempts to get a volume entered into a system-managed library if the volume can be used on the system and when:
  - The volume is in location SHELF and is not moving to a storage location, and its home location is system-managed.
  - DFSMSrmm volume information indicates the volume resides in a system-managed library.
  - The volume destination is a system-managed location.

DFSMSrmm uses the information to build a WTOR message that includes the volume location and that prompts the operator to enter the volume into the system-managed library. For volumes residing in a VTS, DFSMSrmm returns additional information for a volume. The information indicates if the volume is a physical volume or a logical volume and the stacked volume on which the logical volume is exported.

The CBRUXVNL exit does not allow a volume to be used when:
- The volume is pending release or is in scratch status.
- The initialize volume action is pending.
- The volume is not to be used on MVS.

In all other cases the CBRUXVNL exit allows the volume to be used but a non-system managed tape drive is allocated by the system.

Confirming Volume Movement For System Managed Libraries

DFSMSrmm automatically confirms volume moves during cartridge entry processing. When you manually confirm the moves for volumes to an automated tape library dataserver, DFSMSrmm checks for the volume and library name in the TCDB and only confirms movements if the volume is library resident. DFSMSrmm If there is a mismatch between the information in the TCDB and the DFSMSrmm control data set, use the RMM CHANGEVOLUME subcommand with the LOCATION operand to update the destination information in the control data set to match the library name in the TCDB.

If a volume is returning to a manual tape library, there is no automatic confirmation. You must explicitly confirm that the move has taken place when the volume is entered into the library. When you confirm that a volume has moved to a manual tape library, DFSMSrmm requests that the volume location in the TCDB is updated with the new location. DFSMSrmm also changes the volume location information in the TCDB when you issue the DFSMSrmm CHANGEVOLUME *volser* LOCATION (*mtl_name*) to change the volume location to a manual tape library.

If you specify the RMM CHANGEVOLUME subcommand with the EJECT operand for a volume for which no move has been identified, DFSMSrmm does not set a destination for the volume but the volume is set to be 'intransit'. Once the volume is ejected and cannot be entered again, you should specify the location where the volume is placed and then confirm the move.

When you specify the RMM CHANGEVOLUME subcommand with the LOCATION operand, DFSMSrmm sets a destination for the volume. You only need to confirm the move after the eject.

Defining System-Managed Volume Information

System-managed tape volumes are defined in the tape configuration database (TCDB). The TCDB is an integrated catalog facility (ICF) user catalog marked as a volume catalog (VOLCAT) containing tape volume and tape library records. For more information about the TCDB, see *z/OS DFSMS Migration* and *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries*.

System-managed tapes should be defined to the DFSMSrmm control data set for the volumes to be managed by DFSMSrmm.To ensure that volumes are defined to both DFSMSrmm and the TCDB, use the RMM ADDVOLUME subcommand for volumes not yet known to DFSMSrmm, and the RMM CHANGEVOLUME

subcommand for volumes already defined to DFSMSrmm but not the TCDB. For information on using DFSMSrmm commands, see *z/OS DFSMSrmm Guide and Reference*.

When you use DFSMSrmm to request that a volume should move to a system-managed tape library, DFSMSrmm ensures volume information is recorded in the TCDB.

Keeping System-Managed Volume Information Consistent

DFSMSrmm uses information in the TCDB to verify requests or to obtain information about volumes being added to DFSMSrmm. When you define volumes to DFSMSrmm using the RMM ADDVOLUME subcommand with the STATUS(VOLCAT) operand, DFSMSrmm uses TCDB information to update the DFSMSrmm control data set. If there is a conflict between information in the TCDB and the control data set, DFSMSrmm uses the value in the TCDB.

You can control the way DFSMSrmm updates the information in the TCDB by specifying the DFSMSrmm EDGRMMxx parmlib OPTION command SMSTAPE operand and the OPTION command OPMODE operand. See “Defining System Options: OPTION” on page 122 for information about the DFSMSrmm EDGRMMxx parmlib OPTION command. When DFSMSrmm is running in PROTECT mode, DFSMSrmm updates the TCDB. If you are running DFSMSrmm in other modes, you can decide if and when you want DFSMSrmm to update the TCDB. DFSMSrmm updates the following TCDB information:

Volume owner information
: DFSMSrmm uses the first 8 characters of the 64 bytes of owner information in the TCDB to store the DFSMSrmm volume owner information. DFSMSrmm does not overlay any information you might have entered into the first 8 bytes. Keep the first bytes of the field blank and DFSMSrmm maintains the volume information for you.

Expiration date
: The expiration date is updated in the tape volume record whenever the DFSMSrmm control data set is updated.

Volume use attribute (status)
: DFSMSrmm updates this information when an RMM TSO subcommand is issued and a volume’s status is changed. For example, if you issue the RMM CHANGEVOLUME subcommand with the STATUS(USER) operand or the RMM GETVOLUME subcommand, the TCDB volume use attribute is changed to PRIVATE. Volume status is also changed when volumes are returned to scratch status during inventory management.

You can use the DFSMSrmm EDGUTIL utility to:

- Check the consistency of the control data set with the TCDB and the Library Manager database and use EDGUTIL MEND(SMSTAPE) to synchronize the TCDB and Library Manager database from the DFSMSrmm control data set.
- Mend information in the control data set based on information in the TCDB and the Library Manager database.

For more information about EDGUTIL, see “Creating and Verifying the Contents of the Control Data Set: EDGUTIL” on page 299.

Use the RMM CHANGEVOLUME subcommand with the LOCATION(*mtl_name*) operand to rebuild manual tape library information in the TCDB.

If you use DFSMSrmm, ISMF, or operator commands to eject a volume, DFSMSrmm notes that the volume is 'intransit'. During eject processing, DFSMSrmm checks the setting of the DFSMSrmm EDGRMMxx OPTION SMSTAPE(PURGE) operand to determine whether to request deletion of volume information from the TCDB. This optionally overrides the ISMF default cartridge eject option you might have specified. If the volume record is not deleted, DFSMSrmm sets the volume destination information into the TCDB volume shelf location field.

Initializing Scratch Volumes in System-Managed Libraries

You can use these methods to label volumes in an automated tape library dataserver.

- Use EDGINERS or IEHINITT to label them before they are entered.
- For scratch volumes you can leave the labeling to be performed the first time the volume is used for output once they enter the automated tape library dataserver. Labeling is performed by DFSMSdfp during OPEN processing.
- Use EDGINERS or IEHINITT for volumes in all system-managed tape libraries.

To use the EDGINERS initialize function to label volumes you can set the DFSMSrmm initialize action by using the DFSMSrmm ISPF dialog or the RMM TSO subcommand.

If you set the initialize action for a scratch volume before it enters an automated tape library dataserver and then enter the volume into the automated tape library dataserver, DFSMSrmm defers initialization to DFSMSdfp labeling support. If you later eject the scratch volume before it is used DFSMSrmm reinstates the initialize action.

If you set the initialize action for a scratch volume while it is resident in an automated tape library dataserver, the initialize action is set outstanding and you must use the DFSMSrmm EDGINERS utility to create the labels. See "Using EDGINERS with System-Managed Tape Libraries" on page 321 for additional information.

When you use the DFSMSdfp labeling support in an automated tape library dataserver, DFSMSdfp obtains the volume serial number from the library vision system, but still issues the WTOR IEC704A to prompt the operator to provide optional owner information. The IEC704A message text includes an indicator that the volume is system managed. Normally, DFSMSrmm provides information to bypass the issuing of the message. If DFSMSrmm is running in record mode or a volume is rejected in warning mode, the WTOR is issued and must be replied to by the operator.

The DFSMSdfp labeling support for manual tape libraries cannot obtain the volume serial number from the vision system. DFSMSdfp still uses the WTOR IEC704A to prompt the operator for it.

You can decide to exploit DFSMSdfp automatic labeling to avoid unnecessary mounting of volumes or use EDGINERS before volumes enter the tape library dataserver or after volumes are resident in the tape library dataserver.

DFSMSrmm Support for Storage Group Name

You can specify a storage group name for each volume defined in the control data set. Setting the name is optional.

DFSMSrmm validates the storage group name using services provided by the Storage Management Subsystem. For system-managed volumes, DFSMSrmm passes the storage group name to OAM unless the volume is in scratch status. For non-system managed volumes you can use the assigned storage group names for scratch pooling. For more information about using SG for scratch pooling, see "Using Storage Groups for DFSMSrmm Scratch Pooling" on page 63.

When a volume is moved from one system-managed tape library to another, DFSMSrmm does not change the storage group name. OAM validates the storage group name during entry to the new library and fails the entry if the storage group is not defined for use in that new library.

DFSMSrmm uses the OAM installation exits to record any changes that ISMF and Automatic Class Selection Routine processing make to the storage group name. This function enables DFSMSrmm to provide the storage group name at cartridge re-entry time, if the volume information had been removed from the TCDB.

For information on how DFSMSrmm records data class, management class, storage class, and storage group information, see *z/OS DFSMSrmm Guide and Reference*.

Using DFSMSrmm with the IBM Virtual Tape Server

DFSMSrmm supports VTS libraries such as automated system-managed libraries with extensions to that support to handle the special requirements for different volume types and functional capability. DFSMSrmm supports virtual tape server import/export in different ways depending on whether or not DFSMSrmm stacked volume support is enabled. When you enable stacked volume support, DFSMSrmm tracks logical volumes and stacked volumes.

When you do not enable stacked volume support, DFSMSrmm does not track the stacked volumes. DFSMSrmm supports the IBM Peer-to-Peer VTS by ensuring that you cannot use the names of distributed VTS libraries with DFSMSrmm. You must only use the names of consolidated libraries with DFSMSrmm. See *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries* for information about using OAM for virtual tape server support.

See *z/OS DFSMSrmm Reporting* for information about the DFSMSrmm EDGRPTD utility that you can use to obtain information about volumes that reside in virtual tape server libraries. See *Magstar 3494 Tape Library Introduction and Planning Guide*, *Magstar 3494 Tape Library Operator Guide*, *Magstar 3495 Tape Library Introduction and Planning Guide*, and *Magstar 3495 Tape Library Operator Guide* for information about the format for the import and export lists.

Defining Logical Volumes in a Virtual Tape Server Library

A logical volume is a volume that resides in a virtual tape server library either on DASD (in the tape volume cache as a virtual volume) or on a stacked volume (as a logical volume) and is referenced from the host as if it were a physical volume.

When volumes are automatically added to DFSMSrmm, DFSMSrmm sets the volume type based on where the volume resides. If the volume resides in a VTS, DFSMSrmm sets the volume type to logical. If the volume does not reside in a VTS, DFSMSrmm sets the volume type to physical. You can chose to define the volumes to DFSMSrmm rather than having the volumes automatically defined when they are entered into the library. You must ensure that you specify the correct volume type

for each volume that you define. If you do not specify the correct volume type for volumes residing in system-managed tape libraries, these volumes will not be processed successfully.

To ensure that all logical volumes are correctly identified to DFSMSrmm as logical volumes, use the DFSMSrmm TSO subcommand example shown in Figure 41 to change the volume type of previously defined volumes. DFSMSrmm allows you to identify any volume as a logical volume as long as it is not resident in a system-managed automated tape library dataserver.

```
RMM SEARCHVOLUME VOLUME(*) LIMIT(*) OWNER(*) LOCATION(vts) -
 CLIST('RMM CHANGEVOLUME ',' TYPE(LOGICAL)')
 EXEC EXEC.RMM.CLIST
```

Figure 41. Changing Volume Type

Logical Volume Cartridge Entry Processing

DFSMSrmm processes new logical volumes and imported volumes differently at entry time.

- DFSMSrmm automatically defines both new logical volumes and imported logical volumes if they are not defined to DFSMSrmm already. DFSMSrmm does not define rack numbers for these volumes.
- DFSMSrmm checks the rack number for a logical volume that is already defined to DFSMSrmm. If the rack number does not match the logical volume's volume serial number, DFSMSrmm fails the entry request and issues message EDG8189I. If the rack number matches the volume serial number, DFSMSrmm continues processing the request. DFSMSrmm frees the rack number for the logical volume so the logical volume is no longer associated with the rack number.
- DFSMSrmm checks that an imported logical volume that is already defined to DFSMSrmm, is also a logical volume and does not reside in a virtual tape server library. When a logical volume is being imported, DFSMSrmm checks that the volume, if already defined to DFSMSrmm, is correctly defined as an exported logical volume. DFSMSrmm issues message EDG8183I when the entry request fails.
- DFSMSrmm accepts new scratch logical volumes that match existing scratch logical volumes. DFSMSrmm updates the volume information with information for the new volume. If the volume serial numbers match but the volume is not defined as a scratch volume, DFSMSrmm fails the entry request and issues message EDG8182I.

Table 14 describes the entry processing decisions DFSMSrmm makes.

Table 14. DFSMSrmm Entry Processing Decisions

Case	Physical Volume	Stacked Volume	Logical Volume	Imported Volume
Volume is not defined; no REJECT.	Added	Not applicable	Added scratch or private	Added private
Volume is not defined; REJECT.	Ignored	Not applicable	Ignored	Ignored
Volume is defined for use with MVS.	Updated	Not applicable	Updated	Updated
Volume is defined for use with VM.	Ignored	Not applicable	Ignored	Ignored

Table 14. DFSMSrmm Entry Processing Decisions (continued)

Case	Physical Volume	Stacked Volume	Logical Volume	Imported Volume
Rack number associated with the volume is the same as the volume serial number.	Updated	Not applicable	Updated; DFSMSrmm clears the rack number.	Updated; DFSMSrmm clears the rack number.
Rack number associated with the volume is not the same as the volume serial number.	Entry fails; DFSMSrmm issues EDG8189I.	Not applicable	Entry fails; DFSMSrmm issues EDG8189I.	Import fails; DFSMSrmm issues EDG8189I.
No rack number is present.	Updated	Not applicable	Updated	Updated
Volume is a scratch and not logical volume.	Updated	Not applicable	Entry fails; DFSMSrmm issues EDG8182I.	Import fails; DFSMSrmm issues EDG8182I.
Volume is private and not a logical volume.	Updated	Not applicable	Entry fails; DFSMSrmm issues EDG8182I.	Import fails; DFSMSrmm issues EDG8182I.
Volume is a logical volume and not an exported volume.	Entry fails; DFSMSrmm issues EDG8184I.	Not applicable	Update	Import fails; DFSMSrmm issues EDG8183I.
Volume is a logical exported volume.	Entry fails; DFSMSrmm issues EDG8184I.	Not applicable	Entry fails; DFSMSrmm issues EDG8184I.	Updated
Volume destination is not the library.	Entry fails; DFSMSrmm issues EDG8192I.	Not applicable	Entry fails; DFSMSrmm issues EDG8192I.	Import fails; DFSMSrmm issues EDG8192I.
Volume owner is not valid.	Entry fails; DFSMSrmm issues EDG8195I.	Not applicable	Entry fails; DFSMSrmm issues EDG8195I.	Import fails; DFSMSrmm issues EDG8195I.
Defined rack number=vol is not available.	Entry fails; DFSMSrmm issues EDG8198I.	Not applicable	Entry fails; DFSMSrmm issues EDG8198I.	Import fails; DFSMSrmm issues EDG8198I.
Maximum retention period is exceeded.	Entry fails; DFSMSrmm issues EDG8196I.	Not applicable	Not applicable	Import fails; DFSMSrmm issues EDG8196I.

DFSMSrmm Support for Logical Volumes

The DFSMSrmm support for defining and entering logical volumes is common regardless of how you set up DFSMSrmm. Other functions supported by DFSMSrmm are dependent on how you request stacked volumes to be managed. For details of how DFSMSrmm supports export and import processing for logical volumes refer to “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled” on page 89 and “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support Is Not Enabled” on page 93.

DFSMSrmm Support for Stacked Volumes

A stacked volume is a volume in a virtual tape server library that is used to store one or more logical volumes.

DFSMSrmm can manage volume movement based on the logical volume or the stacked volume. You control the way DFSMSrmm supports stacked volumes by doing nothing or by enabling stacked as described in “Enabling Stacked Volume Support” on page 95. No matter what support you choose, you can always use the

DFSMSrmm TSO subcommands to add, change, or delete information about stacked volumes. You can also perform export and import processing of logical volumes.

If you do nothing and do not enable stacked volume support, DFSMSrmm bases volume movement on the logical volume. DFSMSrmm records the stacked volume as the in container value but does not use the stacked volumes to determine volume movement. See “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support Is Not Enabled” on page 93 for details about how DFSMSrmm supports stacked volumes when stacked volume support is not enabled.

If you enable stacked volume support, DFSMSrmm tracks stacked volumes and bases volume movement on the stacked volume. See “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled” on page 89 for details about how DFSMSrmm supports stacked volumes when stacked volume support is enabled.

Managing Stacked Volumes

Stacked volumes normally start and end their movement in a VTS automated tape library. The host system is not notified when stacked volumes enter or leave an automated tape library so stacked volumes cannot be managed the same way that physical volumes in an automated tape library are managed.

When you use a DFSMSrmm command for a stacked volume, DFSMSrmm checks both the TCDB and the Library Manager database to see if the volume is known. If the volume is not known to the Library Manager, you cannot define the volume as being in the VTS library, but the destination is set to the VTS library name. Once the volume is entered into the VTS, you can use the CHANGEVOLUME subcommand with CONFIRMMOVE to inform DFSMSrmm that the volume is now in the VTS.

Defining Stacked Volumes to DFSMSrmm

You must use the Library Manager console to ensure that the ranges of stacked volumes for containers are defined correctly to avoid accidentally entering stacked volumes into the library as native volumes. DFSMSrmm ensures at cartridge entry processing time that a physical or logical volume does not duplicate a stacked volume defined to DFSMSrmm.

Defining stacked volumes to DFSMSrmm is optional. If you do not define them, DFSMSrmm defines them automatically at export time only if stacked volume support is enabled. You use the RMM ADDVOLUME subcommand to define stacked volumes to DFSMSrmm. Stacked volumes are defined to DFSMSrmm as volumes with a type of stacked. There is no automatic host notification when stacked volumes enter the VTS, leave the VTS, or change category, so you must use DFSMSrmm commands if you want to always have them defined to DFSMSrmm.

Changing Stacked Volume Information

Once you have defined a stacked volume to DFSMSrmm you do not normally need to change information about that volume. Once stacked volume support is enabled, DFSMSrmm manages the information about stacked and logical volumes and the movement of stacked volumes as they are exported from the VTS library.

You do need to use the CHANGEVOLUME command to confirm the movement of the stacked volume, just as you would for a physical volume that was moving.

Assigning a Shelf Location for a Stacked Volume

You can optionally assign a shelf location to a stacked volume. When a stacked volume is resident in a VTS library, no shelf location is needed; however, if it is stored outside the VTS assigned to location SHELF you can assign a rack number using either the RACK or POOL operands. Specify RACK with a specific rack number or use POOL to allow DFSMSrmm to select the first empty rack number in that pool of shelf locations. During normal processing, DFSMSrmm storage location management processing assigns shelf locations to a stacked volume that must move to a shelf-managed storage location.

Deleting Stacked Volume Information

You can only delete an empty stacked volume. All logical volumes must previously have been imported or removed from the stacked. To remove a volume from a stacked volume, use the RMM CHANGEVOLUME subcommand with the CONTAINER(' ') operand to clear the container name.

DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled

With DFSMSrmm stacked volume support enabled, you can manage the movement of logical volumes using stacked volumes. To enable stacked volume support, see “Enabling Stacked Volume Support” on page 95.

To ensure that stacked volumes are managed correctly, DFSMSrmm inventory managemetn processing checks that stacked volumes reside in a library. At the completion of export processing for a single stacked volume, DFSMSrmm uses the required location of the stacked volume to attempt to start its movement. If the required location is not shelf-managed, DFSMSrmm sets the destination but does not mark the stacked volume as being 'intransit'. If the required location is shelf-managed, DFSMSrmm storage location management processing starts the volume move. Inventory management checks to see if closed, not-empty stacked volumes still reside in their location, and marks those no longer resident as 'intransit'. Storage location management processing starts movement of stacked volumes by assigning bin numbers for storage locations and setting the destination for the volume.

The next time inventory management is run, DFSMSrmm checks the library to see if the stacked volume has been ejected, and if so, the stacked volume is marked as being 'intransit'. Those stacked volumes which are 'intransit' to a destination VTS are checked for library residence at their destination and the move confirmed if found resident. Stacked volumes that are 'intransit' to storage locations are confirmed only if a global confirm move has been requested for the location and destination pair. When stacked volumes move from storage locations they are set 'intransit' by storage location management processing. The result is that DFSMSrmm can automatically determine some of the moves for stacked volumes and needs you to confirm those to storage locations.

Resolving Movement Conflicts

If there is a movement conflict for multiple logical volumes in a stacked volume, DFSMSrmm resolves the conflict by using location priority to determine where the stacked volume should be moved. See “Moving Volumes” on page 270 for information about how DFSMSrmm prioritizes volume movement.

Confirming Stacked Volume Movement

You confirm the movement of stacked volume containers to storage locations when their movement is completed. Use the RMM CHANGEVOLUME * CMOVE

subcommand. The READYTOSCRATCH option is not applied to stacked volume moves and container moves are confirmed either with the ALL option or the NOTREADYTOSCRATCH option.

The stacked volume is used to identify the media that is used for the export container volume, to track its location, and to aggregate the logical volumes contained in the volume. All movement for exported logical volumes is managed and tracked using the stacked volume. You can move a stacked volume manually, but normally you control the movement automatically using vital record specifications. The vital record specifications identify movement for data sets on logical volumes. The movement specified for the logical volumes in the stacked volume container direct the movement of the stacked volume. DFSMSrmm automatically defines stacked volumes at EXPORT time. DFSMSrmm keeps track of the ″in container″ information only while the logical volume is exported.

DFSMSrmm Support for Export Processing When Stacked Volume Support is Enabled

To use DFSMSrmm for export processing, you must first make sure that the volume information reflects the most current required location information. Perform DFSMSrmm inventory management vital record processing to set the required location for any volume moves that are required.

As logical volumes are exported, DFSMSrmm tracks the ″in container″ stacked volume and drives the stacked volume movement based on the required location of the contained volumes.

Use DFSMSrmm export processing to remove logical volumes from a VTS.

1. Define vital record specifications that specify locations to which data sets in the VTS should be moved.
2. Run DFSMSrmm inventory management vital record processing to determine which logical volumes should be moved and to set the required location for each volume to be moved.
3. Create a list of volumes to export after you run vital record processing. The required moves are volume moves that are identified during vital record processing or by changes made when you issue the RMM CHANGEVOLUME subcommand. Use the RMM SEARCHVOLUME subcommand with the REQUIRED and CLIST operands for each storage location to obtain volume information for the list as shown in Figure 42. DFSMSrmm returns a list of volumes to export that you can use as input for creating the export list logical volume file 1. You can use the EDGJIMPC sample to reformat the CLIST file for use in the export list.

```
RMM SEARCHVOLUME VOLUME(*) OWNER(*) LIMIT(*) REQUIRED(STORE1) LOCATION(vts) -
   CLIST(,' STORE1')
```

Figure 42. Setting the Required Location for Logical Volumes

See the *z/OS DFSMSrmm Guide and Reference* for information about the RMM SEARCHVOLUME subcommand. See these examples in SYS1.SAMPLIB for the format and required files for the export list volume.

- CBRSPSXP is the sample JCL for export list volume scratch request.
- CBRSPPXP is the sample JCL for export list volume private request.

When stacked volume support is enabled, you can no longer track the movement of logical volumes using the LOCATION and DESTINATION fields of the volume information. Any volume exported on a stacked volume resides in a container and has no location name assigned for it. DFSMSrmm continues to manage the volume movement using vital record specifications for data sets and volumes but uses this information only to set the REQUIRED location. DFSMSrmm never assigns a destination to a logical volume.

4. Start the export process as described in the *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries* using the LIBRARY EXPORT command or use the CBRSPLCS sample program.

   The VTS export process runs asynchronously to DFSMSrmm processing. Once the export request has been initiated, VTS library signals trigger DFSMSrmm actions related to export processing.

   During the VTS export process, logical volumes are copied to a stacked volume and the stacked volume is completed. For each logical volume copied to the stacked volume, DFSMSrmm is notified of both the logical volume and stacked volume. DFSMSrmm updates the DFSMSrmm control data set with the volume serial number of the stacked volume as the 'in container'.

   During export processing, DFSMSrmm updates the 'In container' value for each logical volume exported. DFSMSrmm updates the stacked volume and tracks export completion, marking the stacked volume closed.
5. Run DFSMSrmm inventory management storage location management to set destinations for the volumes and to make bin assignments and create an extract data set after VTS export processing is completed.
6. Create movement report and pick lists by using the DFSMSrmm EDGRPTD report utility.
7. Use the movement reports to eject the stacked volumes from the VTS using the Library Manager and move them to the destination storage location. Transfer the stacked volumes in the export hold category to the exit station using the Library Manager console. Physically move the stacked volumes listed in your movement report from the VTS exit station to the destination storage location.
8. Confirm that volumes have been moved. When the volumes have been moved, use the RMM CHANGEVOLUME subcommand, as shown in Figure 43 to confirm the completion of the movement of volumes. When the stacked volume is moved, you must confirm the move for all the logical volumes that reside on the volume. You can use the RMM CHANGEVOLUME subcommand with the CONFIRMMOVE operand to confirm the move. You must confirm the move of stacked volumes from the VTS. When DFSMSrmm stacked volume support is enabled, confirm that the stacked volume has moved.

```
RMM CHANGEVOLUME * CONFIRMMOVE(vts,ALL)
```

Figure 43. Confirming Volume Moves for Exported Volumes

DFSMSrmm Support for Import Processing When Stacked Volume Support Is Enabled

DFSMSrmm supports the importing of logical volumes that are defined to DFSMSrmm or not defined to DFSMSrmm. During import processing for a logical volume, DFSMSrmm automatically adds the volume information to the DFSMSrmm control data set or leaves the volume to be processed on another system. Note that DFSMSrmm does not automatically add rack numbers for logical volumes because rack numbers are not supported for logical volumes.

You can initiate the import of logical volumes as follows.

1. Use the Library Manager console to transfer stacked volumes to be imported from the Unassign category to the Import category. See *3495 Tape Library Dataserver Introduction* and *3495 Tape Library Dataserver Operator's Guide* for more information about the Library Manager.
2. Create an import list. See these examples in SYS1.SAMPLIB for the format and required files for the import list volume.
   - CBRSPSIM is the sample JCL for import list volume scratch request.
   - CBRSPPIM is the sample JCL for import list volume private request.

   To create the volume list for file 1 of the import list logical volume, you can search in the DFSMSrmm control data set, tailor the DFSMSrmm report extract data set, or use any other method to identify the volumes to be imported.

   You can use the RMM SEARCHVOLUME subcommand to build the list of logical volumes with their containing stacked volume and status as shown in the following examples. When you specify the TYPE(LOGICAL) operand, DFSMSrmm returns the container volume serial number, logical volume serial number, and volume status between your specified CLIST prefix and suffix strings. The SEARCHVOLUME output file can be used as input for creating the import list logical volume file 1 after it is reformatted using the EDGJIMPC sample.

   When stacked volumes are returned to the library, you can build import lists either using the logical volumes or using the stacked volumes. To build a list of stacked volumes to be imported, you can issue the DFSMSrmm TSO subcommand shown in Figure 44.

```
RMM SEARCHVOLUME VOLUME(*) OWNER(*) LIMIT(*) TYPE(STACKED) DESTINATION(vts) -
   CLIST
```

Figure 44. Building a List of Stacked Volumes to be Imported from a Single Stacked Volume

   To build a list of logical volumes to import from a single stacked volume, you can issue the DFSMSrmm TSO subcommand shown in Figure 45.

```
RMM SEARCHVOLUME CONTAINER(S12345) VOL(*) OWN(*) LIMIT(*) TYPE(LOGICAL) CLIST
```

Figure 45. Building a List of Logical Volumes to be Imported from a Single Stacked Volume

   To build a list of logical volumes to import from multiple stacked volumes, you can issue the DFSMSrmm TSO subcommand shown in Figure 46.

```
RMM SEARCHVOLUME VOLUME(*) LIMIT(*) OWNER(*) CONTAINER(*) -
   REQUIRED(vts) TYPE(LOGICAL) CLIST
```

Figure 46. Building a List of Logical Volumes to be Imported from Multiple Stacked Volumes

3. Request import processing using the CBRXLCS macro, the OAM CBRSPLCS sample programs or the LIBRARY command.

   During import processing, the imported volumes can be automatically defined to DFSMSrmm or the volumes can be left for processing by another system if the library is partitioned. If the volume is already known to DFSMSrmm, the volume is accepted for processing if it is defined as an exported logical volume, otherwise the volume is rejected.

4. To complete the import process, DFSMSrmm uses the cartridge entry processing installation exit to track logical volumes that are imported by the VTS. OAM calls the exit once for each logical volume imported. For logical volumes, DFSMSrmm removes the stacked volume association. The stacked volume is updated to remove information for each imported volume.
5. When all logical volumes on a stacked volume are imported, the count of contained volumes is set to 0. You now must decide what to do with the stacked volume. For example, you can return the scratch volume to the pool of empty stacked volumes for use by the VTS; use the Library Manager console to transfer empty stacked volumes to other categories within the VTS so they ready for reuse.

DFSMSrmm Support for Stacked Volumes When Stacked Volume Support Is Not Enabled

A stacked volume is a volume in a virtual tape server library that is used to store one or more logical volumes. When stacked volume support is not enabled, DFSMSrmm does not track stacked volumes but allows you to define them to DFSMSrmm. DFSMSrmm records the name of the exported stacked volume as the 'In container' information for each logical volume. DFSMSrmm keeps track of the 'In container' information only while the logical volume is exported.

DFSMSrmm Support for Export Processing When Stacked Volume Support Is Not Enabled

To use DFSMSrmm for export processing, you must first make sure that volume information reflects the most current location information. Perform DFSMSrmm inventory management storage location processing to set the destinations for any volume moves that are required.

As logical volumes are exported, DFSMSrmm tracks the 'in container' stacked volume and drives movement based on the destination of logical volumes. Use DFSMSrmm export processing to remove logical volumes from a VTS.

1. Define vital record specifications that specify locations to which data sets in the VTS should be moved.
2. Run DFSMSrmm inventory management vital records and storage location management processing to determine which logical volumes should be moved. DFSMSrmm allocates a bin number to the volume if the volume's destination is shelf-managed. There will be unused bin numbers for logical volumes that are moving to shelf-managed storage locations. You will waste bin numbers because EDGRPTD ignores the assigned bin numbers for logical volumes.
3. Create a list of volumes to export. Create the list after you run storage location management. The moves are those identified during vital record processing or by changes made when you issue the RMM CHANGEVOLUME subcommand. Use the RMM SEARCHVOLUME subcommand to obtain volume information for the list as shown in Figure 47.

   DFSMSrmm returns a list of volumes to export that you can use as input for creating the export list logical volume file 1. See these examples in SYS1.SAMPLIB for the format and required files for the export list volume.

   - CBRSPSXP — sample JCL for export list volume scratch request.

```
RMM SEARCHVOLUME VOLUME(*) LIMIT(*) LOCATION(vts)-
   DESTINATION(dest) CLIST(',dest') -
   INTRANSIT(N)
```

Figure 47. Creating a Volume Export List

- CBRSPPXP — sample JCL for export list volume private request.

You can track the movement of logical volumes using the LOCATION and DESTINATION fields of the volume information.

4. Start the export process as described in the *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries* using the LIBRARY EXPORT command or use the CBRSPLCS sample program.

   The VTS export process runs asynchronously to DFSMSrmm processing. Once the export request has been initiated, VTS library signals trigger DFSMSrmm actions related to export processing.

   During the VTS export process, logical volumes are copied to a stacked volume and the stacked volume is completed. For each logical volume copied to the stacked volume, DFSMSrmm is notified of both the logical volume and stacked volume. DFSMSrmm updates the DFSMSrmm control data set with the volume serial number of the stacked volume as the 'in container'.
5. After export VTS processing is completed, you can run DFSMSrmm inventory management report extract processing to obtain information about the volumes that were processed.
6. Create movement report and pick lists by using the DFSMSrmm EDGRPTD report utility.
7. Use the movement reports to eject the stacked volumes from the VTS using the Library Manager and move them to the destination storage location.Transfer the stacked volumes in the export hold category to the exit station using the Library Manager console.
8. Physically move the stacked volumes listed in your movement report from the VTS exit station to the destination storage location.
9. Confirm that volumes have been moved. When the stacked volume is moved, you must confirm the move for all the logical volumes that reside on the volume. Use the RMM CHANGEVOLUME subcommand as shown in Figure 48 to confirm the completion of the movement of volumes.

```
RMM CHANGEVOLUME * CONFIRMMOVE(vts,ALL)
```

Figure 48. Confirming Volume Moves for Exported Volumes

DFSMSrmm Support for Import Processing When Stacked Volume Support Is Not Enabled

DFSMSrmm supports the importing of logical volumes that are defined to DFSMSrmm or not defined to DFSMSrmm. During entry processing for a logical volume, DFSMSrmm automatically adds the volume information to the DFSMSrmm control data set or leaves the volume to be processed on another system. Note that DFSMSrmm does not automatically add rack numbers for logical volumes because rack numbers are not supported for logical volumes.

You can initiate the import of logical volumes independently of DFSMSrmm by:

1. Use the Library Manager console to transfer stacked volumes to be imported from the Unassign category to the Import category. See *3495 Tape Library Dataserver Introduction* and *3495 Tape Library Dataserver Operator's Guide* for more information about the Library Manager.
2. Create an import list volume. See these examples in SYS1.SAMPLIB for the format and required files for the import list volume.
   - CBRSPSIM -- sample JCL for import list volume scratch request.
   - CBRSPPIM -- sample JCL for import list volume private request.

To create the volume list for file 1 of the import list logical volume, you can search in the DFSMSrmm control data set, tailor the DFSMSrmm report extract file tailoring, or use any other method to identify the volumes to be imported.

You can use the RMM SEARCHVOLUME subcommand to build the list of logical volumes with their containing stacked volume and status as shown in Figure 49. Specify the TYPE(LOGICAL) operand and DFSMSrmm returns the container volume serial number, logical volume serial number, and volume status between your specified CLIST prefix and suffix strings. The resultant output file can be used as input for creating the import list logical volume file 1 after it is reformatted using the EDGJIMPC sample.

```
RMM SEARCHVOLUME VOLUME(*) LIMIT(*) OWNER(*) DESTINATION(vts) -
   TYPE(LOGICAL) CLIST
```

Figure 49. Creating a Volume Import List

3. Request import processing using the CBRXLCS macro, the OAM CBRSPLCS sample programs or the LIBRARY command.

   During import processing, the imported volumes can be automatically defined to DFSMSrmm or the volumes can be left for processing by another system if the library is partitioned. If the volume is already known to DFSMSrmm, the volume is accepted for processing if it is defined as an exported logical volume, otherwise the volume is rejected.
4. To complete the import, DFSMSrmm uses the cartridge entry processing installation exit to track logical volumes that are imported by the VTS. OAM calls the exit once for each logical volume imported. DFSMSrmm removes the stacked volume association for logical volumes. DFSMSrmm removes the 'in container' value for the logical volumes.
5. When all logical volumes on a stacked volume are imported, you must decide what to do with the stacked volume. For example, you can return the scratch volume to the pool of empty stacked volumes for use by the VTS; use the Library Manager console to transfer empty stacked volumes to other categories within the VTS so they are ready for reuse.

Enabling Stacked Volume Support

With DFSMSrmm stacked volume support enabled, you can manage the movement of logical volumes using stacked volumes. Without stacked volume support enabled, you can define and list stacked volumes using the DFSMSrmm ADDVOLUME TSO subcommand with the TYPE(STACKED) operand. DFSMSrmm inventory management ignores any stacked volumes you have defined and uses just the container name in the volume records.

Prior to enabling stacked volume support, consider:

- You cannot disable stacked volume support once it is enabled.
- Do not enable support unless all systems using a control data set support stacked volumes. If the control data set is shared with a lower level and support is enabled you can create inconsistent information in the control data set. You must correct inconsistencies using the DFSMSrmm EDGUTIL MEND utility before you can run inventory management.

To enable stacked volume support:

1. Update all systems sharing a control data set to the DFSMSrmm level of code containing stacked volume support.

2. If you have stacked volumes defined to DFSMSrmm, but not as stacked volumes, you need to change volume information. Use the RMM SEARCHVOLUME subcommand to set the correct location information and volume type for non-exported stacked volumes. You need to do this before running EDGUTIL MEND. Although the EDGUTIL processing changes the volume type to stacked, it does not set the correct location information unless the stacked volume is exported and contains volumes.

   You can use the RMM SEARCHVOLUME subcommand to build the command to change the volumes:

   ```
   RMM SEARCHVOLUME VOLUME(ST*) OWNER(*) LIMIT(*) -
    CLIST('RMM CHANGEVOLUME ',' TYPE(STACKED) LOCATION(vts_name) NORACK')
   ```

3. Use EDGUTIL UPDATE with the STACKEDVOLUME(YES) operand on the CONTROL statement of the SYSIN file.

   Once you have enabled support, you can use EDGUTIL with VERIFY(VOLUME) to check if the container information is consistent.

4. Use the RMM LISTCONTROL CNTL subcommand to display the status of support.

   If support shows MIXED, run the EDGUTIL MEND utility to make the container information consistent. The inconsistency is the result of having container information in volume records in the control data set.

   During EDGUTIL MEND processing, DFSMSrmm creates the necessary stacked volumes if you have not previously defined them to DFSMSrmm using the DFSMSrmm TSO subcommands.

   During EDGUTIL MEND processing, DFSMSrmm converts each volume in a container as being in the container instead of a DFSMSrmm location. The location and bin number information in volumes which are in a container is removed, and bins returned to empty status. A bin number is assigned to the stacked volume if the location it is in is bin managed. The bin number is selected from one of the contained volumes using location priority. The bin number choice should reflect the processing used by EDGRPTD in producing movement reports before stacked volume support is enabled.

   From now on, when you run storage location processing DFSMSrmm moves the stacked volumes based on the required location and priority of the contained logical volumes.

5. Update your procedures used to export or import logical volumes to use the required location of the logical volume instead of using the destination. See “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled” on page 89.

Performing a Virtual Export of Logical Volumes

You can use DFSMSrmm subcommands to perform a virtual export for a private logical volume to an existing exported stacked volume container. A virtual export is when you use the DFSMSrmm subcommands rather than VTS export processing to export a volume. This is possible if you have imported a logical volume from a stacked volume, processed the logical volume only for input, and now want to re-associate the logical volume with the previously exported volumes on the original stacked volume container. You use the CHANGEVOLUME subcommand with the CONTAINER operand to do the virtual export. For example:

```
RMM CHANGEVOLUME V12345 CONTAINER(S26901)
```

DFSMSrmm changes the status of the logical volume to scratch in the Library Manager database prior to ejecting the volume. This results in a logical eject which

deletes the logical volume from the Library Manager database. DFSMSrmm then adds the volume logically back into the container.

For the logical eject to work and delete the logical volume from the TCDB and the Library Manager data base, the scratch categories in the VTS must be defined with the 'Fast Ready' attribute. If you do not use the fast ready attribute for your scratch categories, do not use virtual export. If you do so, you will receive messages CBR3650I and EDG3726I with error code '06' and the volume will not be deleted from the TCDB and the Library Manager data base.

Recovering a Logical Volume from an Exported Stacked Volume

DITTO is used to recover a logical volume from an exported stacked volume in situations where no VTS is available. DITTO does not go through OPEN processing nor issue regular mount messages. DITTO recovers the logical volume as a physical volume. As a result, managing these recovered logical volumes requires some additional consideration and processing.

Here are some considerations:

- When you specify DFSMSrmm EDGRMMxx REJECT command values to manage volumes, DFSMSrmm relies on information available at OPEN. These REJECT command values do not apply because DITTO does not issue OPEN requests.
- DFSMSrmm does not update existing volume information when DITTO copies the data.
- The DITTO output volume is a physical volume but might have the same volume serial number as the original logical volume. If you use the original logical volume serial number for the recovered volume, you can convert the logical volume in the DFSMSrmm control data set to a physical volume by issuing the DFSMSrmm CHANGEVOLUME subcommand as shown in Figure 50

```
RMM CHANGEVOLUME volser TYPE(PHYSICAL) CONTAINER(' ')-
LOCATION(SHELF) CMOVE FORCE
```

Figure 50. Converting A Logical Volume to a Physical Volume

  Use the recovered volume as a normal physical volume. If the output volser is different than the original logical volser, the volume information, the data set information and other details can be reused by issuing the DFSMSrmm CHANGEVOLUME subcommand as shown inFigure 51.

```
RMM CHANGEVOLUME volser TYPE(PHYSICAL) CONTAINER(' ')-
LOCATION(SHELF) CONFIRMMOVE NEWVOLUME(pvolser)
```

Figure 51. Reusing Volume Information for a Recovered Volume

- You can also add data set information for the DITTO output volume from the original logical volume.

  To copy details for the original logical volume to the new physical volumes, use DFSMSrmm subcommands to obtain the data set and volume details for the volumes you want to redefine.

Setting Up DFSMSrmm for the System-Managed Tape Library

To get started with the system-managed tape library, information about the volumes in the system-managed tape library must be defined to DFSMSrmm. This section describes scenarios for getting volumes defined to DFSMSrmm.

Using the System-Managed Tape Library With New Volumes

If you intend to populate the system-managed tape library with new scratch volumes, you do not need to explicitly define them to DFSMSrmm. During entry processing, with DFSMSrmm active, DFSMSrmm automatically records information about each volume in its control data set. DFSMSrmm uses the defaults you specified in ISMF for the library entry values; you should set the default entry status to scratch. See “Partitioning System-managed Tape Libraries” on page 101 for additional information.

Using the System-Managed Tape Library with Volumes Already Defined in DFSMSrmm

Volumes already defined to DFSMSrmm have location and other information known to DFSMSrmm. If you plan to use these volumes with the system-managed tape library, you need to update the volume location and home location to a system-managed library name. Here are two methods to implement the system-managed tape library with DFSMSrmm.

Method 1

1. For volumes going to a system-managed tape library, use the RMM CHANGEVOLUME subcommand with the LOCATION operand to change the location to the correct automated tape library dataserver name. This sets the automated tape library dataserver name as the destination name and home location name for each volume going to an automated tape library dataserver. For volumes going to a manual tape library, specify a manual tape library name and you are now ready to use the volumes.

   You can use the RMM SEARCHVOLUME subcommand with the CLIST operand to build a data set containing the required CHANGEVOLUME LOCATION requests.

   ```
   RMM SEARCHVOLUME VOLUME(A*) LIMIT(*) -
       OWNER(*) LOCATION(SHELF) -
       CLIST('RMM CHANGEVOLUME ',' LOCATION(ATL1)')
   ```

   This subcommand builds a command list that you can execute. Repeat this step for each storage location from which you intend to move volumes.
2. Run EDGHSKP specifying PARM=’REPTEXT’ and use EDGRPTD to generate a list of volumes to insert into the automated tape libraries.
3. Insert the volumes. You are now ready to use the volumes.
4. If you have volumes in storage locations that you want returned to the system-managed tape library when they no longer need to be retained, change the volume HOME location from SHELF to the library name, using the RMM CHANGEVOLUME subcommand. For example, specify:

   ```
   RMM SEARCHVOLUME VOLUME(A*) LIMIT(*) -
       OWNER(*) LOCATION(LOCAL) -
       CLIST('RMM CHANGEVOLUME ',' HOME(ATL1)')
   ```

Method 2

1. Pull all volumes that are to go into the system-managed tape library and physically load them.

2. Run the inventory process of the system-managed tape library and let it drive the adding of volumes to the volume catalog. This also flags the volume location as an automated tape library dataserver, but does not change the home location name.
3. Use the RMM SEARCHVOLUME subcommand with the CLIST operand to create a CLIST to create CHANGEVOLUME commands for all the volumes in the library to set the HOME location to the automated tape library dataserver. For example, specify:

   ```
   RMM SEARCHVOLUME VOLUME(A*) LIMIT(*) -
       OWNER(*) LOCATION(ATL1) -
       CLIST('RMM CHANGEVOLUME ',' HOME(ATL1)')
   ```

   If you do not change the home location name, all private volumes are eligible for moving out of the automated tape library dataserver when you next run VRSEL as part of inventory management.
4. If you have volumes in storage locations that you want returned to the system-managed tape library when they no longer need to be retained, change the volume HOME location from SHELF to the library name, using the RMM CHANGEVOLUME subcommand. For example, specify:

   ```
   RMM SEARCHVOLUME VOLUME(A*) LIMIT(*) -
       OWNER(*) LOCATION(LOCAL) -
       CLIST('RMM CHANGEVOLUME ',' HOME(ATL1)')
   ```

Using the System-Managed Tape Library with Existing Volumes

If you want to use the system-managed tape library with existing volumes that are not defined to DFSMSrmm or if you have never used DFSMSrmm to manage these volumes, you must ensure that current information about your volumes is recorded in the DFSMSrmm control data set.

You need to ensure that the correct status is recorded for each private and scratch volume you want to use with the system-managed tape library. One way to do this is to predefine all the private volumes. You can use any existing information you have for the volumes either from an existing tape management system or based on data set catalog entries. You use this information to build a list of RMM ADDVOLUME subcommands to define the volumes to DFSMSrmm. For example, for a private volume:

```
RMM ADDVOLUME volser LOCATION(ATL1) STATUS(MASTER) –
    OWNER(owner) STORGRP(storagegroup)
```

Adding rack numbers is optional. You can define shelf space first using the ADDRACK subcommand so there are empty rack numbers for each volume you add.

Depending on the ISMF library entry defaults, you might be able to avoid defining scratch volumes to DFSMSrmm as this can happen automatically during entry processing.

Using DFSMSrmm with an Existing Tape Library Dataserver

If you have been using an automated tape library dataserver without DFSMSrmm, volume status information and retention requirements from the TCDB must be recorded in the DFSMSrmm control data set for private and scratch volumes in the Tape Library Dataserver.

Assuming that you are using a single range of volume serial numbers starting with S00000 in the Tape Library Dataserver, follow these steps to obtain the information:

1. Adding shelf space is optional for physical volumes and not supported for logical volumes. Define shelf space for the volumes to DFSMSrmm using the RMM ADDRACK subcommand:

   ```
   RMM ADDRACK S00000 COUNT(5000)
   ```

2. Use the RMM ADDVOLUME subcommand to define the volumes to DFSMSrmm and get the correct status information from the volume catalog. You can provide an owner on the RMM ADDVOLUME subcommand. If you do not specify the EXPDT operand, DFSMSrmm obtains the expiration date from the volume catalog. If there is no date in the volume catalog, DFSMSrmm uses the DFSMSrmm parmlib RETPD default.

   ```
   RMM ADDVOLUME S00000 COUNT(5000) STATUS(VOLCAT) OWNER(owner) -
       STATUS(USER) EXPDT(yyyy/ddd)
   ```

   If you do not provide an owner, DFSMSrmm assigns a default owner as described in *z/OS DFSMSrmm Guide and Reference*. If you are not using a single range of volumes in the automated tape library dataserver, issue multiple ADDVOLUME subcommand requests to define all volumes.

It is likely that while implementing DFSMSrmm with the automated tape library dataserver you are converting from an existing tape management system. If so, add this step to your overall conversion plan. Instead of using the RMM ADDVOLUME subcommand to define the volumes, use information from your existing tape management system to define the volumes to DFSMSrmm during the conversion.

Returning Volumes to Scratch Status

When a volume in a system-managed tape library is returning to scratch status, DFSMSrmm can inform OAM during expiration processing for each volume being changed to scratch status. This function also allows DFSMShsm volumes to return to the scratch category.

DFSMSrmm informs OAM to update the TCDB volume status during expiration processing or when the status of a volume is changed using the RMM CHANGEVOLUME subcommand based on the DFSMSrmm EDGRMMxx parmlib OPTION SMSTAPE operand value you specify. See “Defining System Options: OPTION” on page 122 for information about the DFSMSrmm EDGRMMxx parmlib OPTION SMSTAPE operand.

DFSMSrmm uses the OAM status change exit, CBRUXCUA, to allow DFSMSrmm to be notified of all volume status changes made by others, for example, by ISMF. CBRUXCUA performs the following processing:

- If a volume is not defined to DFSMSrmm, but is resident in an automated tape library dataserver, it is automatically defined to DFSMSrmm. If any errors are encountered, as for cartridge entry processing, the status change is rejected.
- If a volume is defined to DFSMSrmm:
  - All changes from PRIVATE to SCRATCH status are rejected unless the DFSMSrmm control data set already shows SCRATCH status.
  - All changes from PRIVATE to PRIVATE and SCRATCH to SCRATCH are supported to enable OAM to correct discrepancies that might exist with the Library Manager inventory.
  - All changes from SCRATCH to PRIVATE status are accepted. This includes open processing.
  - Storage group name changes are recorded in the DFSMSrmm control data set.

– Any change to make TCDB information consistent with DFSMSrmm information is accepted.

The objective is to keep the TCDB and the DFSMSrmm control data set information consistent.

We recommend that you use the STGADMIN.IGG.LIBRARY resources to protect the new catalog facilities define, alter, and delete of library entries, and volume entries to ensure changes go through the OAM installation exits. We recommend using IDCAMS as an error recovery tool.

Partitioning System-managed Tape Libraries

You can partition a system-managed library including a VTS by:

- Specifying the USE operand value on the RMM ADDVOLUME or RMM CHANGEVOLUME subcommands. You can set this value to MVS or VM or both. If you do not specify MVS for a volume, DFSMSrmm prevents the volume from being defined in the volume catalog on this system.
- Defining parmlib member EDGRMMxx REJECT prefixes as described in "Defining Tapes Not Available on Systems: REJECT" on page 144. You can use REJECT to prevent a volume not defined to DFSMSrmm from being defined in a system-managed tape library. The REJECT ANYUSE(*prefix*) operand prevents a volume from being defined in the system-managed tape library on the current system. The REJECT OUTPUT(*prefix*) operand allows you to define the volume to the system-managed tape library but only use the volume for input processing.

When you enter a volume into a system-managed tape library, if the volume is defined to DFSMSrmm and you have specified the USE operand without MVS, or the volume matches a specified REJECT ANYUSE(*prefix*), EDGLCSUX sets a return code of 12 to pass to OAM. OAM leaves the volume in the system-managed tape library in the INSERT category; it does not create a volume entry in the TCDB. The volume is then available for another sharing system to process the insert request. The sharing system could be another VM or MVS system.

If DFSMSrmm allows the volume entry to be performed, OAM creates an entry in the TCDB. If the volume matches a specified REJECT OUTPUT(*prefix*), at OPEN time DFSMSrmm fails any requests for output processing while allowing requests for input processing.

To tailor partitioning when the REJECT ANYUSE option cannot be used, add code to the DFSMSrmm-supplied OAM installation exit to check the volume serial number and set a return code of 12 if the volume is not for use on this system. See "Managing System-Managed Tape Library Volumes: EDGLCSUX" on page 179 for information about the DFSMSrmm EDGLCSUX installation exit.

Sharing a System-Managed Library and a BTLS-Managed Library

When you share an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver between DFSMS and BTLS, there are restrictions on the sharing of volumes between the systems. For example, although a private volume is defined in the TCDB on DFSMS, it cannot be shared unless it is also defined in the BTLS catalog.

We recommend that you consider partitioning the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver using some volumes under

DFSMS and other volumes under BTLS. This is particularly important when you plan to use scratch volumes. Volumes that are part of scratch pools cannot be effectively shared.

Only volumes which are long-term private volumes can be shared effectively. You can define each private volume to both systems, but if the volume changes status, it is likely that the BTLS catalog and the TCDB will not match the volume status defined in the DFSMSrmm control data set. You can modify the CBRUXENT exit supplied with DFSMSrmm to force the Library Control System to not process the volumes intended for BTLS management.

If you want to designate specific scratch volumes for use on DFSMS and others for use with BTLS:

1. Modify the DFSMSrmm supplied CBRUXENT exit by setting the return code to 12 (UXEIGNOR) for all volumes that are to be managed by BTLS.
2. Use the AMS LIBRARY SETCATEGORY command to set the appropriate BTLS private or scratch category for all volumes entering the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver that are ignored by the Library Control System.

If you modify the CBRUXENT exit, you could issue a WTO that you trap in Netview or equivalent and use this event to trigger the start of the AMS LIBRARY SETCATEGORY command on the system where BTLS resides.

An easier implementation would be possible using separate control data sets, one for DFSMSrmm with system-managed tapes, and one for DFSMSrmm with BTLS volumes. The disadvantage of this is extra administration and total segregation of volumes.

Moving from a Non-system-managed to a System-Managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver

If you plan to move volumes from an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver controlled by BTLS to a system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver managed with DFSMSrmm, the DFSMSrmm control data set should be updated to reflect the new locations for the volumes. Issue the RMM CHANGEVOLUME subcommand on the DFSMSrmm system to update both the home location and current location of the volumes.

```
RMM CHANGEVOLUME volser LOCATION(sms_lib_name)
```

If you have volumes that are in storage locations that you want returned to the system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver rather than the non-system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver, use the RMM CHANGEVOLUME subcommand on the DFSMSrmm system to change the home location for the volumes.

```
RMM CHANGEVOLUME volser HOME(sms_lib_name)
```

See “Defining Pools: VLPOOL” on page 148 for information about retaining and moving volumes.

Chapter 5. Running DFSMSrmm with BTLS

You can use DFSMSrmm with Basic Tape Library Support (BTLS). BTLS is an IBM program offering that provides basic automation support for the IBM 3494 and IBM 3495 Tape Library Dataservers in a non-system-managed library environment. Since DFSMSrmm does not interact directly with BTLS or the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver, you must take steps to update the BTLS catalog to reflect changes to volumes that are managed by DFSMSrmm.

When you define volumes to DFSMSrmm, information about the volumes is added to the DFSMSrmm control data set. If you plan to use any of the volumes defined to DFSMSrmm with BTLS, use the access methods services LIBRARY command to define the volumes in the BTLS catalog. Refer to the *Basic Tape Library Support Version 1 Release 1 User's Guide and Reference* for more information.

If you plan to use DFSMSrmm for volumes managed by BTLS, you must set up procedures required to return scratch volumes to scratch status in the BTLS catalog after DFSMSrmm expiration processing.

Here is a summary of the steps you follow to use BTLS with DFSMSrmm:

1. Use the NAME operand on the VLPOOL parmlib commands to identify the BTLS scratch pools to be used.
2. Optionally, if pooling is to be based on data set name and jobname, use the EDGUX100 installation exit to select a pool for new tape data sets.
3. Set up the procedures to return BTLS-managed volumes to scratch status after running inventory management.
4. Set up the procedures to update BTLS when volumes are added to or removed from the installation media library.

Setting Up Scratch Pools for BTLS-Managed Volumes

"Defining Pools: VLPOOL" on page 148 provides information on defining VLPOOL and other EDGRMMxx options.

Both DFRMM and DFSMSrmm use VLPOOL scratch pool definitions to:

- Update mount messages
- Update 3480 and 3490 drive displays if the MSGDISP installation exit IGXMSGEX is called
- Reject scratch volumes which are not from the correct pools

If you plan to use DFSMSrmm with BTLS, you must define and use scratch pools with special care to prevent DFSMSrmm from rejecting volumes needlessly. DFSMSrmm does not know that volumes managed by BTLS reside in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver and attempts to control scratch tape assignment for mounts inside the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver. DFSMSrmm, on the other hand, does not attempt to control scratch tape assignment for mounts inside a system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver.

© Copyright IBM Corp. 1992, 2001

If you have scratch volumes residing in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver managed by BTLS, ensure that any pool definitions you define that include those volumes do not prevent the volumes from being used.

DFSMSrmm accepts or rejects volumes based on the VLPOOL definitions that you provide in parmlib member, EDGRMMxx. For volumes that reside in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver and are managed by BTLS, ensure that the VLPOOL definitions do not cause conflicts when scratch volumes are used.

For example, consider these VLPOOL definitions:

```
VLPOOL PREFIX(A*) SYSTEM(A) TYPE(S)
VLPOOL PREFIX(B*) SYSTEM(B) TYPE(S)
```

On system *A* when a scratch volume is requested, if the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver contains volumes from both pools A* and B*, it can select a scratch volume from either pool. If the Library Manager selects a volume in pool B*, DFSMSrmm rejects it. The Library Manager might *never* select a volume that is can be used because all available scratch volumes are selected until a volume acceptable to DFSMSrmm is found.

If you want DFSMSrmm to manage pool selection when using BTLS, use the NAME operand on the VLPOOL definition for the pool to specify a pool name. For example, you could define VLPOOL definitions as follows:

```
VLPOOL PREFIX(A*) NAME(SCRTCH5) TYPE(S) SYSID(SY1) DESC('BTLS pool 5')
VLPOOL PREFIX(B*) NAME(SCRTCH3) TYPE(R) DESC('BTLS pool 3')
```

Note: DFSMSrmm uses the value in the NAME operand to update messages and tape drive displays for non-specific mount requests. Do not use the NAME operand if your operations depend on a pool prefix rather than a pool name.

For scratch pools of volumes contained in a IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver managed by BTLS, we recommend that the SYSID operand is not used on VLPOOL definitions unless the NAME operand is used. For more information, refer to “Returning BTLS-managed Volumes to Scratch” on page 106.

Running DFSMSrmm Inventory Management with BTLS

Use the EDGHSKP utility to run inventory management activities which include: vital record processing, expiration processing, storage location management processing, backing up the control data set and journal and creating an extract data set. See “Chapter 13. Performing Inventory Management” on page 247 for more information.

You should consider how to perform inventory management if you are using DFSMSrmm with BTLS. Since you need to complete the update to the BTLS catalog, once inventory management is completed, use the Access Method Services (AMS) LIBRARY SETCATEGORY command to update the status of the volumes managed by BTLS.

For example, to keep track of volumes managed by BTLS and update information about volumes returning to scratch in the BTLS catalog:

1. Put all your BTLS-managed volumes in racks with a specific media name, for example: BTLS. Any other method to identify BTLS volumes, such as rack number or volume prefix could be used instead.

2. After inventory management is complete, issue the following command to create a list of BTLS racks in scratch status.

   ```
   RMM SEARCHRACK RACK(*) LIMIT(*) MEDIANAME(BTLS) SCRATCH -
       CLIST NOLIST
   ```

3. Use the resulting data set with the scratch volume list as the LIBIN DD input to an IDCAMS job with the following command:

   ```
   LIBRARY SETCATEGORY UNIT(xxx) CATEGORY(SCRTCH)
   ```

Running EDGINERS for BTLS-managed Volumes

For volumes managed only by BTLS, use DFSMSrmm to run EDGINERS. You must use the TAPE DD to allocate a tape drive in the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver and can use the POOL or any other execution parameter to restrict processing to specific volumes that are managed by BTLS.

Restrictions

DFSMSrmm does not ensure that volumes you plan to use or attempt to use with BTLS in the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver meet the MVS labeling restrictions that apply for system-managed tape volumes. You must make sure that only MVS standard label volumes with the same external and internal volume serial number are entered into the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver. Failure to do so can result in incorrect processing by DFSMSrmm. For example, DFSMSrmm uses the internal volume serial number of the mounted volume to record information in the DFSMSrmm control data set, while BTLS uses the external volume serial number to request a mount.

When you migrate from BTLS management to system-managed tape, migration is easier if you use only MVS standard label volumes. Also, under system-managed tape processing, DFSMSrmm ensures that the volume serial number and rack number match, rejecting volumes that do not meet this requirement. Considering these restrictions during BTLS implementation will make migration to system-managed tape easier.

Defining Volume Information for BTLS-managed Volumes

When you define volumes to DFSMSrmm, information about the volumes is added to the DFSMSrmm control data set.

DFSMSrmm does not interface with BTLS so volumes are not automatically defined to the BTLS catalog. If you plan to use any of the volumes defined to DFSMSrmm in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver managed by BTLS, you must also define the volumes in the BTLS catalog using the AMS LIBRARY SETCATEGORY command.

When you delete volumes from DFSMSrmm, if the volumes are managed by BTLS you also need to ensure the volumes are deleted from the BTLS catalog and ejected from the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver, if appropriate.

Returning BTLS-managed Volumes to Scratch

When volumes that reside in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver are returned to scratch by DFSMSrmm, information needs to be updated in the TCDB or the BTLS catalog. DFSMSrmm provides no support to automatically update the BTLS catalog.

If you perform scratch management of volumes residing in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver managed by BTLS, you must ensure that BTLS volume status information matches DFSMSrmm volume status information. After you run expiration processing, you can prepare a list of volumes that are in scratch status. Issue the LIBRARY SETCATEGORY command to update the status of each volume to scratch. You can issue the following command for each volume even if the status of the volume is scratch:

```
LIBRARY SETCATEGORY UNIT(addr) VOLSER(volser) CATEGORY(SCRTCH)
```

You can use DFSMSrmm to help build the input to the SETCATEGORY function. The TMP step shown in Figure 52 uses the RMM SEARCHVOLUME subcommand to produce a simple list of scratch volumes in the CLIST data set. This list is then input to IDCAMS in the LIBIN DD file. You can tailor the RMM SEARCHVOLUME subcommand to list volumes based on more selective criteria.

```
//jobname JOB ......
//TMP      EXEC PGM=IKJEFT01
//SYSTSPRT DD SYSOUT=*
//SYSTSIN  DD *
RMM SEARCHVOLUME VOL(*) OWN(*) STATUS(SCRATCH) LIMIT(*) -
 CLIST
/*
//AMS      EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//LIBIN DD DSN=userid.EXEC.RMM.CLIST,DISP=SHR
//SYSIN DD *
  LIBRARY SETCATEGORY UNIT(addr) CATEGORY(SCRTCH)
/*
```

Figure 52. Sample JCL to Return Volumes to Scratch

You need to modify this example if you are using system-managed tape with DFSMS and BTLS-managed volumes. Limit the search to volumes that are in the BTLS scratch pool. Otherwise all scratch volumes will become BTLS scratch and will not be available for use as scratch on the DFSMS system. Refer to *Basic Tape Library Support Version 1 Release 1 User's Guide and Reference* for more information on using the LIBRARY command.

Chapter 6. Managing Storage Locations

Storage locations are those places outside the removable media library where you send removable media. Storage locations can be destinations for disaster recovery related activities or any other purpose your installation chooses.

DFSMSrmm provides shelf-management of storage locations by assigning bin numbers to shelf locations within a storage location. DFSMSrmm automatically provides shelf-management for the built-in locations. This means that DFSMSrmm assigns bin numbers to each volume in a built-in storage location. You can request shelf-management of installation defined storage locations when you create your location definitions using the parmlib LOCDEF command.

You can also specify media names in the parmlib LOCDEF command to provide a way to segregate shelf locations in an installation defined storage location. The media names you specify for a storage location should be the same as or a subset of the media names you specify for pools in your removable media library. See “Defining Pools in Parmlib Member EDGRMMxx” on page 58 for information about pooling.

The movement and retention of volumes in and out of storage locations is done during DFSMSrmm inventory management. During vital record processing, DFSMSrmm sets the required location for each volume using information from vital record specifications. The volume does not move to the required location during vital record processing. During storage location management processing, RMM sets the destination for a volume using the required location information if that volume can be moved. When stacked volume support is enabled, DFSMSrmm can also set the destination for a stacked volume at completion of export processing. When stacked volume support is enabled, no destination is set for logical volumes and all logical volumes are moved based on the stacked volume destination.

You can also manually assign destinations and override inventory management processing.

Types of for Storage Locations

DFSMSrmm recognizes two types of storage locations: DFSMSrmm built-in storage locations and installation defined storage locations. There are three DFSMSrmm built-in storage locations named: LOCAL, DISTANT, and REMOTE.

Installation defined storage locations can be used for volumes for disaster or vital records, or for controlling any media moving outside your installation. Using DFSMSrmm installation defined storage locations, you can:

- Define more than three storage locations.
- Use any name up to 8 characters in length to name the storage location.
- Change the movement priority for the installation defined storage locations.
- Continue to use the DFSMSrmm built-in storage locations.
- Select shelf-management or no shelf-management for the installation defined storage locations.

© Copyright IBM Corp. 1992, 2001

Defining Storage Locations

Use the LOCDEF parmlib command to define installation defined storage locations. Storage locations can be any 1 to 8 character named location except for the DFSMSrmm reserved location names ALL, HOME, and CURRENT. You can also use the DFSMSrmm built-in storage location names as installation defined storage locations. You can also define characteristics of system-managed storage locations using the LOCDEF parmlib command. Table 15 shows the differences between built-in and installation defined storage locations.

Table 15. Differences between Built-in and Installation Defined Storage Locations

To	For Built-in Storage Locations	For Installation-defined Storage Locations
Segregate shelf locations by media name	You cannot segregate built-in storage locations by media name or type of media.	You can segregate shelf locations by specifying media names
Define storage locations	You do not need to define built-in storage location names. The three are:LOCAL, DISTANT, and REMOTE.	You can define an unlimited number of storage location names.
Define bin numbers	DFSMSrmm uses bin numbers 1 through 999999.	You can use any 6 character value.
Shelf-manage	DFSMSrmm automatically provides shelf-management.	You can decide.
Determine location priority	DFSMSrmm uses the default priority.	You can define the priority in the LOCDEF location definitions.

Processing for Storage Locations

During storage location management processing, DFSMSrmm determines if a move of the volume is required. If a move is required, and the move is to a shelf-managed storage location, DFSMSrmm assigns an empty bin in the target location to the volume based on the media name and LOCDEF information. If no empty bin numbers of the required media name are available, DFSMSrmm issues message EDG2403E, and inventory management processing continues.

When the volume is returned from the storage location, the bin number is identified for reuse as part of move confirmation processing. See “Chapter 13. Performing Inventory Management” on page 247 for information about inventory management vital record processing and storage location management.

Implementing Installation Defined Storage Locations

You might implement installation defined storage locations for the following reasons:

- To choose the storage location names you want
- To change the dominance priority of the locations for inventory management vital record processing for use when moves conflict
- To separate volumes by shape when sending them to storage locations
- To use storage locations without shelf management
- To use more than 3 storage locations

To implement installation defined storage locations:

1. Identify:
   a. The number of storage locations you require. DFSMSrmm provides you with three built-in storage locations. If you use more than three storage locations, use the LOCDEF parmlib command to define additional storage locations. You can identify any location as an installation defined storage location except the locations ALL, HOME, and CURRENT which are DFSMSrmm reserved location names.
   b. The location names you will use.
   c. The priority you want to use for each location. Priority is used to resolve movement conflicts that occur when more than one policy applies to a volume or when multiple logical volumes reside on a stacked volume. The relative priority of the locations is used to determine where a volume is sent. Include the location name SHELF and any system-managed libraries to develop your location priority.
   d. The media names you will use in your installation. If you have different media shapes in your installation, you can set movement policies based on the different shapes. For example, you might have separate shelving for tape reels, cartridge tape, and optical media due to differences in their shape.
   e. If you require storage locations without shelf management.
2. Define LOCDEF parameters in parmlib. See “Defining Storage Locations: LOCDEF” on page 115.
3. Restart or refresh the DFSMSrmm procedure to use the updated parmlib member.
4. Define the bin numbers for the shelf-managed storage locations using the RMM ADDBIN subcommand. See *z/OS DFSMSrmm Guide and Reference* for information.

   When the new location and bin numbers are defined, they are available for assignment to volumes moving to the storage location. In order for DFSMSrmm to use the new storage locations and bin numbers for storage management, you must continue with step 5. Inventory management sequentially assigns the bin numbers to moving volumes. If you do not define vital record specifications and run inventory management, the locations and bin numbers can only be assigned manually by using the RMM CHANGEVOLUME subcommand.
5. Create new vital record specifications or update existing vital record specifications specifying the location names and media names you defined using LOCDEF.
6. Run inventory management vital record processing to produce a Vital Records Retention Report. Check the report to ensure that the correct destination is selected for each data set and volume retained by a vital record specification.
7. If you plan to export logical volumes, run export processing before running DFSMSrmm storage location management.
8. Once the retention report is correct, run inventory management storage location management and report extract processing to assign destinations and bin numbers and to prepare an extract data set which you use as input to EDGRPTD.
9. Run EDGRPTD to produce the movement and inventory reports for use to pull and ship the volumes to the correct locations.
10. Once volumes have been moved, use the RMM CHANGEVOLUME subcommand to confirm volume movement.

Changing Storage Locations

To change the bin management for a storage location information:

1. Identify the storage locations information you want to change and the vital record specifications that specify the storage location names.
2. Build RMM ADDVRS subcommands using the information from the vital record specifications you want to change. Later you will issue these subcommands to add the vital record specifications you delete. Build RMM DELETEVRS subcommands for each vital record specification that contains the storage location name you want to change.
3. Issue the RMM DELETEVRS subcommands in the background to delete all vital record specifications that use the storage location you want to change.
4. Update the DFSMSrmm EDGRMMxx parmlib member LOCDEF command MANAGEMENTTYPE operand for a storage location.
5. Restart the DFSMSrmm subsystem (F DFRMM,M=xx.) described in “Step 17: Restarting MVS with DFSMSrmm Implemented” on page 44.
6. Use the RMM ADDBIN subcommand to add bins required for the storage location if the new MANAGEMENTTYPE is BIN.
7. Issue the RMM ADDVRS subcommands in the background to add the vital record specifications that you previously deleted.
8. Perform inventory management vital record processing and storage location management to move volumes to the updated storage location.

Deleting Storage Locations

You can delete storage locations by removing the EDGRMMxx parmlib LOCDEF definition for the location. Before removing the LOCDEF definition in parmlib, check that:

- All bin numbers have been deleted in the location you want to delete.
- There are no volumes that are marked to be moved to the location.
- DFSMSrmm does not list any volumes for the location by using the RMM SEARCHVOLUME subcommand with the LOCATION operand.
- There are no vital record specifications that use the location you want to delete.

Moving Volumes to Storage Locations Using Media Shape

You can describe removable media in terms of media shape. For example, you can identify all round media, all square media, all small size media, or all cartridge media. You can use the VLPOOL parmlib command to define pools of media that are based on shape. You can use media shape to identify the type of media that is allowed in a storage location. For example, you can keep tape reels, cartridges, and optical disks in different ranges of shelf space, where each type of media requires a differently shaped slot for storage.

When you decide which media names to use, consider the different media you have or might have in the future. You should the same media names for storage locations that you use for pools. Use the LOCDEF command MEDIANAME operand to define each media name for each location to allow or restrict storage using media name. You can also aggregate similar media to use the same range of shelf space by using a media name of *.

Consider an installation with the following types of media:

- Mini tape reels
- Tape reels
- Cartridge system tape
- Enhanced capacity cartridge system tape

There are four different types of media that fall into three basic media shapes: mini reels, reels, and cartridges. The number of reels in use in the installation is declining. Table 16 shows how the VLPOOL MEDIANAME and the LOCDEF MEDIANAME values can be defined. A different VLPOOL MEDIANAME has been defined for each different type of media. The media names describe the shape of the volumes or a physical characteristic like TWOTONE for enhanced capacity CST. In Table 16 (Case 1), the same LOCDEF media names are used to describe the media that can reside in the storage location. All volumes are segregated by their media name. In (Case 2), the cartridge system tape and enhanced capacity cartridge system tape are defined with the same media name and can be stored together because they are the same shape.

Table 16. Storing Media of the Same Shape

Type of Media	**VLPOOL MEDIANAME**	**LOCDEF MEDIANAME (Case 1)**	**LOCDEF MEDIANAME (Case 2)**
Mini tape reels	MINI	MINI	MINI
Tape reels	REELS	REELS	REELS
Cartridge system tape	CART	CART	*
Enhanced capacity CST	TWOTONE	TWOTONE	*

In Table 17, the media names REELS and CARTRDGE are used in the VLPOOL command to describe media shape. Each basic type of media has been allocated a different media name that gives information about the volumes. When the volumes are moved to a storage location, as shown in Table 17 (Case 3), all volumes are segregated by their media name. In (Case 4), all volumes are segregated by their media name but use is made of the * media name.

Table 17. Storing Media of Different Shapes

Type of Media	**VLPOOL MEDIANAME**	**LOCDEF MEDIANAME (Case 3)**	**LOCDEF MEDIANAME (Case 4)**
Mini tape reels	REELS	REELS	REELS
Tape reels	REELS	REELS	REELS
Cartridge system tape	CARTRDGE	CARTRDGE	*
Enhanced capacity CST	CARTRDGE	CARTRDGE	*

By careful selection of media names you can segregate shelf space in your removable media library using the VLPOOL parmlib command and in your storage locations using LOCDEF. See “Organizing the Library by Pools” on page 55 for information about the use of VLPOOL.

You can also use media name to control movement of volumes to non-shelf-managed storage locations. For example, you might have a customer that can only accept cartridge system tape. You can control the type of media sent to that customer by defining the LOCDEF command with a specific media name. In

Figure 53, only volumes with a media name of CART can be moved to the CUST1 location.

```
LOCDEF LOCATION(CUST1) TYPE(STORAGE) MANAGEMENTTYPE(NOBINS) -
   MEDIANAME(CART)
```

Figure 53. Using Media Name to Control Volume Movement

During inventory management DFSMSrmm checks the media name for the location and prevents volume movement when the media name does not match. DFSMSrmm issues message EDG2412E for each volume that cannot be moved because its media name is not supported at the location.

Converting from Built-In Storage Locations

If you already have volumes stored in the DFSMSrmm built-in storage locations, you need to decide if you migrate the volumes to installation defined storage locations or allow the built-in storage locations to fall out of use when volumes are moved out and not replaced.

Once you decide to move to installation defined storage locations, whether or not you decide to continue to use the same names (LOCAL, DISTANT, and REMOTE), you must redefine the vital record specification definitions so that DFSMSrmm knows you are using installation defined storage locations.

The built-in storage locations LOCAL, DISTANT and REMOTE can be defined on LOCDEF parameters. This gives you the ability to use the existing built-in names rather than having to change the storage location names in use. When you use the DFSMSrmm built-in storage locations in a LOCDEF parmlib command, the DFSMSrmm built-in storage locations are treated like any other installation defined storage location.

Note: You cannot use the LOCDEF command to change the PRIORITY of LOCAL, DISTANT or REMOTE and have them otherwise continue to work as before. Once you have defined the built-in names using LOCDEF:

- You can no longer use previously assigned bin numbers. You must define new bin numbers using the media names that are specified in the LOCDEF command.
- You must redefine the vital record specifications which reference these locations so that volumes can be scheduled to move to the installation defined location.

If the built-in storage location names are defined using LOCDEF without the PRIORITY operand, the default installation defined location priority is used.

Switching Volumes to Installation Defined Storage Locations

You can switch volumes from built-in storage locations to the installation defined storage locations without moving the volumes.

Make sure you have defined the LOCDEF command in parmlib to identify the target installation defined storage location and its attributes as shown in Figure 54 on page 113.

```
LOCDEF LOCATION(REMOTE) TYPE(STORAGE) MEDIANAME(CART) -
   MANAGEMENTTYPE(BINS)
```

Figure 54. Identifying an Installation Defined Storage Location

Issue the RMM CHANGEVOLUME subcommand with the BIN operand to assign bin numbers for the volumes you are switching from the built-in storage location to the installation defined storage location. For example, the volume MIKE01 resides in the built-in storage location REMOTE in bin number 000010. To switch the volume to the installation defined storage location REMOTE, issue:

```
RMM CHANGEVOLUME MIKE01 LOCATION(REMOTE) BIN(000010) CONFIRMMOVE
```

The volume is allocated to the bin number in the installation defined storage location and the original bin number in built-in location REMOTE is empty. To move all the volumes you can use the data in the report extract file to generate the RMM CHANGEVOLUME subcommands.

DFSMSrmm provides sample JCL as EDGJCVB in SAMPLIB. You can use this sample to switch the storage location name to any installation defined storage location name while keeping the assigned shelf location number the same. Substitute the LOCATION(REMOTE) with LOCATION(*storage_locname*) you choose.

Going Back to Built-In Storage Locations

If you converted built-in storage locations to installation defined storage locations as described in “Converting from Built-In Storage Locations” on page 112, you can go back to using the storage locations as built-in storage locations.

1. Remove the LOCDEF commands that use the built-in names.
2. Restart or refresh the DFSMSrmm procedure to use the updated parmlib member.
3. Define the bin numbers for the built-in storage locations using the RMM ADDBIN subcommand.
4. If LOCAL, DISTANT, or REMOTE were used as installation defined storage location names, any vital record specification using the names must be deleted and then redefined.
5. Run inventory management vital record processing to produce a Vital Records Retention report.
6. Run inventory management storage location management processing to assign destinations and bin numbers. Request a report extract file for EDGRPTD.
7. Run EDGRPTD to produce the movement and inventory reports for use to pull and ship the volumes to the correct locations.
8. Once volumes have been moved, use the RMM CHANGEVOLUME subcommand to confirm volume movement.
9. Delete the empty bins used for the installation-defined storage location.

Using Manual Move Control

You can override automatic processing and control volume movement manually by using the RMM CHANGEVOLUME subcommand with the MANUALMOVE operand. To return the volume to automatic movement control, use the RMM CHANGEVOLUME subcommand with the AUTOMOVE operand.

When you put a volume under manual move control, DFSMSrmm does not move the volume anywhere automatically, even when it expires and is pending release. Volume movement occurs only if you request it using the RMM CHANGEVOLUME subcommand with the LOCATION operand.

To allow release processing, you must remove the volume from manual move control unless the volume is in its home location. When a volume is in its home location, DFSMSrmm performs release processing even if the volume is under manual move control.

You might use manual move control to keep a volume on-site even though the volume is flagged to be sent off-site for disaster recovery. To keep the volume on-site or to request that the volume be moved back to its home location, you could specify:

```
RMM CHANGEVOLUME volser MANUALMOVE LOCATION(HOME)
```

Figure 55. Keeping Volumes On-site

When a volume is put under manual move control, any outstanding move is canceled. Moves can also be canceled by issuing the RMM CHANGEVOLUME command with the LOCATION operand. The operand LOCATION(HOME) is specified in Figure 55 to cancel any pending moves because the volume is in its home location.

You might use manual move control for volumes you create on one system and then send to other systems for processing. Define the other systems as locations using the parmlib LOCDEF command. When a volume is ready to be sent to the other system, you can confirm the volume move and put the volume under manual move control at the same time. For example, to send a volume to another system defined on a LOCDEF command as OTHER1, you can issue the command:

```
RMM CHANGEVOLUME volser LOCATION(OTHER1) CONFIRMMOVE MANUALMOVE
```

Figure 56. Sending a Volume to Another System

The CONFIRMMOVE operand shown in Figure 56 confirms that the volume move has completed. The MANUALMOVE operand shown in Figure 56 puts the volume under manual move control and prevents the volume from being moved automatically. When the volume is returned from the other system, remove the volume from manual move control. Then confirm that the volume is back in its home location as shown in Figure 57.

```
RMM CHANGEVOLUME volser LOCATION(HOME) CONFIRMMOVE AUTOMOVE
```

Figure 57. Returning a Volume from Another System

Chapter 7. Using the Parmlib Member EDGRMMxx

This section describes the options that you can specify in the parmlib member EDGRMMxx.

Specify the options using the following format:

```
command operand1(value1) operand2(value2) -
        operand3(value3)
```

You can include comments in the parmlib member by enclosing your comments within /* */ as shown in the following example. Comments can precede and follow the parameters as well as appear within the parameters:

```
/*Your command syntax example*/
command operand1(value1) operand2(value2) /* comment */ -
        operand3(value3) /*end of command*/
```

The parmlib member EDGRMMxx uses the following commands:

- LOCDEF described in “Defining Storage Locations: LOCDEF”.
- MNTMSG described in “Defining Mount and Fetch Messages: MNTMSG” on page 119.
- OPTION described in “Defining System Options: OPTION” on page 122.
- REJECT described in “Defining Tapes Not Available on Systems: REJECT” on page 144.
- SECCLS described in “Defining Security Classes: SECCLS” on page 145.
- VLPOOL described in “Defining Pools: VLPOOL” on page 148.

Use the OPTION command to set defaults for DFSMSrmm on a system. Use the VLPOOL command to override the system-wide defaults for particular tape pools.

Do not specify duplicate operands. If you do, DFSMSrmm uses the last value you specified.

Defining Storage Locations: LOCDEF

Use the LOCDEF command to define installation defined storage locations to DFSMSrmm. You can also use LOCDEF to set the priority for shelf locations and system-managed tape libraries. The LOCDEF command in Figure 58 defines the location MIKESLOC, which accepts media with the media name SQUARE, and which is shelf-managed.

```
     /* LOCDEF - Add a location definition                    */
LOCDEF LOCATION(MIKESLOC) MEDIANAME(SQUARE) TYPE(STORAGE)  -
   MANAGEMENTTYPE(BINS)
```

Figure 58. Parmlib Member EDGRMMxx LOCDEF Command Example

LOCDEF Command Syntax

Figure 59 on page 116 shows the syntax of the LOCDEF Command for defining storage locations.

© Copyright IBM Corp. 1992, 2001

Parmlib Member LOCDEF Command



Figure 59. Parmlib Member EDGRMMxx LOCDEF Command for Defining Storage Locations

Figure 60 shows the syntax of the LOCDEF Command for defining shelf locations and system-managed libraries.



Figure 60. Parmlib Member EDGRMMxx LOCDEF Command for Defining Shelf and System-Managed Libraries

LOCDEF Command Operands

LOCATION(*installation_defined_location_name***,** *system_managed_library_name***,**

LOCAL,DISTANT,REMOTE,SHELF)
Specifies the name of the location being defined. *installation_defined_location_name* can be any 1 to 8 character name or LOCAL, DISTANT, REMOTE, or SHELF. *system_managed_library_name* can be any 1 to 8 character name starting with a non-numeric. The DFSMSrmm reserved location names HOME, CURRENT or ALL cannot be used as location names. When you use SHELF or a system-managed library, the only other operands that can be specified are PRIORITY and TYPE.

All LOCDEF location names must be unique. DFSMSrmm issues message EDG0225E if you define duplicate location names. You cannot have a storage location with the same name as a system-managed library. If you specify the same name, DFSMSrmm issues message EDG0233E. You cannot specify a distributed library name. If you specify a distributed library name, DFSMSrmm issues message EDG0235E.

MANAGEMENTTYPE(BINS|NOBINS)
Use this operand to identify the shelf-management technique you want for the location. This operand is required when defining a location of type STORAGE.

BINS
DFSMSrmm shelf-manages the location by assigning bin numbers to volumes in the location.

NOBINS
Specifies that the location is not to be shelf-managed. Volumes sent to this

location are not assigned bin numbers. However, they will still only be eligible to be sent to the location if their medianame or * appears in the LOCDEF media name list.

You can change the type of a location by specifying the LOCDEF command with the TYPE operand. The changed value applies to the vital record specifications you define after you make the change. To implement the change, you must change the location information in existing vital record specifications and run inventory management vital record processing. During vital record processing, DFSMSrmm changes the required location and location type for each volume. See “Changing Storage Locations” on page 110 for additional information.

Although vital record specifications must be updated and inventory management vital record processing must be run to implement the new LOCDEF MANAGEMENTTYPE, you can use the new LOCDEF MANAGEMENTTYPE when issuing DFSMSrmm CHANGEVOLUME subcommands with the LOCATION operand.

MEDIANAME(*medianame***|*)**

Specifies a list of the media names that are acceptable for the storage location. *medianame* can be any 1 to 8 character name you choose to describe a media name, type of media, a shape, or size. Examples of MEDIANAME include: CART, ROUND, SQUARE, 3490, 3590, TAPE, OPTICAL, CASSETTE, and so on. The media names you use on the LOCDEF commands should be the same as or a subset of the media names you use for your installation VLPOOL definitions. See “Defining Pools: VLPOOL” on page 148.

When you specify MEDIANAME(*) using the parmlib LOCDEF command or the RMM ADDBIN or RMM ADDRACK subcommands, any volume with any media name can be sent to the location and DFSMSrmm does not segregate the volumes by shape. For example, if you specified a LOCDEF command with the media names:

```
LOCDEF LOCATION(MYLOC) MEDIANAME(3480,*)
```

then you could use the following media names on RMM ADDBIN subcommand requests:

```
RMM ADDBIN KG0002 LOCATION(MYLOC) MEDIANAME(3480)
```

and

```
RMM ADDBIN KG0100 LOCATION(MYLOC) MEDIANAME(*)
```

Note: The example shown in Figure 61 is not valid because the MEDIANAME(3420) was not listed on the LOCDEF parameters for the storage location.

```
RMM ADDBIN KG0005 LOCATION(MYLOC) MEDIANAME(3420)
```

Figure 61. Using a Medianame Not Defined in the LOCDEF Command

PRIORITY(1-9999)

Defines the priority of this location relative to other locations. Lower numbers have higher priorities. PRIORITY is used to determine where to move a volume when a volume is assigned multiple destinations based on matching to two or more vital record specification definitions. PRIORITY is used to select a location in case of a move conflict. Move conflicts include:

- Multiple data sets with different required locations on one volume.
- Multiple volumes with different required locations in one volume set and the DFSMSrmm EDGRMMxx parmlib option is set for movement by volume set.
- Multiple logical volumes with different required locations on one stacked volume.

You can override this value by specifying a PRIORITY on the vital record specification. If PRIORITY is omitted, priority is based on the location type:

Priority
Location Name or Type

2000 installation defined STORAGE type, including LOCAL, DISTANT, and REMOTE if they are specified on LOCDEF.

4800 AUTO automated tape libraries

4900 MANUAL manual tape libraries

5000 SHELF location

For each location you do not specify in a LOCDEF, the default priority is determined from the following list:

Priority
Location Name or Type

100 REMOTE location
200 DISTANT location
300 LOCAL location
2000 installation-defined STORAGE type
4800 AUTO automated tape libraries
4900 MANUAL manual tape libraries
5000 SHELF location

TYPE(STORAGE|LIBRARY)

Use this operand to identify the type of location you are defining. The value can be either STORAGE or LIBRARY. This operand is optional. If MEDIANAME or MANAGEMENTTYPE are specified, only TYPE(STORAGE) is valid. If you do not specify the TYPE operand DFSMSrmm sets a default value based on whether you specify the MEDIANAME or MANAGEMENTTYPE operands.

STORAGE
Specifies that the location is a storage location, either shelf-managed or non-shelf-managed.

LIBRARY
Specifies that the location is either SHELF or a system-managed library. The only reason to define these locations on LOCDEF parameters is to change the default priority for the location. For a LIBRARY type location the only LOCDEF operands you can use are PRIORITY and LOCATION.

You can change the shelf-management technique used in a location by specifying the LOCDEF command with the TYPE operand. The changed value applies to the vital record specifications you define after you make the change. To implement the change, you must change the location information in existing vital record specifications and run inventory management vital record processing. During vital record processing, DFSMSrmm changes the required location and location type for each volume.

Although vital record specifications must be updated and inventory management vital record processing must be run to implement the new LOCDEF TYPE value, you can use the new LOCDEF TYPE when issuing DFSMSrmm CHANGEVOLUME subcommands with the LOCATION operand.

Points on Usage:

1. A LOCDEF parameter is required in the DFSMSrmm parmlib member for each installation defined storage location name and when you want to define a movement priority for the location.

   If you have multiple systems sharing a control data set we recommend that you use the same LOCDEF commands on all sharing systems. However, you only need to define storage locations to the systems where you will use any RMM ADDVRS, ADDBIN or CHANGEVOLUME subcommands, and where you plan to run inventory management. During storage location management processing, DFSMSrmm ensures that the storage locations used during vital record processing are defined by LOCDEF commands. If you specify a system-managed library name on a LOCDEF command, DFSMSrmm validates that it is a library which is defined on the current system. If your system-managed libraries are not defined on all systems, DFSMSrmm assumes a TYPE(LIBRARY) location is manual tape library if it is not defined as a system-managed library. During inventory management vital record selection processing, if no priority is obtained from a vital record specification, DFSMSrmm obtains the priority from the LOCDEF commands. If no LOCDEF command is specified and DFSMSrmm knows that the location is a system-managed library, DFSMSrmm uses the default priority for the location type. Otherwise DFSMSrmm uses a priority of 9999.
2. If a LOCDEF parameter is altered or removed, existing bin numbers which are now in a location which is not defined via LOCDEF, or which have a media name which is no longer listed under the LOCDEF MEDIANAME operand, are handled correctly. Bin numbers are freed up when a volume is moved from the storage location or can be removed using the RMM DELETEBIN subcommand. You cannot add more bin numbers nor assign the bin numbers to new volumes going to the location.
3. Changes to LOCDEF PRIORITY or MEDIANAME operands take effect during the first run of vital record processing after DFSMSrmm has been stopped and restarted, or the MODIFY command used to update the changed LOCDEF parameters in parmlib.
4. Changes to LOCDEF MANAGEMENTTYPE or TYPE operands only take effect after the vital record specifications that refer to the value have been redefined, or when using the LOCATION operand on the RMM ADDVOLUME or CHANGEVOLUME subcommands.
5. See “Chapter 6. Managing Storage Locations” on page 107 for more information on LOCDEF and storage locations.

Defining Mount and Fetch Messages: MNTMSG

Use the MNTMSG command to tailor mount and fetch messages so they display the volume serial number, rack number, and pooling decision. The pooling decision can be a pool prefix, pool name, or storage group name. The operator can use this information to pull and mount volumes.

MNTMSG is an optional parmlib command. Specify a MNTMSG command for any message you want DFSMSrmm to update. When you specify the MNTMSG command, you must include all the MNTMSG operands.

DFSMSrmm inserts the required information within the message text or at the end of the message based on the value you use with the RACK operand. For non-specific mount requests, if you have defined a pool name with the VLPOOL command, DFSMSrmm provides a pool name or storage group name rather than a pool prefix in the message. DFSMSrmm updates mount messages with a pool name only when DFSMSrmm updates messages at the end of the message text.

Use the VOLUME operand to define the position of the volume serial number in a message. Figure 62 shows examples of the parmlib member EDGRMMxx MNTMSG command specified with the VOLUME operand defined for 4-digit device numbers. If your definitions specify a volume serial number offset 1 less than the value shown in the examples, your definitions are from MVS supported 3-digit device numbers and should be updated to match the position of the volume serial number when 4-digit device numbers are used.

```
     /* MNTMSG - Add RACK= or POOL= at end of WTOs           */
MNTMSG  MSGID(IEF233A)      ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID(IEF233D)      ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEF234E K')  ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEF234E R')  ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEF234E D')  ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEF455D')    ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID(IEC501A)      ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEC502E K')  ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEC502E D')  ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEC502E R ') ID(1) VOLUME(16) RACK(999)
MNTMSG  MSGID('IEC502E RD') ID(1) VOLUME(17) RACK(999)
MNTMSG  MSGID('IEC502E RK') ID(1) VOLUME(17) RACK(999)
MNTMSG  MSGID(IAT5110) ID(1) VOLUME(44) RACK(999)
MNTMSG  MSGID(IAT5210) ID(1) VOLUME(50) RACK(999)
MNTMSG  MSGID(IAT5410) ID(1) VOLUME(20) RACK(999)
```

Figure 62. Parmlib Member EDGRMMxx MNTMSG Command Examples for 4-digit Devices

JES3 Considerations: When you use the JES3 IATUX71 exit, use the RACK operand to determine if you want the the rack number to replace the volume serial number in the message or appended to the end of the message. If the RACK operand value indicates a position within the length of the message, DFSMSrmm replaces the volume serial number in the message with the required information. If the RACK operand value exceeds the message length, DFSMSrmm appends the information to the end of the message.

When the JES3 IATUX71 exit is not used, use the TYPE=MCS keyword on at least one CONSOLE statement in the JES3 parmlib. This activates JES3 MCS console support so JES3 issues messages as WTO messages rather than directly to JES3 consoles.

MNTMSG Command Syntax

Figure 63 shows the syntax of the MNTMSG command:



Figure 63. Parmlib Member EDGRMMxx MNTMSG Command Syntax

DFSMSrmm supplies a sample set of mount messages for your use. You can define additional MNTMSG commands to include other IBM operator messages and messages produced by your installation.

For example, if you define:

```
MNTMSG MSGID(IEF233A) ID(1) VOLUME(16) RACK(999)
```

your mount message displays the following:

```
IEF233A M 0480,999003,,J1400001,S0300 - RACK = T14103
```

If you specify the following:

```
MNTMSG MSGID(IEF233A) ID(1) VOLUME(16) RACK(16)
```

your mount message displays the following:

```
IEF233A M 0480,T14103,,J1400001,S0300
```

If you have a non-specific mount request where you have defined scratch pool AB* for that system, and you specify:

```
MNTMSG MSGID(IEF233A) ID(1) VOLUME(16) RACK(999)
```

your mount message displays the following:

```
IEF233A M 0480,PRIVAT,,J1400001,S0300 - POOL = AB****
```

If you specify:

```
MNTMSG MSGID(IEF233A) ID(1) VOLUME(16) RACK(16)
```

your mount message displays the following:

```
IEF233A M 0480,AB****,,J1400001,S0300
```

MNTMSG Command Operands

ID(*nnn***)**
Specifies the starting position of the message identifier. Specify a value between 1 and 128.

Default: None. You must specify ID when you define a MNTMSG command in parmlib.

MSGID(*nnnnnnnnnnnn***)**
Specifies message text 1 to 12 characters long. Normally the text is the message number, but it can include additional characters and blanks. You must enclose the MSGID value in quotes if you use blanks or special characters.

Default: None. You must specify MSGID when you define a MNTMSG command in parmlib.

RACK(*nnn***|999)**
Specifies the position to insert the rack number, pool prefix, pool name, or storage group in the message. Specify a value between 1 and 128 to insert the value within the message text.

Use 999 if you want to add the value to the end of the message.

DFSMSrmm adds either RACK=rack_number or POOL=pool_value to the end of the message if there is enough space for the additional information. If you specify RACK(999), DFSMSrmm adds '- POOL=pool_value' if a pool name or

storage group is substituted for a non-specific volume mount. If there is not enough space to add the information, DFSMSrmm overlays the end of the message text with the 6 to 8 character rack number or pool value preceded by a -. For a rack number, DFSMSrmm writes *nnnnnn*. For a pool prefix, DFSMSrmm writes *nnnnn**. For a pool name or storage group, DFSMSrmm writes *nnnnnnnn*.

- If you specify RACK(999), DFSMSrmm adds - RACK=*nnnnnn* if a rack number is added:

  ```
  IEF233A M 0480,999003,,J1400001,S0300 - RACK=T14103
  ```

- If you specify RACK(999), DFSMSrmm adds - POOL=*ppp** if a pool prefix is substituted for a non-specific volume mount:

  ```
  IEF233A M 0480,PRIVAT,,J1400001,S0300 - POOL=AB****
  ```

- If you specify RACK(999), DFSMSrmm adds - POOL=pool_value if a pool name is substituted for a non-specific volume mount.

  ```
  IEF233A M 0480,PRIVAT,,J1400001,S0300 - POOL=SCRTCH00
  ```

If there is not enough space to write the rack number or pool prefix, DFSMSrmm overwrites the end of the message text.

To display the pool prefix in the message, you must specify the SYSID operand on the VLPOOL command as described in “Defining Pools: VLPOOL” on page 148.

Default: None. You must specify RACK when you define a MNTMSG command in parmlib.

VOLUME(*nnn***)**
Specifies the position of the volume serial number in the message. Specify a value between 1 and 128.

Default: None. You must specify VOLUME when you define a MNTMSG command in parmlib.

Defining System Options: OPTION

Use the OPTION command to define the installation options for DFSMSrmm. Figure 64 on page 123 shows an example of the OPTION command and the operands you can code in the parmlib member EDGRMMxx.

```
OPTION  OPMODE(P)                  /* protect mode         */   -
        TPRACF(A)                  /* automatic            */   -
        NOTIFY(N)                  /* no notification      */   -
        SYSID(DG4)                 /* system name          */   -
        MAXHOLD(100)               /* number of records    */   -
        DSNAME(RMM.CONTROL.DSET)   /* control data set     */   -
        JRNLNAME(RMM.JOURNAL.DSET) /* journal              */   -
        JOURNALFULL(75)            /* journal percentage   */   -
                                   /* threshold            */   -
        CATRETPD(12)               /* catalog retention    */   -
        CATSYSID(*)                /* catalogs shared      */   -
        SMFAUD(248) SMFSEC(249)    /* SMF records          */   -
        DATEFORM(E)                /* European dates       */   -
        RETPD(5)                   /* default retention    */   -
        MAXRETPD(NOLIMIT)          /* maximum retention    */   -
        SCRATCHPROC(RMMSCR)        /* scratch procedure    */   -
        BACKUPPROC(RMMBKUP)        /* backup procedure     */   -
        CDSID(MVS2)                /* control data set ID  */   -
        BLP(RMM)                   /* bypass label process */   -
        VRSJOBNAME(2)              /* retention by job name*/   -
        MSG(M)                     /* message mixed case   */   -
        MASTEROVERWRITE(LAST)      /* overwrite default    */   -
        ACCOUNTING(J)              /* Account information  */   -
        VRSCHANGE(VERIFY)          /* VRS change information*/  -
        VRSMIN(1,FAIL)             /* VRS minimum          */   -
        VRSEL(OLD)                 /* VRS processing       */   -
        MOVEBY(VOLUME)             /* movement processing  */   -
        RETAINBY(VOLUME)           /* retention processing */   -
        PDA(ON)                    /* PDA trace enabled    */   -
        PDABLKCT(255)              /* PDA block count      */   -
        PDABLKSZ(12)               /* PDA blocksize        */   -
        PDALOG(OFF)                /* Disable trace logging*/   -
        SMSTAPE(UPDATE(EXITS,SCRATCH,COMMAND),PURGE(YES))       -
                                   /* TCDB update and purge*/  -
        TVEXTPURGE(RELEASE)        /* EDGTVEXT action      */
```

Figure 64. Parmlib Member EDGRMMxx OPTION Command Examples

OPTION Command Syntax

Figure 65 shows the syntax of the OPTION command:

Figure 65. Parmlib Member EDGRMMxx OPTION Command Syntax



Parmlib Member OPTION Command




OPMODE(
PROTECT
MANUAL
RECORD
WARNING
)
PDA(
ON
NONE
OFF
)
PDABLKCT(
255
nnn
)
PDABLKSZ(
blksz
nn
)
PDALOG(
ON
OFF
SWAP
)
RETAINBY(
VOLUME
SET
)
RETPD(
5
nnnn
)
SCRATCHPROC(
EDGXPROC
proc_name
)
SMFAUD(
No SMF audit records
nnn
)
SMFSEC(
No SMF security records
nnn
)
SYSID(
SMF System name
System name
)
SMSTAPE(
UPDATE options
PURGE(
ASIS
NO
YES
)
)
TPRACF(
NONE
PREDEFINED
AUTOMATIC
)
TVEXTPURGE(
RELEASE
NONE
EXPIRE
)

Parmlib Member OPTION Command



UPDATE Options:



OPTION Command Operands

ACCOUNTING(JOB|STEP)
Specifies whether DFSMSrmm records JOB or STEP accounting information along with volume information.

JOB
DFSMSrmm records the accounting information from the JOB statement of the JCL.

STEP
DFSMSrmm records the accounting information from the EXEC statement of the JCL. If you specify STEP and there is no accounting information in the EXEC statement, DFSMSrmm records the JOB statement accounting information.

Default: ACCOUNTING(JOB).

BACKUPPROC
Specifies the name of the procedure that you want to be started automatically when the journal percentage full threshold is reached.

Specify a valid alphanumeric procedure name from 1 to 8 characters. If no name is specified, then no automatic start command is issued. See “Automating Control Data Set Backup and Journal Clearing” on page 290 for more information.

Default: None.

BLP(RMM|NORMM)
Specifies how DFSMSrmm controls bypass label processing (BLP).

Authorization to perform BLP is still dependent on the ICHBLP resource in the RACF FACILITY class, and the ability to use BLP can still be controlled via JES.

Note: DFSMSrmm allows BLP processing to continue if a volume is mounted with a VOL1 header label that matches the volume serial number specified in JCL or if the volume has no label. When a labeled volume is mounted and the volume serial number does not match the requested volume, DFSMSrmm prevents processing when either volume is defined to DFSMSrmm. To circumvent this DFSMSrmm processing, you can request that DFSMSrmm ignores the volume serial number as described in “Using EDGUX100 to Ignore Duplicate or Undefined Volume Serial Numbers” on page 197.

RMM
You can use BLP for input from and output to volumes in user status, and for input from volumes in master status.

NORMM
You can use BLP under the normal system controls and DFSMSrmm records the activities you perform on tapes. You can also use BLP for input from and output to volumes in user and master status, and for output to scratch tapes. BLP can be used for reading and writing of master and user status tapes and for output to scratch tapes. BLP read of scratch tapes is not supported.

For scratch tapes written using BLP, DFSMSrmm changes the volume to master status and sets the initialize release action so that the tape is correctly labeled on return to scratch. DFSMSrmm also overrides the logical volume serial number generated by OPEN for BLP output to scratch tapes, so that the correct volume serial number is used for cataloging of data sets.

DFSMSrmm does not allow no label (NL) tapes to be mounted in response to a scratch request. However, you can use BLP to create NL tapes during scratch processing.

Default: BLP(RMM)

CATRETPD(*ret_hours*)
Specifies the number of hours from creation that a data set should be retained if it has not been cataloged and matches a vital record specification with the WHILECATALOG operand.

DFSMSrmm retains the data set for the catalog retention period if the data set has never been cataloged. DFSMSrmm does not retain the data set if DFSMSrmm detected that the data set was cataloged and then uncataloged during the catalog retention period.

ret_hours is 0-9999 hours. For example, CATRETPD(24) keeps data sets for 24 hours. Set *ret_hours* to 0 to request that DFSMSrmm does not perform this processing.

Default: CATRETPD(12).

CATSYSID(*|*sys_ID_list*)
Specify CATSYSID to enable DFSMSrmm catalog synchronization. Use the CATSYSID operand to identify the user catalogs you want tracked when you run the DFSMSrmm EDGHSKP utility with the CATSYNCH operand to exploit catalog status tracking. All the systems you identify must have the code that supports catalog synchronization. See“Running DFSMSrmm Catalog Synchronization” on page 257 for more information.

CATSYSID(*) means that all catalogs are fully shared. You must specify an * to specify that catalogs are fully shared so that any data set can be processed by DFSMSrmm on any DFSMSrmm subsystem.

CATSYSID(sys_ID_list) provides a list of DFSMSrmm system IDs that share tape data set user catalogs with this DFSMSrmm subsystem. You can identify up to 16 system IDs for DFSMSrmm subsystems. You must specify a list of system IDs when user catalogs are not shared and must ensure they are synchronized with the DFSMSrmm control data set before you run inventory management vital record processing.

Default: None.

CDSID(*ID*)
Specifies the identifier of the control data set that must be used on this system. Specify a value one to eight alphanumeric characters long.

When you start DFSMSrmm, the CDSID ID is compared to the ID in the control data set control record. If the IDs match, DFSMSrmm startup continues. If the control data set does not have an ID, DFSMSrmm creates the ID in the control record from the CDSID. If the IDs do not match, DFSMSrmm startup fails and DFSMSrmm issues a message to the operator to select another parmlib member.

If you do not specify a value for CDSID, you cannot use a control data set that already has an ID in its control record. See “Creating or Updating the Control Data Set Control Record” on page 303 for information about how the DFSMSrmm EDGUTIL utility sets the control data set ID.

Default: None.

DATEFORM(*AMERICAN*|*EUROPEAN*|*ISO*|*JULIAN*)
Specifies the date format for messages and reports. See “EXEC Parameters for EDGHSKP” on page 253 for information about setting different date formats for reports.

Value	Language	Format	Example
A	American	mm/dd/yyyy	12/15/1994
E	European	dd/mm/yyyy	15/12/1994
I	ISO	yyyy/mm/dd	1994/12/15
J	Julian	yyyy/ddd	1994/349

Default: DATEFORM(JULIAN)

DISPDDNAME(*DD_name*)
Specifies the name of the DD card which identifies the data set that contains disposition control statements that DFSMSrmm processes during CLOSE or EOV processing. The data set must be a sequential file and must be defined

with LRECL 80. The data set can be a member of a partitioned data set. When you specify the DISPDDNAME operand, you are requesting that DFSMSrmm performs disposition processing during CLOSE or EOV processing.

If you code DISPDDNAME, you must provide the name of the DD card that identifies the data set containing the disposition control statements optionally included in your JCL.

Default: None.

DISPMSGID(*message_id***)**
Specifies the message number that DFSMSrmm uses for write–to–operator messages specified in the disposition control file.

EDG4054I
The message text provides the device number, volume serial number, volume sequence, the location where the volume is to move, and any message text you defined in the disposition control file.

message_id
You can define any alphnumeric value of up to eight characters.

Default: Message EDG4054I.

DSNAME(*name***)**
Specifies the name of the DFSMSrmm control data set. Specify a name up to 44 characters long.

If you do not specify DSNAME, you must specify the data set name in the MASTER DD statement in the DFSMSrmm started procedure. If you specify a name both for DSNAME and MASTER DD, DFSMSrmm ignores the MASTER DD statement.

IPLDATE(*NO*|*YES***)**
Specifies whether IPL date checking is required. Specify *YES* to request IPL date checking, or *NO* to bypass it.

If you specify YES, DFSMSrmm issues a write-to-operator message during startup only if the date of the last run of expiration processing did not occur within two days of the current date. The message prompts the operator to enter the current date and day of the week. Initialization does not proceed until DFSMSrmm receives a valid reply. If you specify *NO* for this operand value, DFSMSrmm does not issue a message.

The IPLDATE operand helps prevent you from running expiration processing with an incorrect system date that can result in expiration of unexpired volumes.

Under normal conditions, the operator message requesting the current date is only issued once per IPL of MVS. If you restart DFSMSrmm, it does not recheck the date.

Additionally, if you run expiration processing daily, a message is not issued. As a result, it is possible under normal conditions to run for a long time and never have the operator prompted to confirm the system date.

Default: IPLDATE(NO)

JOURNALFULL(*nn*)
Specify JOURNALFULL to define a percentage full threshold for the journal data set. When DFSMSrmm detects that the journal has reached this threshold, DFSMSrmm issues message EDG2107E. DFSMSrmm also issues message EDG2107E at DFSMSrmm startup if the journal has already reached the threshold specified. DFSMSrmm issues message EDG2108E as a reminder until the backup completes and the journal is reset. If you specify a backup procedure name on the BACKUPPROC operand, the procedure is started automatically. If you specify a value of 0, DFSMSrmm issues no warnings on that system. You can specify different threshold values for sharing systems.

Specify a value in the range 0-99.

Default: 75.

JRNLNAME(*name*)
Specifies the name of the journal. Specify a name up to 44 characters long.

If you do not specify JRNLNAME in EDGRMMxx, you can specify a name in the JOURNAL DD statement in the DFSMSrmm started procedure. If you do not specify a journal name in either EDGRMMxx or the started procedure, DFSMSrmm does not provide journaling. If you specify a name in both, DFSMSrmm uses the JRNLNAME value and ignores the JOURNAL DD statement.

LINECOUNT(*nnn*)
Specifies the default number of lines per page for reports, including heading and trailer lines. Specify a value between 10 and 999.

You can override this value when producing individual reports by specifying a parameter to the report program or report utility as described in the *z/OS DFSMSrmm Reporting* book.

Default: LINECOUNT(*54*)

MASTEROVERWRITE(ADD|LAST|MATCH|USER)
Specify to control how DFSMSrmm allows the overwriting of a volume. You can use one of the following values:

ADD
Specify this value so new data can be created and no existing data can be destroyed. No existing file on a volume can be re-created, but the last file can have new data added to it. When adding data to the last file, DFSMSrmm checks that the data set name used must match the existing data set name. Select this option when you want the last file on the volume to be extended or a new file added to the volume.

LAST
Specify this value to ensure that when an existing file on a master volume is being written to that only the last file on the volume can be used. The data set name used must match the existing data set name. Select this option when you want the last file on the volume to be used for output.

MATCH
Specify this value to ensure that when an existing file on a master volume is being used for output that exactly the same data set name must be used. Select this option when you want any existing file on the volume to be re-created regardless of whether it is the last file on the volume as long as the same data set name is used.

When you use an existing tape file for output all the files which are higher in sequence are destroyed.

USER
Specify this value to allow any existing file on a master volume to be used for output regardless of the data set names being used and its relative file position on the volume. Select this option when you want validation of master volumes to be just the same as for user status volumes.

When you use an existing tape file for output all the files which are higher in sequence are destroyed.

Default: LAST.

MAXHOLD(*nnn*)
Specifies the maximum number of activities DFSMSrmm performs before the reserve is released and reacquired. For example, if you specify MAXHOLD(100) and you issue the RMM ADDRACK command with COUNT(1000), DFSMSrmm adds 100 racks before the reserve is released and reacquired. Specify MAXHOLD to minimize the impact that long operations, such as RMM TSO ADD subcommands with large COUNT values, or large searches, have to other users.

Even if the DASD where the control data set resides is not shared, consider specifying MAXHOLD because it controls how often users on the same system can gain access to the data set when a long task is running. MAXHOLD also influences the amount of virtual storage that DFSMSrmm uses. Increasing the value might improve the performance of individual DFSMSrmm functions, but other users are locked out from the control data set for a longer time. In a shared environment, the device is also reserved for a longer time, possibly impacting users of other data on the volume.

You do not normally need to alter this value. If your system is storage constrained, you might lower the value from 100 to reduce the amount of virtual storage that DFSMSrmm needs, and therefore its demand on real storage.

In a shared DASD environment in which you are using global resource serialization to convert the DFSMSrmm control data set reserve, you could increase the value to reduce the frequency of the release/reserve, which reduces the traffic on the global resource serialization ring. However, this action causes more virtual storage to be used and increases the time between releases of the control data set. The result is that other users wait longer before gaining access to the control data set.

Specify a value between 10 and 500. Under normal conditions, use the default value.

Default: MAXHOLD(*100*)

MAXRETPD(NOLIMIT|*nnnn*)
Specifies the maximum retention period that a user can request for data sets on volumes. Specify NOLIMIT or a value between 0 and 9999 days. When a value between 0 and 9999 days is specified, the value is added to the current date to determine the maximum allowed expiration date. Specify NOLIMIT to use the dates 99365 or 99366 which mean to never expire. If the calculated date is 31 December 1999, the expiration date 1 January 2000 is used.

MAXRETPD is always used to determine the volume expiration date. The volume expiration date can be ignored when EXPIRYDATEIGNORE is specified on all vital record specifications. MAXRETPD is important if the vital record specification specifies UNTILEXPIRED and the decision is based on the volume expiration date. The preferred method is to put the retention requirements all into the vital record specifications and make MAXRETPD=RETPD. If users are allowed to specify expiration and retention period to override vital record specifications, select a MAXRETPD that covers the maximum retention period they would like to enforce. If this forces 99365 to be reduced, define vital record specifications for any data that should be permanently retained, like DFSMShsm tape data.

Use MAXRETPD to set limits on the values that can be specified for EXPDT and RETPD.If the retention period or expiration date specified in the JCL exceeds the MAXRETPD value, DFSMSrmm overrides it and uses the value in MAXRETPD to determine the expiration date. The volume label has the JCL-specified value because DFSMSrmm does not change tape labels or system control blocks. The control data set contains the JCL-specified value as well as the expiration date calculated from MAXRETPD. You can display the JCL-specified value for information only.

If the DFSMSrmm ISPF dialog or RMM TSO subcommands are used to specify a retention period or expiration date that exceeds the MAXRETPD value, DFSMSrmm fails the subcommand or panel request.

For more information about how to automatically handle expiration date-protected tapes, see “Defining Pools: VLPOOL” on page 148 for information on EXPDTCHECK.

Default: MAXRETPD(NOLIMIT)

MOVEBY(SET|VOLUME)

Specify the MOVEBY operand to move volumes that are retained by DFSMSrmm vital record specifications as a set of volumes or as individual volumes.

SET

Specify this value when you want volumes moved as a set. DFSMSrmm moves all volumes in the same multi-volume set that are retained by vital record specifications. All the volumes are retained in the same location selected by the VRS priority or location priority for the volume.

VOLUME

Specify this value when you want volumes moved as individual volumes. DFSMSrmm moves the volumes without considering the location of the other volumes in the multi-volume set.

Default: VOLUME

MSG(MIXED|UPPER)

Specify to control the case for message text. You can use:

MIXED

Specify MIXED when you want messages to be displayed exactly as they appear in EDGMTAB. This includes mixed case message text.

UPPER
Specify UPPER to ensure that all messages are displayed in upper case only. Any mixed case messages in EDGMTAB are translated to upper case before they are displayed.

This is the value used when DFSMSrmm is inactive and utilities need to issue messages.

Default: MIXED.

NOTIFY(*NO*|*YES***)**
Specifies whether DFSMSrmm should automatically notify volume owners when the volumes they own become eligible for release or when software product volumes are added. Specify YES for automatically notify owners, or NO for notification. You must run DFSMSrmm under the JES2 or JES3 subsystem to use the DFSMSrmm NOTIFY function.

Specify YES and DFSMSrmm notifies the owner using the TSO TRANSMIT command to send an electronic message. The owner information in the DFSMSrmm control data set must include a valid user ID and node name for the message to be sent, and the volume record must specify Notify Owner as a release action.

Specify NO for expired volumes with a release action of notify and the librarian performs the notification. The librarian issues the RMM CHANGEVOLUME subcommand with the CONFIRMRELEASE operand to indicate that the notification has been performed.

Default: NOTIFY(NO).

OPMODE(MANUAL | RECORD | WARNING | PROTECT)
Specifies the running mode of DFSMSrmm. The running mode affects how DFSMSrmm enforces the tape mount validation rules described in “How Does DFSMSrmm Validate Tape Mounts?” on page 17. Protect mode is the only running mode that provides complete validation of volumes and rejection of volumes that do not adhere to DFSMSrmm tape mount validation rules. The running mode also affects other actions and defaults used by DFSMSrmm.

MANUAL — Manual mode. When DFSMSrmm is running in manual mode:

- DFSMSrmm does not record volume usage or validate volumes.
- DFSMSrmm does not provide information to OAM during entry or eject activities.
- You can use RMM TSO subcommands, the DFSMSrmm ISPF dialog, and inventory management functions for all types of media. Updates to the TCDB are controlled by the SMSTAPE parmlib option and affect the following functions:
  - Volume status updates if you run inventory management processing.
  - Any TSO command change that affects the information in the TCDB, such as EJECT, status change, and media information.

RECORD — Record-only mode. When DFSMSrmm is running in record mode: DFSMSrmm performs the actions described for manual mode and also:

- DFSMSrmm records information about tape volumes used on the system, including details about volume owners and data set names.
- DFSMSrmm does not validate or reject volumes during OPEN processing.

- You can use RMM TSO subcommands, the DFSMSrmm ISPF dialog, and inventory management functions for all types of media. Updates to the TCDB are controlled by the SMSTAPE parmlib option and affect the following functions.
  - Volume status updates if you run inventory management processing. Any TSO command change that affects the information in the TCDB, such as EJECT, status change, and media information.
  - Providing information to OAM during entry or eject activities.
  - Updates to the DFSMSrmm control data set based on OAM activity.
  - Controlling the disposition of TCDB volume records at EJECT time.
- DFSMSrmm provides no information to OAM during entry or eject activities and does not update the volume status in the TCDB during inventory management processing or command processing.
- DFSMSrmm tracks OAM changes in the DFMSMSrmm control data set.

WARNING — Warning mode. When DFSMSrmm is running in warning mode, DFSMSrmm performs the actions described for manual and record-only mode. DFSMSrmm issues warning messages when an action would have failed if DFSMSrmm was running in protect mode.

- DFSMSrmm records information about tape volumes used on the system, including details about volume owners and data set names.
- DFSMSrmm does not validate or reject volumes during OPEN processing.
- You can use RMM TSO subcommands, the DFSMSrmm ISPF dialog, and inventory management functions for all types of media. Updates to the TCDB are controlled by the SMSTAPE parmlib option and affect the following functions:
  - Volume status updates if you run inventory management processing.
  - Any TSO command change that affects the information in the TCDB, such as EJECT, status change, and media information.
  - Providing information to OAM during entry or eject activities.
  - Updates to the DFSMSrmm control data set based on OAM activity.
  - Controlling the disposition of TCDB volume records at EJECT time.

PROTECT — Protect mode. In protect mode, DFSMSrmm is fully operational. In addition to performing the actions described for manual and record-only mode, DFSMSrmm

- Validates all magnetic tape requests and rejects magnetic tape volume mounts under certain conditions, discussed in “How Does DFSMSrmm Validate Tape Mounts?” on page 17.
- Sets the UNCATALOG operand default to YES. UNCATALOG(YES) specifies that DFSMSrmm should uncatalog data sets under conditions described in the UNCATALOG operand description. During OAM exit processing, DFSMSrmm validates all changes to the TCDB and fails those that are not allowed. During cartridge entry processing, DFSMSrmm information overrides information provided by OAM. DFSMSrmm always updates the TCDB. Use SMSTAPE(PURGE) to control the purging or keeping of records in the TCDB during eject processing.

Note: DFSMSrmm processes some parmlib options you have set even when DFSMSrmm does not validate or reject volumes. For example, if you set the TPRACF or UNCATALOG operands described in this section, DFSMSrmm honors these operands when running in any mode. For

example if you specify UNCATALOG(YES) and OPMODE(RECORD), DFSMSrmm uncatalogs data sets even though DFSMSrmm does not validate or reject volumes. When you specify OPMODE(WARNING) or OPMODE(PROTECT), DFSMSrmm also honors the setting of the VLPOOL EXPDTCHECK options. To obtain the results you desire, you should review the values you select for these additional options.

Table 18 and Table 19 provide information about the options which are affected by the OPMODE value.

Table 18. How OPMODE Honors the Settings of Various Options

Option	Manual	Record Only	Warning	Protect
EXPDTCHECK	N	N	Y	Y
UNCATALOG	Y	Y	Y	Y
TPRACF	Y	Y	Y	Y
SMSTAPE(UPDATE)	Y	Y	Y	N
SMSTAPE(PURGE)	N	Y	Y	Y

Table 19. How OPMODE Value Affects System-Managed Tape Library Support

Main Area of Activity	Manual	Record Only	Warning	Protect
Command Processing	N	N	N	Y
Expiration Processing	N	N	N	Y
Support for CBRUXxxx Exits	Y	N	N	Y
Purging TCDB Records During Eject Processing	Y	N	N	Y

Default: OPMODE(PROTECT).

PDA(*ON*|*NONE*|*OFF***)**
Specify to enable or disable the PDA trace facility.

NONE
Specify to prevent DFSMSrmm from enabling the PDA facility. If NONE is specified at startup, DFSMSrmm does not obtain storage for the trace buffer. If NONE is specified when DFSMSrmm is refreshed, it is equivalent to specifying PDA(OFF) and PDALOG(OFF).

OFF
Specify to disable the trace facility after DFSMSrmm initialization. When the trace facility is disabled, trace data is not accumulated.

ON
Specify to enable the trace facility.

Default: ON.

PDABLKCT(*nnn***)**
Specifies the number of blocks or buffers that make up the in-storage trace

wrap table. Each block or buffer is the size specified by the PDABLKSZ operand. *nnn* is a minimum of 3 and a maximum of 255.

Default: 255.

PDABLKSZ(*blksz***)**
Specifies the DASD blocksize for the DFSMSrmm PDA trace facility data sets, EDGPDOX and EDGPDOY. *nn* is the number of kilobytes in each DASD block and is a minimum of 1 and a maximum of 31.

The default is 27 for 3390 DASD devices, 22 for 3380 DASD devices, and 12 for all other DASD devices.

PDALOG(*ON*|*OFF***)**
Specify to enable or disable output to the PDA trace data sets.

OFF
Specify to disable output to the PDA trace data sets.

ON
Specify to enable output to the PDA trace data sets.

Default: ON.

RETAINBY(SET|VOLUME)
Use the RETAINBY option to specify whether DFSMSrmm retains multi-volume sets as a set or as individual volumes.

SET
When you retain by set, if any volume in a set is retained by a vital record specification, all volumes in the set are retained as vital records. DFSMSrmm uses highest retention date of all volumes in the set as the retention date for all volumes retained as vital records in a set. If no volume in a set is retained by a vital record specification, DFSMSrmm performs expiration processing by set. DFSMSrmm does not expire volumes in a set if at least one volume in a set is still not ready to expire because it has not reached its expiration date and you have not specified that you want the expiration date ignored.

VOLUME
When you retain by volume, DFSMSrmm retains a volume based on vital record specifications and on the volume expiration date. DFSMSrmm does not consider other volumes in the set.

DFSMSrmm sets an indicator 'retained by set' in the volume information when a volume is vital record specification retained or not expired only because it is a member of a set.

The location where volumes are retained is determined by the MOVEBY option.

Default: RETAINBY(VOLUME).

RETPD(*nnnn***)**
Specifies the default retention period for all new data sets on volumes. Specify a value between 0 and 9999 days. The specified value is added to the current date to determine the expiration date. Select a default retention for parmlib RETPD that is a small value that will ensure that all tape data created outside the service levels will be released as soon as possible. Note that the MAXRETPD value you specify in the parmlib limits the calculated expiration date.

DFSMSrmm sets a default retention period as follows:

- If you specify RETPD or EXPDT, the value is used as the volume's new expiration date. If you do not specify RETPD or EXPTD, DFSMSrmm uses the EXPDT or RETPD allocation attribute of a data class, if all the following are true:
  - The Storage Management Subsystem is active
  - The data set is associated with a data class, either explicitly by the DATACLAS keyword on the JCL or implicitly by an automatic class selection routine
  - The data class has an EXPDT or RETPD allocation attribute
- If you do not specify RETPD or EXPDT, DFSMSrmm uses the default retention period set in EDGRMMxx.

Whenever a new data set is written to tape, DFSMSrmm checks whether the volume's expiration date should be updated, based on whether the new data set has a longer expiration date than the volume on which it is written. DFSMSrmm gets the expiration date for a data set from the job file control block (JFCB) at open time. If there is a date in the JFCB, DFSMSrmm compares this date to the current expiration date for the volume. If the date in the JFCB allows the volume to be retained longer, DFSMSrmm uses that date to update the volume's expiration date.

If there is no expiration date in the JFCB, DFSMSrmm uses the EDGRMMxx RETPD value to calculate the new expiration date. If the RETPD value allows the volume to be retained longer, DFSMSrmm uses that date to update the volume's expiration date.

You can set the date in the JFCB in several ways, including:

- RETPD and EXPDT keywords in the JCL
- Data class when the Storage Management Subsystem is active and the volume is system-managed
- Management class when the Storage Management Subsystem is active and the volume is system-managed
- A user program, using the RDJFCB macro and the OPEN TYPE=J after modifying the JFCB
- Installation exits in use on your particular system

Use vital record specifications to define more specific default retention periods for users by using a data set name prefix. For example, specify:

```
RMM ADDVRS DSNAME('RICK.**') DAYS COUNT(30)
```

to keep all data sets for ID RICK for 30 days. For more information about using vital record specifications, see *z/OS DFSMSrmm Guide and Reference*.

Default: RETPD(*5*)

SCRATCHPROC(*proc_name***)**
Specifies the name of the procedure DFSMSrmm starts to replenish scratch volumes in an automated tape library dataserver. Specify a procedure name one to eight characters long.

You must run DFSMSrmm with a scratch procedure. You can modify or replace the DFSMSrmm-supplied sample, EDGXPROC, to support your location procedures. You can use the scratch procedure to take any action you would

like. For example, you can code the procedure to trigger the required inventory management expiration processing job, to run inventory management, or to take no action.

When an automated tape library dataserver detects a low-on-scratch condition, OAM issues a write-to-operator message (CBR3660A). DFSMSrmm intercepts the message and starts the SCRATCHPROC procedure. This procedure runs DFSMSrmm expiration processing to replenish the automated tape library dataserver's scratch volumes.

Default: SCRATCHPROC(EDGXPROC)

See "Replenishing Scratch Volumes in a System-Managed Library" on page 340 for information about EDGXPROC the DFSMSrmm default procedure.

SMFAUD(*nnn*)
Specifies the SMF record number to be used for audit records. Specify a number between 128 and 255 that is different from the value for SMFSEC. The value must conform to standard SMF conventions.

If you do not specify a number, DFSMSrmm does not produce audit records.

Default: No audit records

SMFSEC(*nnn*)
Specifies the SMF record number to be used for security records. Specify a number between 128 and 255 that is different from the value for SMFAUD. The value must conform to standard SMF conventions.

If you do not specify a number, DFSMSrmm does not produce security records.

Default: No security records

SMSTAPE(UPDATE | PURGE)
Use SMSTAPE to specify how DFSMSrmm updates the TCDB and controls system-managed tape processing.

UPDATE
Use UPDATE to select the system-managed tape functions DFSMSrmm provides. The UPDATE operand has 3 subparameters, EXITS, SCRATCH, and COMMAND. You can specify one or more of the subparameters. When DFSMSrmm is running in PROTECT mode, DFSMSrmm ignores the UPDATE operand and performs processing as if you specified EXITS, SCRATCH, and COMMAND. When DFSMSrmm is running in WARNING or RECORD mode, DFSMSrmm does not update TCDB information unless you request the update. You can specify one or more of the values. When you specify a value, DFSMSrmm performs the updates to the TCDB.

- Specify EXITS when you want DFSMSrmm volume status information to override the OAM volume status during entry processing and you want to use the DFSMSrmm VNL exit.
- Specify SCRATCH when you want DFSMSrmm to update the volume status in the TCDB during expiration processing when volumes are returned to scratch status.
- Specify COMMAND when you want to use the RMM TSO subcommands or the DFSMSrmm API to update the TCDB. This controls change of status, TDSI and owner information, eject processing and manual cartridge entry processing.

Default: UPDATE(EXITS,SCRATCH,COMMAND) when DFSMSrmm is running in PROTECT MODE.

PURGE
Use PURGE to control how DFSMSrmm affects the TCDB volume records during EJECT processing. The default is PURGE(ASIS) in all operating modes except MANUAL mode. In manual mode, DFSMSrmm provides no support for eject processing.

ASIS
Specify ASIS when you do not want DFSMSrmm to determine the TCDB volume record dispositions at eject time. Specifying ASIS allows the eject requestor or Library defaults to control the TCDB volume record disposition

NO
Specify NO to request that DFSMSrmm prevent TCDB records being deleted.

YES
Specify YES when you want DFSMSrmm to force the TCDB volume records to be purged at eject time.

Default: ASIS.

SYSID(*system_name***)**
Specifies the name of the system running DFSMSrmm. Specify a unique system name one to eight characters long.

DFSMSrmm uses the SYSID system name for information stored in the control data set. DFSMSrmm also uses SYSID to match the SYSID specified in the VLPOOL definitions. If you have unshared catalogs and specify a list of system IDs for the CATSYSID operand, select the SYSID values from the values you currently specify and previously have specified for SYSID on each system.

If you are running multiple MVS systems and sharing the control data set and journal, specify a unique SYSID for each system.

Default: DFSMSrmm uses the system's SMF identification.

TPRACF(NO/PREDEFINED/AUTOMATIC)
Specifies the type of RACF tape support for DFSMSrmm to provide. Use this operand when you want DFSMSrmm to maintain the security profiles that protect tape volumes. You can define RACF tape support for pools of volumes within your installation by using the VLPOOL RACF command described in "Defining Pools: VLPOOL" on page 148. RACF tape support you define can be overridden by RACF tape support you define with VLPOOL.

Note: DFSMSrmm honors the TPRACF setting when running in all modes.
N —When you specify TPRACF(N), DFSMSrmm does not create RACF tape profiles for any volumes in your installation. If you also specify:
– VLPOOL RACF(N) or VLPOOL RACF(Y)

DFSMSrmm does not create tape profiles or TVTOCS for volumes in the pool you are defining with the VLPOOL command.
P —When you specify TPRACF(P), DFSMSrmm creates predefined RACF tape profiles for any volumes in your installation. If you specify:
– VLPOOL RACF(N)

DFSMSrmm does not create tape profiles or TVTOCS for volumes in the pool you are defining with the VLPOOL command.

– VLPOOL RACF(Y)

DFSMSrmm creates RACF tape profiles for volumes in the pool you are defining with the VLPOOL command. The RACF tape profiles are created using RACF options you have specified and the RACF tape profiles that DFSMSrmm creates when RMM ADDVOLUME, CHANGEVOLUME, or DELETEVOLUME subcommands are issued.

DFSMSrmm deletes TAPEVOL profiles during recycling of scratch tapes if the profiles exist. This recycling ensures that any profiles are cleaned up.

DFSMSrmm creates a profile when a volume used for output does not have a RACF tape profile defined.

The owner of the volume is given RACF access to the profile.

If TAPEVOL and TAPEDSN are active, DFSMSrmm creates a TVTOC and adds the first file data set entry.

A — When you specify TPRACF(A), DFSMSrmm creates tape profiles for any volume in your installation. If you also specify:

– VLPOOL RACF(N)

DFSMSrmm does not create tape profiles or TVTOCS for volumes in the pool you are defining with the VLPOOL command.

– VLPOOL RACF(Y)

DFSMSrmm creates RACF tape profiles for volumes in the pool. Table 29 on page 165 shows what DFSMSrmm processing takes place when you specify RACF(Y) for a pool.

The processing is the same as TPRACF(P), except that:

– Scratch tape volumes do not have TAPEVOL profiles created.
– IF TAPEVOL and TAPEDSN are active, RACF automatically creates TAPEVOL and data set profiles for the ADSP and PROTECT=YES users.
– This operand also supports the environment where an installation uses RACF installation exits to create TAPEVOL profiles.

If you set TPRACF(P) or TPRACF(A), DFSMSrmm ensures that your tapes are protected by RACF. DFSMSrmm ensures that all non-scratch tapes are protected by a discrete RACF TAPEVOL profile. DFSMSrmm checks that a RACF profile exists whenever a data set is written on a tape. If a profile does not exist, DFSMSrmm creates one. Therefore you do not need to use RACF installation exits to set the JCL PROTECT=YES option or specify PROTECT=YES in your JCL. You can use generic data set profiles for all tape data sets without changes to JCL or installation procedures, if you used the VLPOOL command with the RACF(Y) operand because DFSMSrmm creates a TVTOC when the RACF TAPEDSN option is used.

For both TPRACF(P) and TPRACF(A), TAPEVOL profiles are always deleted during recycling of scratch volumes, if they exist. This recycling ensures that any profiles created are cleaned up. When you use a volume for output and there is no RACF protection for the volume when you close the data set, DFSMSrmm creates a profile to protect the volume. The owner of the volume is given RACF access to the profile. If TAPEVOL and TAPEDSN are active, DFSMSrmm creates a TVTOC and adds the first file data set entry.

For more information on RACF processing and security options, see “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.

Default: TPRACF(*N*)

TVEXTPURGE(RELEASE | EXPIRE | NONE)
Specifies how DFSMSrmm processes volumes to be purged by callers of EDGTVEXT or EDGDFHSM.

- NONE — DFSMSrmm take no action for volumes to be purged.
- RELEASE — DFSMSrmm releases volume to be purged according to the release actions set for the volume. You must run expiration processing to return a volume to scratch status.
- EXPIRE — Use the EXPIRE option to set the volume expiration date to the current date for volumes to be purged. Use this operand in combination with vital record specifications that use the UNTILEXPIRED retention type. You can then optionally extend retention using the extra days retention type.

Default: RELEASE

UNCATALOG(*YES*|*NO*|*SCRATCH***)**
Specifies the type of catalog support to provide:
N — Do not use DFSMSrmm catalog processing. DFSMSrmm does not uncatalog data sets under any circumstances.
Y — always uncatalog data sets. Use DFSMSrmm catalog processing. DFSMSrmm uncatalogs data sets when:

- A volume is returned to scratch status, DFSMSrmm uncatalogs all the data sets on the volume.
- The RMM DELETEVOLUME FORCE subcommand is issued for a volume, DFSMSrmm uncatalogs all the data sets on the volume.
- The RMM CHANGEVOLUME DSNAME subcommand is issued for a volume, DFSMSrmm uncatalogs all the data sets on the volume. If the data set name specified on the RMM CHANGEVOLUME subcommand command matches the data set name on the volume, then DFSMSrmm only uncatalogs subsequent data sets.
- The RMM DELETEDATASET subcommand is issued for a data set, DFSMSrmm uncatalogs the data set. Also, DFSMSrmm uncatalogs all data sets recorded on the same volume with higher data set sequence numbers.
- A tape data set is overwritten, DFSMSrmm uncatalogs the data set. Also, all data sets recorded on the same volume with higher data set sequence numbers are uncataloged.

S — Only uncatalog data sets when the volume on which they reside is returned to scratch status.

Default: The default is UNCATALOG(N) unless DFSMSrmm is running in protect mode. DFSMSrmm uses the UNCATALOG default of Y when DFSMSrmm is running in protect mode.

If you set UNCATALOG(S) or UNCATALOG(Y), DFSMSrmm can uncatalog data sets even when DFSMSrmm is running in manual, record, or warning mode.

You should use the UNCATALOG(N) option during early implementation of DFSMSrmm on your system, when DFSMSrmm is running at the same time as your existing management software.

If you use the DFSMSrmm EDGUX100 exit to request suppression of data set recording for a volume, you should ensure that any data sets that are cataloged, but not recorded by DFSMSrmm are uncataloged by some other mechanism. Leaving non-existent data sets cataloged could lead to later processing problems.

If you use the UNCATALOG(N) option to prevent DFSMSrmm from uncataloging tape data sets, you should ensure that data sets are uncataloged by some other mechanism. Leaving non-existent data sets cataloged could lead to later processing problems.

Integrated catalog facility catalogs must be shared if catalog control is required or if UNCATALOG(Y) or (S) is coded.

VRSCHANGE(INFO|VERIFY)
Use VRSCHANGE to specify the action that DFSMSrmm should take during inventory management if you have made any changes to vital record specifications using RMM ADDVRS or RMM DELETEVRS subcommands.

If You Specify	Then
INFO	No additional processing or actions are required when vital record specification changes occur.
VERIFY	Any changes made to vital record specifications must be verified by running EDGHSKP vital record processing using the VERIFY parameter. DFSMSrmm must issue return code zero before EDGHSKP vital record processing can be performed to update the control data set.

Default: VERIFY.

VRSJOBNAME(*1*|*2*)
Use VRSJOBNAME to select how DFSMSrmm uses a job name in a vital record specification to match a data set to a movement and retention policy. DFSMSrmm records the data set name and job name for new tape files you create. You can define the name of the job that created a data set by using the RMM ADDDATASET subcommand or the CHANGEDATASET subcommand for existing data sets. You can specify a job name and data set name in a vital record specification so that data sets that match the data set name and job name are moved and retained by the policy defined in the vital record specification.

If You Specify	DFSMSrmm Uses	And if There Is No Match
VRSJOBNAME(1)	The data set and job name to match a data set to a vital record specification. Job name is the primary value used to match the data set to a vital record specification.	A match by data set name only is acceptable.
VRSJOBNAME(2)	The data set name to match a data set to a vital record specification. If a data set matches multiple vital record specifications with the same data set name, then DFSMSrmm uses a job name to further qualify the data set name.	DFSMSrmm does not apply a policies to the data set.

Default: VRSJOBNAME(2).

VRSMIN(*count*,*action*)

Use VRSMIN to specify a minimum number of vital record specifications required by inventory management vital record processing, and the action to be taken by DFSMSrmm when the minimum number of vital record specifications are not defined. DFSMSrmm counts the vital record specifications used by vital record processing. DFSMSrmm does not count vital record specifications that are deleted during vital record processing.

count can be 0 to 2,147,483,647. Specify a count value of 0 to disable this checking.

The default count value is 1. Specify *action* to control the action DFSMSrmm takes when the *count* is not reached. *action* can be FAIL, INFO, or WARN.

If You Specify	DFSMSrmm
FAIL	Issues message EDG2229I to the MESSAGE file and stops inventory management processing. Processing ends with return code 8.
INFO	Issues message EDG2229I to the MESSAGE file and processing continues.
WARN	Issues message EDG2229I to the MESSAGE file and sets a minimum return code of 4. Processing continues.

Default: FAIL.

VRSEL(OLD/NEW)

Use VRSEL to control how DFSMSrmm inventory management vital record processing uses retention and movement information defined in vital record specifications.

OLD

Specify OLD if you want DFSMSrmm to:

- Ignore retention information defined in NAME vital record specifications
- Ignore release options defined in vital record specifications
- Treat the ANDVRS in the RMM ADDVRS command as if it is a NEXTVRS

NEW

Specify NEW if you want DFSMSrmm to process retention information in NAME vital record specifications, release options defined in vital record specifications, and vital record specifications chained using the RMM ADDVRS ANDVRS operand.

Default: OLD.

Defining Tapes Not Available on Systems: REJECT

Use the REJECT command to prevent a range of tapes from being used on a particular system. For example, you can reject production tapes on a development system.

This command is useful when you are:

- Using a shared RACF data set and the security profiles for a volume allow the volume to be used on all systems.
- Partitioning tape libraries as described in “Partitioning System-managed Tape Libraries” on page 101.

The REJECT command helps you limit tape usage at the system level. Figure 66 shows an example of the REJECT command and the operands you can code in the parmlib member EDGRMMxx.

```
REJECT OUTPUT(CC12*)
REJECT ANYUSE(VM1*),OUTPUT(VM*)
REJECT ANYUSE(DD0*)
REJECT ANYUSE(*)
```

Figure 66. Parmlib Member EDGRMMxx REJECT Command Examples

REJECT Command Syntax

Figure 67 shows the syntax of the REJECT command:



Figure 67. Parmlib Member EDGRMMxx REJECT Command Syntax

You can specify multiple REJECT commands to define different ranges of tapes. However, use only one ANYUSE operand and one OUTPUT operand for each REJECT command, as shown in Figure 66.

DFSMSrmm allows all volume mounts. DFSMSrmm checks volume validity only when a data set on the volume is opened. When a data set on a volume is opened, DFSMSrmm checks the volume’s shelf location against the prefixes specified in the REJECT command. If a volume has no library shelf location, DFSMSrmm checks the volume serial number against the prefixes specified in the REJECT command. DFSMSrmm recognizes the most specific prefix match. If you specify both ANYUSE and OUTPUT for the same prefix, ANYUSE overrides OUTPUT. Normally, REJECT prefixes match those used on VLPOOL definitions, but it is not mandatory.

At OPEN time, DFSMSrmm can reject a range of tapes if you define the range of volumes to DFSMSrmm. DFSMSrmm cannot reject a range of tapes not defined to it.

You can use the REJECT ANYUSE command with an automated tape library dataserver to prevent volumes from being automatically defined in the TCDB when they are entered in an automated tape library dataserver. If the volume matches the REJECT ANYUSE command, the volume is not defined to the TCDB. Another system sharing the automated tape library dataserver can take the volume to define

it in its TCDB only. You can also prevent a volume from being defined in the TCDB by specifying other than the USE(MVS) attribute when defining the volume to DFSMSrmm.

If you use REJECT OUTPUT commands, the volume is defined in the TCDB and can be entered into an automated tape library dataserver.

Use caution when using the REJECT command with an automated tape library dataserver as it is possible to continue rejecting volumes needlessly.

REJECT Command Operands

ANYUSE(*prefix***)**
Specifies the shelf locations of volumes not available for read or write processing. *prefix* is a generic shelf location consisting of a one to five character prefix followed by an *. Specify a single asterisk if, at OPEN time, you want to reject all volumes not defined to DFSMSrmm. For example, ANYUSE(*) prevents foreign tapes from being used, unless you use the installation exit, EDGUX100, to request that DFSMSrmm ignore such tapes.

Default: None.

OUTPUT(*prefix***)**
Specifies the shelf locations of volumes not available for write processing. *prefix* is a generic shelf location consisting of a one to five character prefix followed by an *. Specify a single asterisk if, at OPEN time, you want to prohibit writing to all volumes not defined to DFSMSrmm.

Default: None.

Defining Security Classes: SECCLS

Use the SECCLS command to define security classes for data sets and volumes. These security classes appear in reports and RMM TSO subcommand output. DFSMSrmm records these security classes in the DFSMSrmm control data set only; it does not make RACF aware of them. There is no connection between these definitions and any similar definitions or function provided in RACF, but you can use similar values for overall consistency.

DFSMSrmm determines the security classification of a tape volume with multiple data sets by the highest classification found for a single data set.

Data sets that do not match any of the masks specified in SECCLS definitions are assigned no security classification. DFSMSrmm uses a number 0 to indicate no security classification. Whenever you create a tape data set, DFSMSrmm uses the SECCLS masks to classify data sets and volumes. Figure 68 on page 146 shows an example of the SECCLS command and the operands you can code in the parmlib member EDGRMMxx.

If you remove a security class that is assigned to a volume, DFSMSrmm issues an error message when a data set on the volume is opened. DFSMSrmm also treats the volume as having the lowest defined security level. The default security class is defined by a mask of '**'.

Parmlib Member SECCLS Command

```
SECCLS  NUMBER(01)                                  -
        NAME(UNCLASS)                               -
        DESCRIPTION('UNCLASSIFIED')                 -
        MASK('**')                                  -
        SMF(N)                                      -
        MESSAGE(N)                                  -
        ERASE(N)
SECCLS  NUMBER(02)                                  -
        NAME(U)                                     -
        DESCRIPTION('UNCLASS')                      -
        MASK('STSGAM.**')                           -
        SMF(N)                                      -
        MESSAGE(N)                                  -
        ERASE(N)
SECCLS  NUMBER(10)                                  -
        NAME(IUO)                                   -
        DESCRIPTION('INTERNAL USE ONLY')            -
        SMF(N)                                      -
        MESSAGE(N)                                  -
        ERASE(N)                                    -
        MASK('SYS1.IUO.**')
SECCLS  NUMBER(30)                                  -
        NAME(CC)                                    -
        DESCRIPTION('CONFIDENTIAL')                 -
        MASK('PAYROLL.**')                          -
        SMF(Y)                                      -
        MESSAGE(N)                                  -
        ERASE(Y)
```

Figure 68. Parmlib Member EDGRMMxx SECCLS Command Examples

SECCLS Command Syntax

Figure 69 shows the syntax of the SECCLS command:



Figure 69. Parmlib Member EDGRMMxx SECCLS Command Syntax

To make the default security class the highest level, specify the following operands with the SECCLS command:

```
SECCLS NUMBER(255) MASK('**')
```

If you do not specify any SECCLS statements, DFSMSrmm defaults to a classification of blanks.

SECCLS Command Operands

DESCRIPTION(*'cc.....cc'***)**
Describes the security class. DFSMSrmm uses the description you provide as the security class name. Specify a description between 1 and 32 characters.

Default: None. You must specify this operand.

ERASE(*N*|*Y***)**
Specifies whether volumes must be erased on release. *Y* indicates volumes must be erased on released, and *N* indicates that they do not have to be.

You can use the DFSMSrmm utility EDGINERS to automatically erase and reinitialize tapes or you can use your own method to erase them.

Default: ERASE(N)

MASK(*'dsname_mask'***)**
Specifies a data set name mask used for assigning a security classification. In addition to standard data set naming conventions, you can use the following masking characters to create the data set name mask:

***** A single * represents a single qualifier of any number of characters.

a single * when used within a qualifier represents zero or more characters.

more than one single * can be used within a qualifier as long as a character precedes or follows the *.

.** represents zero or more qualifiers. At the end of the mask, it indicates to ignore any remaining characters.

** indicates to select all data sets.

% (percent_sign)
A place holder for a single character.

For example, you can specify MASK('USERID.**.CONF.**').

Default: You are required to specified this operand.

MESSAGE | MSG(*N*|*Y***)**
Specifies whether to issue operator confirmation messages when a data set on a volume in this security class is opened. Specify *Y* to issue operator confirmation messages for this class, or *N* to suppress the messages. The message number is EDG4008A.

You can use this opportunity to perform any local operation procedures, such as adding a security sticker to a volume.

Default: MSG(*N*)

NAME(*name***)**
Specifies a name for the security class. The name is used for reports and communication with users. Specify a value between 1 and 8 characters.

Default: None. You are required to specify this operand.

NUMBER(*nnn***)**
Specifies a security classification number between 1 and 255.

The security classification numbers indicate relative levels of importance. Higher numbers mean higher levels of security. Your installation can assign more specific meanings to the numbers.

Default: None. You are required to specify this operand.

SMF(*N*|*Y*)
Specifies whether to write an SMF security record each time a tape data set in this class is opened. *Y* means to write an SMF record, and *N* means not to write it. See “Chapter 14. Creating Reports with DFSMSrmm” on page 283 for information on using EDGAUD to produce a report for these SMF records.

Default: SMF(*N*)

Defining Pools: VLPOOL

Use the VLPOOL command to define pools. See “Chapter 3. Organizing the Removable Media Library” on page 55 for information about pooling. When you add a new volume to the library, DFSMSrmm assigns it a shelf location from the specified pool. Figure 70 shows an example of the VLPOOL command and the operands you can code in the parmlib member EDGRMMxx.

```
VLPOOL PREFIX(Y2*) TYPE(R) DESCRIPTION('CUSTOMER REEL TAPES') -
         MEDIANAME(3420) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(Y3*) TYPE(R) DESCRIPTION('CUSTOMER 3480 CARTRIDGES') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(P0*) TYPE(R) DESCRIPTION('SOFTWARE PRODUCT REELS') -
         MEDIANAME(3420) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(P2*) TYPE(R) DESCRIPTION('SOFTWARE CARTRIDGES') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(C*) TYPE(R) DESCRIPTION('MVS AND VM BACKUP TAPES') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(X8*) TYPE(R) DESCRIPTION('IN TAPES') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(M*) TYPE(S) DESCRIPTION('SCRATCH POOL') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y) SYSID(DG4)
VLPOOL PREFIX(*) TYPE(R) DESCRIPTION('EVERYTHING ELSE') -
         MEDIANAME(3480) RACF(Y) EXPDTCHECK(Y)
VLPOOL PREFIX(*) NAME(DEFAULT) TYPE(S) SYSID(SYS1) -
         DESCRIPTION('Default pool')
VLPOOL PREFIX(S*) NAME(SPECIAL) TYPE(R) -
         DESCRIPTION('EDGUX100 set pool')
```

Figure 70. Parmlib Member EDGRMMxx VLPOOL Command Examples

VLPOOL Command Syntax

Figure 71 shows the syntax of the VLPOOL command:



Figure 71. Parmlib Member EDGRMMxx VLPOOL Command Syntax

Each VLPOOL command defines a pool. Each generic shelf location defined by PREFIX must be unique. If you do not specify any VLPOOL commands, or do not specify a VLPOOL command for POOL(*), DFSMSrmm automatically creates a default pool definition that includes all the shelf locations and volumes in them. The defaults for this pool are:

```
VLPOOL RACF(N) TYPE(S) EXPDTCHECK(O) MEDIANAME(3480) -
  DESCRIPTION('DEFAULT POOL') PREFIX(*)
```

VLPOOL Command Operands

DESCRIPTION(*'c.....c'***)**
Describes the pool. Specify a description between 1 and 32 characters. You must enclose the value in quotes if you use blanks or special characters.

Default: None. You are required to specify this operand.

EXPDTCHECK(*Y|N|O***)**
Specifies to automate the processing of unexpired tape data sets at the pool level.

N indicates that DFSMSrmm is not to check or validate the expiration date of data sets on a tape. It allows the tape to be overwritten after the system has checked the validity of the tape. DFSMSrmm does not overwrite or replace the expiration date on the tape. This situation happens when a volume is released early, or when someone changes its expiration date or retention period using the RMM TSO subcommands.

We recommend you specify N when running a DFSMSrmm-managed scratch tape pool. DFSMSrmm lets you reuse tapes only when it is certain the information on them is no longer required. DFSMSrmm can easily automate reuse of tapes if they are still expiration protected, for example, when they are reused as scratch tapes.

Y indicates that DFSMSrmm ensures that all unexpired tape data sets are never overwritten. It fails specific mount requests and requests a remount if the

tape request is non-specific. If an expiration date or retention period was coded in the JCL when the date was originally written to the volume, the tape label is expiration date protected, and DFSMSrmm records this as the original expiration date for the volume. Setting EXPDTCHECK(*Y*) ensures that the original expiration dates specified in the JCL are honored, even if the tape has been released early, or its expiration date or retention period has been changed using the RMM TSO subcommands.

When you specify Y and a tape is expiration protected, reinitialize it before using it again. You can determine what volumes you need to reinitialize by looking at the original expiration date recorded in the DFSMSrmm control data set. To find the date, see the extract data set or use the RMM LISTVOLUME subcommand.

O indicates that DFSMSrmm takes no action but allows the operator or automated software such as NetView to reply as necessary to any write-to-operator messages (IEC507D).

DFSMSrmm ignores the EXPDTCHECK operand and requires an operator reply to the write-to-operator with reply messages when:

- DFSMSrmm is running in record-only mode. DFSMSrmm does not have enough information to base a decision on. Your installation's procedures help the operator to decide how to reply to messages.
- DFSMSrmm is running in warning mode and the volume is rejected for any reason. DFSMSrmm decides that the volume should not be used, but allows its use because in warning mode it does not reject volumes. Your operator or current operating procedures determine whether to reuse the volume and override the expiration protection.

Note: When you use the EDGUX100 to tell DFSMSrmm to ignore a volume, DFSMSrmm does not reply to the IEC507D message because the volume is not DFSMSrmm-managed.

Default: EXPDTCHECK(*O*)

MEDIANAME(*media_name***)**
Specifies a name or type of media for all volumes in this pool. Specify a one to eight character name.

You can specify any name because DFSMSrmm does not check if the device type has been defined to MVS. Here are examples of MEDIANAME that you might define: CART, ROUND, SQUARE, 3420, 3480, TAPE, OPTICAL, CASSETTE. DFSMSrmm accepts media names that have not been generated on the MVS system running DFSMSrmm. Using MEDIANAMEs that describe size or shape give you more flexibility in the media that can reside in a pool. Use MEDIANAME to identify different types of physical shelf space for different media or to distinguish different media characteristics such as Cartridge System Tape and Enhanced Capacity Cartridge System Tape. See "Defining Storage Locations: LOCDEF" on page 115 for information about using media names when defining storage locations.

Default: MEDIANAME(*3480*)

NAME(*pool_name***)**
Specifies a pool name that DFSMSrmm uses to update operator messages and tape drive displays for non-specific tape mount requests. *pool_name* can be a 1

to 8 character name. The first character must be an alphanumeric or national character. Blank, comma, or semicolon cannot be used. Specify a BTLS category name to use DFSMSrmm pooling support for volumes managed by BTLS. *pool_name* can be a tape storage group name defined in your active SMS configuration. NAME is optional and is used on tape drive displays. To use the pool name in messages, you must specify RACK(999) on the MNTMSG command so that the message is updated at the end of the message text.

If you specify a NAME value that is a valid storage group name, DFSMSrmm uses the NAME value as the default storage group name for all the volumes added into this pool range. By naming a specific storage group with the RMM ADDVOLUME subcommand, you can select a pool for a volume at the individual volume level.

You can use the same NAME value on multiple VLPOOL commands enabling you to group multiple prefix ranges into a single logical pool without the need to use the RMM ADDVOLUME subcommand to specify storage group names. You can use RMM ADDVOLUME or RMM CHANGEVOLUME subcommand with the STORAGEGROUP operand to add or remove individual volumes in a logical pool.

Default: None.

PREFIX (*nnnnn****)**

Specifies a generic shelf location that is used in operator messages, RMM TSO subcommands, and the DFSMSrmm ISPF dialog. Specify a one to five character prefix followed by an asterisk. Use a single asterisk to define the default volume pool that contains all volumes not specifically included in another pool.

If a volume's shelf location falls into a number of possible pools, DFSMSrmm chooses the most specific pool. For example, you defined AB* and ABC* as pools. If volume ABC123 is from shelf location ABC123, it belongs in pool ABC*, not AB*. DFSMSrmm prevents duplicate pool prefixes.

DFSMSrmm uses the prefix value to assign a newly defined volume to a scratch pool. For all volumes, DFSMSrmm uses the:

- Storage group value specified with the RMM ADDVOLUME subcommand issued when the volume is defined to DFSMSrmm.
- PARMLIB VLPOOL NAME operand value to assign the storage group when NAME specifies a valid tape storage group.
- Pool prefix to assign a pool when no NAME operand value or storage group value is specified.

Default: PREFIX(*)

RACF(*Y*|*N***)**

Specifies the type of RACF tape support that DFSMSrmm should provide for volumes in the pool you are defining. When you are defining RACF tape support for volumes in a pool, you must look at the RACF tape support you have defined for your installation with the OPTION TPRACF command described in "Defining System Options: OPTION" on page 122.Specify *Y* if you want DFSMSrmm to create RACF tape profiles for the volumes in the pool. Ensure that OPTION TPRACF(*A or P*) is specified. If OPTION TPRACF(*N*) is specified, DFSMSrmm will not create the RACF tape profiles.

Only specify *Y* for tape pools because TAPEVOL profiles are not required for non-tape volumes like optical volumes.

Specify *N* if you do not want DFSMSrmm to create RACF tape profiles for the volumes in the pool. If you specify *N*, DFSMSrmm plays no part in creating or deleting RACF tape profiles, regardless of the system-wide option TPRACF.

Default: RACF(*N*)

SYSID(*system_name***)**
Associates the scratch pool you are defining with a particular system. Specify a value one to eight characters long. DFSMSrmm matches the value with the SYSID operand of the OPTION command.

DFSMSrmm enforces a match on SYSID when validating non-specific tape mounts. Only scratch volumes from a pool associated with a specific system can satisfy non-specific mount requests for that system. DFSMSrmm rejects volumes from other pools on that system.

When you specify a SYSID, and you have also activated MNTMSG, all non-specific mount messages are updated to include the pool prefix to identify the pool to be used to the operator.

You can use the EDGUX100 installation exit to assign multiple scratch pools to be used for non-specific tape volume requests for each system.

If there is no scratch pool defined for the current system, and the EDGUX100 exit does not select a specific scratch pool, DFSMSrmm does not update the mount message. DFSMSrmm selects the first pool in the collating sequence with the correct SYSID to update mount messages. However, the operator can mount a volume from any eligible pool. DFSMSrmm ignores the SYSID value when you use ACS routines to select a storage group pool for a non-specific tape request.

Default: The pool is not associated with any particular system.

TYPE(*S*|*R***)**
Specifies the type of pool. In DFSMSrmm, there are two categories of pools: rack and scratch. Specify *R* for a rack pool, and *S* for a scratch pool.

A *rack pool* is shelf space that can be assigned to hold any volumes that are generally read-only and that enter and leave your installation on an ad hoc basis. These volumes are typically software product volumes and customer volumes and do not adhere to your installation's naming conventions. Although you can add scratch volumes to rack pools, you cannot normally use these volumes to satisfy non-specific mount requests unless EDGUX100 selects a pool or a storage group scratch pool is selected.

A *scratch pool* is shelf space assigned to hold volumes for use with DFSMSrmm system based scratch pooling. The volumes assigned to this shelf space can be used to satisfy scratch requests as long as the volumes are in scratch status. Once the volume has been written to, it becomes a volume with MASTER status until the data is no longer required by the installation. The volume remains in the same DFSMSrmm scratch pool in that it occupies the same shelf space regardless of status.

Default: TYPE(*S*)

Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security

To protect DFSMSrmm functions, you need to use an external security product, such as RACF. Invocations to the product are made by DFSMSrmm through the System Authorization Facility (SAF). If RACF is not installed, you must provide equivalent function via the SAF interface described in “Using the SAF Interface” on page 170.

This chapter explains how you can define RACF profiles to protect DFSMSrmm functions. By defining RACF profiles, you authorize DFSMSrmm users to various levels of access, either CONTROL, READ, ALTER, or UPDATE. These access levels vary depending on the security requirements of your installation.

In addition, “Controlling RACF Tape Profile Processing” on page 164 describes how you can control the actions that DFSMSrmm takes on RACF tape profiles using the DFSMSrmm parmlib OPTION TPRACF command and VLPOOL command and your installation’s RACF options.

This chapter also explains how to ensure security by:

- “Creating Audit Trails” on page 162
- “Using Security Classification Processing” on page 163
- “Preventing the Use of IEHINITT” on page 163

Protecting DFSMSrmm Resources with RACF Profiles

The DFSMSrmm resources you protect with RACF profiles in the FACILITY class each have an entity name prefixed with STGADMIN.EDG. Table 20 lists the DFSMSrmm resources.

For optimal security, define RACF profiles to control access to DFSMSrmm functions protected by the DFSMSrmm resource. If there is a RACF profile, specific or generic, that matches to a DFSMSrmm resource, the resource is treated as if it has been defined. If you do not protect DFSMSrmm resources with RACF or its functional equivalent or you do not have a security product in place, DFSMSrmm provides control for some resources as described in “Setting the Level of Access for the DFSMSrmm Resources” on page 155.

Table 20. Resources You Protect with RACF Profiles

Define the Resource	To Control the
STGADMIN.EDG.FORCE	Changing of information recorded by DFSMSrmm during O/C/EOV processing. Adding or deleting data sets on volumes.
STGADMIN.EDG.HOUSEKEEP	Use of DFSMSrmm inventory management functions.
STGADMIN.EDG.IGNORE.TAPE.volser	Use of duplicate volume serial numbers and ignoring volumes. We do not recommend that you assign an access level to the STGADMIN.EDG.IGNORE.TAPE.volser resource to any specific user group. Instead, wait until a tape volume that must be ignored by DFSMSrmm is identified, to define a resource granting a user or user group the needed access level. Once the volume is no longer needed, delete the resource.

© Copyright IBM Corp. 1992, 2001

Table 20. Resources You Protect with RACF Profiles (continued)

Define the Resource	To Control the
STGADMIN.EDG.LABEL.*volser*	Creation of standard tape labels. The variable *volser* can be specified as a specific volume serial number or a generic volume serial number. For example, A12345 is a specific volume serial number and *AB** is a generic volume serial number. If you use generic profiles you can use these functions in a subset of your volumes. If the volume serial numbers and rack numbers match, you can control relabeling at the pool level. For example you could have a pool using rack number prefix AB*. If you want to create an AL tape and your installation has an SL scratch pool, you need ALTER access to STGADMIN.EDG.LABEL.*volser*. The *volser* can be specified as the pool prefix of the scratch pool. If you want to switch to an AL tape from either an SL or NL tape that has already been assigned to you, UPDATE access to STGADMIN.EDG.LABEL.*volser* is required.
STGADMIN.EDG.LISTCONTROL	Use of the RMM LISTCONTROL subcommand to display DFSMSrmm control data set control record information and EDGRMMxx parmlib settings.
STGADMIN.EDG.MASTER	Access to information in the DFSMSrmm control data set. We recommend that you assign the control data set a universal access of NONE so that DFSMSrmm grants access to various functions through STGADMIN.EDG.MASTER.
STGADMIN.EDG.NOLABEL.*volser*	Creation of tapes without labels.
STGADMIN.EDG.OPERATOR	Use of the initialize and erase functions.
STGADMIN.EDG.OWNER.userid	Access to owned resources. DFSMSrmm checks this entity only if the command issuer is not the owner of the resource or does not have CONTROL access to STGADMIN.EDG.MASTER. Use of the RMM CHANGEVOLUME subcommand to update information based on the owner. Using STGADMIN.EDG.OWNER.userid, individual owners can permit other users to access owned volumes. An owner can be a group or department as well as an individual. Define owner resources only for those owners who will allow their volumes to be managed by another user.
STGADMIN.EDG.RELEASE	Use of the RMM DELETEVOLUME RELEASE subcommand to process any release actions specified for a volume.
STGADMIN.EDG.RESET.SSI	Use of the RESET facility for removing DFSMSrmm from the system. You can use the facility without defining this resource when you have no security product installed.
STGADMIN.EDG.VRS	Use of the RMM LISTVRS and SEARCHVRS subcommands to obtain information about vital record specifications. Use of the RMM ADDVRS and DELETEVRS subcommands to define or remove vital record specifications.
STGADMIN.EDG.INERS.WRONGLABEL	Processing for volumes mounted with the wrong label.

Creating Profiles

To protect an DFSMSrmm resource, you can create a RACF profile as shown in Figure 72 on page 155.

```
RDEFINE FACILITY STGADMIN.EDG.OWNER.HSMATH0 UAC(ALTER)
```

Figure 72. Creating a RACF Profile

For the most complete records, create profiles with auditing options set to record attempted activities. For example, to ensure that RACF logs all successful and failed attempts to change vital record specifications, create profiles as shown in Figure 73.

```
RDEFINE FACILITY STGADMIN.EDG.VRS UACC(NONE)
RALT FACILITY STGADMIN.EDG.VRS GLOBALAUDIT(ALL(UPDATE))
```

Figure 73. Creating a RACF Profile with Audit Options

Setting the Level of Access for the DFSMSrmm Resources

When you define the DFSMSrmm resources, you need to authorize levels of access to these resources. DFSMSrmm checks the resource and the level of access to ensure that users are authorized to request certain tasks. For example, if you attempt to change an owned volume, DFSMSrmm checks to ensure that you have at least UPDATE access to resource STGADMIN.EDG.MASTER.

Table 21 shows the access that is required to perform DFSMSrmm functions.

Table 21. Authorized Functions

When You Define	With Access	Then
STGADMIN.EDG.FORCE	Entity not defined	Information previously recorded by DFSMSrmm cannot be changed.
	UPDATE	Information previously recorded by DFSMSrmm can be changed based on access to STGADMIN.EDG.MASTER.
STGADMIN.EDG.HOUSEKEEP	Entity not defined	Same as READ access
	READ	Any of the inventory management facilities can be invoked.
STGADMIN.EDG.IGNORE.TAPE.volser	Entity not defined	Volumes cannot be ignored using the DFSMSrmm installation exit.
	READ	Volumes that are to be ignored by DFSMSrmm for input requests are allowed to be opened.
	UPDATE	Volumes that are to be ignored by DFSMSrmm for output requests are allowed to be opened.
STGADMIN.EDG.LABEL.volser	Entity not defined	A volume must be in user status to switch from NL or to change to label types at OPEN time.
	UPDATE	Standard labels can be created on a non-scratch volume for an AL or SL output request.
	ALTER	Standard labels can be created on a scratch volume during a nonspecific volume request for AL or SL.

Table 21. Authorized Functions (continued)

When You Define	With Access	Then
STGADMIN.EDG.LISTCONTROL	Entity not defined	Functions are based on STGADMIN.EDG.MASTER access.
	CONTROL	You are allowed to use the RMM LISTCONTROL subcommand.
STGADMIN.EDG.MASTER	Entity not defined	Same as CONTROL access.
	READ	The following functions can be performed: • List all control data set information except vital record specifications and control information • Search for all control data set information except vital record specifications • Update your own owner ID details • Request a scratch volume for yourself • Release an owned volume when the STGADMIN.EDG.RELEASE resource is not protected
	UPDATE	Same as READ access, plus: Some non-restricted fields can be updated for owned volumes and data sets as described in *z/OS DFSMSrmm Guide and Reference*, RMM CHANGEVOLUME subcommand information.
	CONTROL	Same as UPDATE access, plus: You can • Define, change, and delete any control data set entries except vital record specifications • List control information when the STGADMIN.EDG.LISTCONTROL resource is not protected
STGADMIN.EDG.NOLABEL.volser	Entity not defined	A volume must be in user status to switch to NL at OPEN time.
	UPDATE	You are allowed to destroy labels on a non-scratch volume for a no label output request.
	ALTER	You are allowed to destroy labels on a scratch volume during a nonspecific volume request for no labels.
STGADMIN.EDG.OPERATOR	Entity not defined	Same as UPDATE access.
	NONE	No authority is granted to use EDGINERS to initialize and erase volumes.
	READ	No authority is granted to use EDGINERS to initialize and erase volumes.
	UPDATE	EDGINERS can be used to initialize and erase volumes.

Table 21. Authorized Functions (continued)

When You Define	With Access	Then
STGADMIN.EDG.OWNER.userid	Entity not defined	No authority is granted to update volume information except based on STGADMIN.EDG.MASTER access.
	NONE	Based on STGADMIN.EDG.MASTER access.
	UPDATE	Some non-restricted fields for volumes and data sets owned by *userid* can be updated. Also a volume owned by *userid* can be released. See *z/OS DFSMSrmm Guide and Reference*, RMM CHANGEVOLUME subcommand information.
STGADMIN.EDG.RELEASE	Entity not defined	Based on STGADMIN.EDG.MASTER access.
	READ	You are allowed to use the RMM DELETEVOLUME RELEASE subcommand to release an owned volume.
STGADMIN.EDG.RESET.SSI	Entity not defined	You cannot use the EDGRESET utility to remove DFSMSrmm from the system. If you have no security product installed, you can use EDGRESET to remove DFSMSrmm from the system.
	ALTER	You are allowed to withdraw DFSMSrmm from the system during error recovery or problem during implementation.
STGADMIN.EDG.VRS	Entity not defined	Same as CONTROL access.
	READ	You are allowed to list and search for all vital record specifications.
	CONTROL	Same as READ access, plus: You can define and delete vital record specifications.
STGADMIN.EDG.INERS.WRONGLABEL	Entity not defined	Use of the EDGINERS EXEC statement PARM IGNORE and RMMPROMPT parameters is denied.
	CONTROL	You are allowed to use the EDGINERS EXEC statement PARM IGNORE parameter.
	UPDATE	You are allowed to use the EDGINERS EXEC statement PARM RMMPROMPT parameter.

Authorizing Resources

Table 22 on page 158 provides suggestions for authorizing different types of users. Implementing these suggestions depends on your organization's structure, administrative procedures, and security requirements.

Table 22. Suggested Resource Access

Resource	General User	Storage Administrator	System Programmer	Librarian	Inventory Management Functions	Operator
STGADMIN.EDG.FORCE						
	-	U	-	U	-	-
STGADMIN.EDG.HOUSEKEEP						
	-	-	-	-	R	-
STGADMIN.EDG.IGNORE.TAPE.volser						
	-	-	-	-	-	-
STGADMIN.EDG.LABEL.volser						
	U	A	A	A	A	A
STGADMIN.EDG.LISTCONTROL						
	C	C	C	C	-	C
STGADMIN.EDG.MASTER						
	R	C	C	C	-	C
STGADMIN.EDG.NOLABEL.volser						
	U	A	A	A	A	A
STGADMIN.EDG.OPERATOR						
	-	-	U	U	-	U
STGADMIN.EDG.OWNER.userid						
	-	U	-	-	-	-
STGADMIN.EDG.RELEASE						
	R	-	-	-	-	-
STGADMIN.EDG.RESET.SSI						
	-	-	-	-	-	A
STGADMIN.EDG.VRS						
	R	C	C	C	-	-
STGADMIN.EDG.INERS.WRONGLABEL						
	-	-	-	U	-	-

Access: R—Read, U—Update, C—Control, A—Alter

The following sections describe the functions available to DFSMSrmm users based on the recommendations in Table 22.

General User Functions

Table 23 on page 159 describes general user functions.

Table 23. General User Functions

With	The General User Can
UPDATE access to STGADMIN.EDG.LABEL.volser	Create standard labels on a non-scratch volume for an AL or SL output request.
CONTROL access to STGADMIN.EDG.LISTCONTROL	Display control information and installation options and rules.
READ access to STGADMIN.EDG.MASTER	Display all control data set details except vital record specifications and control information. Search for data sets, software products, shelf locations, and volumes. Update their owner ID details. Request a scratch volume.
UPDATE access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a non-scratch volume for a no label output request.
READ access to STGADMIN.EDG.RELEASE	Release volumes they own.
READ access to STGADMIN.EDG.VRS	Search for any vital record specification and display the details that DFSMSrmm records.

Storage Administrator Functions

Table 24 describes storage administrator functions.

Table 24. Storage Administrator Functions

With	The Storage Administrator Can
ALTER access to STGADMIN.EDG.LABEL.volser	Create standard labels on a scratch volume during a non-specific volume request for an AL or SL volume.
CONTROL access to STGADMIN.EDG.LISTCONTROL	Display control information and installation options and rules.
CONTROL access to STGADMIN.EDG.MASTER	Display all control data set details. Request scratch volumes. Release volumes. Update volume, data set, owner, and software product details. Add and delete information about volumes, data sets, shelf locations, owner IDs, and software products.
ALTER access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a scratch volume during a non-specific volume request for a no label volume.
UPDATE access to STGADMIN.EDG.OWNER.userid.	Update details that DFSMSrmm records for volumes that *userid* owns and release volumes that *userid* owns. The storage administrator might use this level of authorization rather than CONTROL access to STGADMIN.EDG.MASTER for administrators responsible for specific production applications.
CONTROL access to STGADMIN.EDG.VRS	Create and delete vital record specifications.

System Programmer Functions

Table 25 describes system programmer functions.

Table 25. System Programmer Functions

With	The System Programmer Can
ALTER access to STGADMIN.EDG.LABEL.volser	Create standard labels on a scratch volume during a non-specific volume request for an AL or SL volume.
CONTROL access to STGADMIN.EDG.LISTCONTROL	Display control information and installation options and rules
CONTROL access to STGADMIN.EDG.MASTER	Display all control data set details. Request scratch volumes. Release volumes. Update volume, data set, owner, and software product details. Add and delete information about volumes, data sets, shelf locations, owner IDs, and software products.
ALTER access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a scratch volume during a non-specific volume request for a no label volume.
UPDATE access to STGADMIN.EDG.OPERATOR	Can initialize and erase volumes.
CONTROL access to STGADMIN.EDG.VRS	Create, display, and delete vital record specifications.

Librarian Functions

Table 26 describes librarian functions.

Table 26. Librarian Functions

With	The Librarian Can
ALTER access to STGADMIN.EDG.LABEL.volser	Create standard labels on a scratch volume during a non-specific volume request for an AL or SL volume.
CONTROL access to STGADMIN.EDG.LISTCONTROL	Display control information and installation options and rules.
CONTROL access to STGADMIN.EDG.MASTER	Display all control data set details. Request scratch volumes. Release volumes. Update volume, data set, owner, and software product details. Add and delete information about volumes, data sets, shelf locations, owner IDs, and software products.
ALTER access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a scratch volume during a non-specific volume request for a no label volume.
UPDATE access to STGADMIN.EDG.OPERATOR	Initialize and erase volumes.
CONTROL access to STGADMIN.EDG.VRS	Search, display, add, and delete vital record specifications.

Inventory Management Functions

Table 27 describes inventory management functions.

Table 27. Inventory Management Functions

With	The Person Performing Inventory Management Can
ALTER access to STGADMIN.EDG.LABEL.volser	Create standard labels on a scratch volume during a non-specific volume request for an AL or SL volume.
READ access to STGADMIN.EDG.HOUSEKEEP	Invoke the DFSMSrmm inventory management facilities to perform the following functions: • Create an extract of the control data set. • Select volumes to be retained and moved as vital records or for disaster recovery. • Perform expiration processing. • Perform storage location management processing. • Back up the control data set.
ALTER access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a scratch volume during a non-specific volume request for a no label volume.

Operator Functions

Table 28 describes operator functions.

Table 28. Operator Functions

With	The Operator Can
ALTER access to STGADMIN.EDG.LABEL.volser	Create standard labels on a scratch volume during a non-specific volume request for an AL or SL volume.
CONTROL access to STGADMIN.EDG.LISTCONTROL	Display control information and installation options and rules
CONTROL access to STGADMIN.EDG.MASTER	Display all control data set details. Request scratch volumes. Release volumes. Update volume, data set, owner, and software product details. Add and delete information about volumes, data sets, shelf locations, owner IDs, and software products.
ALTER access to STGADMIN.EDG.NOLABEL.volser	Erase labels on a scratch volume during a non-specific volume request for a no label volume.
UPDATE access to STGADMIN.EDG.OPERATOR	Initialize and erase volumes.
ALTER access to STGADMIN.EDG.RESET.SSI	Remove DFSMSrmm from the system.

Normally, the operator performs these functions using prepared procedures or batch jobs. In these cases, the user ID performing the procedure requires the relevant access, not the operator's user ID. For example, the EDGRESET function is invoked by starting the DFSMSrmm procedure with OPT=RESET. The user ID that the DFSMSrmm procedure uses needs the access to STGADMIN.EDG.RESET.SSI.

Using the Tape Relabeling Resources

DFSMSrmm supports three basic label types: NL, SL, and AL. You can switch between any of these basic types by specifying the new label type in your JCL when creating the first file on a volume.

You can relabel tape volumes by using EDGINERS, but it requires a separate mount of the volume and must be performed prior to the use of the volume.

Changing volume labels at OPEN time when creating the first file does not require EDGINERS or the INIT release action. DFSMSrmm allows the tape volume label to be created or destroyed at any time regardless of the status of the volume if the user has the required access to a security resource. However, scratch volumes can only be used for nonspecific output requests.

To enable this processing, use the STGADMIN.EDG.LABEL.volser and STGADMIN.EDG.NOLABEL.volser profiles in the FACILITY class. These profiles are described in “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153. If you do not create the appropriate security profiles in FACILITY class, the volume must be in user status.

When DFSMSrmm allows the tape labels to be created or destroyed, it automatically replies to the operator WTOR to provide the required information. In addition, for any volume with the return to scratch release action, which has a label type of NL at release time, DFSMSrmm sets the INIT release action to ensure that only standard label tapes are returned to the scratch pool.

Your installation can bypass this processing for any volume by using the DFSMSrmm EDGUX100 installation exit to request that DFSMSrmm ignore the volume. EDGUX100 is called before any tape label conflicts are resolved. See “Using the DFSMSrmm EDGUX100 Installation Exit” on page 195.

Creating Audit Trails

There are several ways you can create audit information with DFSMSrmm. You can use:

- Control data set information
- SMF audit records
- RACF audit information

See *z/OS DFSMSrmm Reporting* for information on creating reports using DFSMSrmm control data set information and SMF audit records as input.

Control Data Set Information

Control data set information can be used as input to inventory and movement reports you can use to keep track of volumes in your removable media library.

You can also obtain control data set information using RMM TSO subcommands and the DFSMSrmm ISPF dialog. Here is some of the information available:

- User ID, system, date, and time stamp of the last update before the audit record was created.
- Create date, time, user ID, and system.
- Storage location data and bin numbers.

- Original expiration date and the current expiration date. The original expiration date is the expiration date coded in the JCL when the data was originally written to the volume.
- Current location of a volume.
- Release actions for a volume.

See *z/OS DFSMSrmm Guide and Reference* for information on using the RMM TSO subcommands.

SMF Audit Information

Using the DFSMSrmm audit facility, you can record in SMF records all the updates your users make to the control data set. To specify that you want auditing, use the SMFAUD installation parameter in the EDGRMMxx parmlib member. You can collect records through your installation's normal SMF processing and use them as input to the DFSMSrmm program EDGAUD. An SMF audit record can capture any change to the DFSMSrmm inventory.

DFSMSrmm provides several mapping macros for DFSMSrmm SMF audit and security records. See *z/OS DFSMSrmm Reporting* for the layout of these macros. See "Updating SMFPRMxx (Optional)" on page 27 for information on how identify records to be collected. See "Defining Security Classes: SECCLS" on page 145 for information on defining which SMF record numbers to use.

RACF Audit Information

Using standard RACF facilities, you can keep an audit trail of any command and authorization violations that occur in RMM TSO subcommands or utilities. Use RACF AUDIT and GLOBALAUDIT options to get RACF to create this information.

Using Security Classification Processing

Certain classifications of data might require special processing, or operator action, or both. You can control these actions by using DFSMSrmm security classifications, defined with the SECCLS command in the EDGRMMxx parmlib member. Use this command to specify that DFSMSrmm:

- Issues messages when certain data sets are opened so the operator can take any required installation action before confirming the use of the volume
- Creates a special SMF record for each access to secure volumes
- Automatically flags these volumes to be erased when they are released, before they can be reused

Preventing the Use of IEHINITT

You no longer need to use IEHINITT because the DFSMSrmm utility EDGINERS labels tapes and validates mounted volumes. Use EDGINERS to process new volumes, volumes where old and new labels are known to DFSMSrmm, or old volumes that have been degaussed. EDGINERS defines volumes to the DFSMSrmm control data set that have not been defined previously. For existing volumes, EDGINERS updates the volume record to show that volumes have been initialized. See "Chapter 17. Initializing and Erasing Volumes" on page 311 for information about using EDGINERS.

To protect IEHINITT from being used or to limit usage to specific individuals, add RACF program resource profiles and create limited access lists as shown in Figure 74:

```
RDEFINE PROGRAM IEHINITT UACC(NONE)
PE IEHINITT CLASS(PROGRAM) RESET(STANDARD)
```

Figure 74. Limiting the Use of IEHINITT

If program control is not active, use the RACF command SETROPTS WHEN(PROGRAM) to activate it. If program control is already active, specify the RACF command SETROPTS WHEN(PROGRAM) REFRESH to activate use of the new profile.

Controlling RACF Tape Profile Processing

You can control the actions that DFSMSrmm takes on RACF tape profiles through the DFSMSrmm OPTION TPRACF command and your installation's RACF options. For more information on OPTION TPRACF, see "Defining System Options: OPTION" on page 122.

If you are running DFSMSrmm with DFSMShsm, see "Securing Tapes When Running DFSMShsm and DFSMSrmm" on page 241. See *z/OS SecureWay Security Server RACF System Programmer's Guide* for information about RACF tape security.

RACF provides the following tape protection options:
- No protection
- TAPEVOL class
- TAPEDSN option
- TAPEVOL and TAPEDSN

The actions DFSMSrmm takes to protect volumes are:

No protection
If neither TAPEVOL nor TAPEDSN is active then DFSMSrmm takes no action, regardless of the setting of the TPRACF option.

TAPEVOL
TPRACF(N)—no action.

TPRACF(P)—a TAPEVOL profile is created or deleted only as a result of issuing a DFSMSrmm ADD, CHANGE, or DELETE subcommand for a private volume from a RACF-protected pool. This includes scratch tapes assigned by the user or librarian using the RMM GETVOLUME subcommand.

If you require tape volume protection for volumes used for nonspecific tape requests, you can either:

1. Specify the JCL PROTECT=YES option, and DFSMSdfp processing protects the volume.

   Or

2. Leave DFSMSrmm to protect the volume when a data set on the volume is closed, by creating a TAPEVOL profile.

DFSMSrmm automatically deletes any TAPEVOL profile for recycled scratch tapes when they return to scratch. If you use nonspecific mounts and scratch pools, no TAPEVOL profile exists while the volume is in scratch status.

TPRACF(A)—The same as TPRACF(P).

TAPEDSN

TPRACF(N)—no action.

TPRACF(P) and TPRACF(A)—The processing is the same for both options. DFSMSrmm does not cause any RACF profiles to be created at any time. During recycling or releasing of tapes, DFSMSrmm checks for discrete RACF data set profiles for data sets known to be on the volume, and automatically deletes them.

TAPEVOL and TAPEDSN

TPRACF(N)—no action.

TPRACF(A)—TAPEVOL profiles are created for identified, RACF- controlled, pools of non-scratch tapes when you use the RMM ADD, CHANGE and DELETE subcommands. No TVTOC is created in these circumstances.

DFSMSrmm assumes that correct DFSMSdfp and RACF processing when a data set on a volume is opened can result in both TAPEVOL and discrete DATASET profiles being created. DFSMSrmm automatically deletes any such profiles for recycled scratch tapes when they return to scratch.

If a volume is unprotected when a data set on the volume is closed, DFSMSrmm automatically protects the volume with a TAPEVOL profile. If it is the first file of an IBM standard label tape being processed, DFSMSrmm creates a TVTOC containing an entry for the first file. This enables the installation to use RACF generic data set profiles to control access to the tape data sets, even when the JCL does not include the PROTECT=YES option.

TPRACF(P)—This processing is the same as TPRACF(A) except that all scratch tapes, whether defined by RMM TSO subcommand or returned to scratch by expiration processing, are protected by predefined RACF TAPEVOL profiles. The TAPEVOL profile includes an empty TVTOC so that RACF considers the volume to be scratch.

Table 29 shows DFSMSrmm processing when RACF is active and OPTION TPRACF is set for volume pools identified as DFSMSrmm and RACF-managed. The processing is dependent on the combinations of RACF TAPEVOL class and TAPEDSN option, and the TPRACF value. The DFSMSrmm EDGRMMxx parmlib VLPOOL RACF(Y) is in effect.

Table 29. RACF Processing Performed by DFSMSrmm

Command or Function	TAPEVOL	TAPEDSN	TAPEVOL and TAPEDSN
ADDVOLUME MASTER	• Create TAPEVOL profile • Add access list built using the owner, user, and access information	No processing	As for TAPEVOL
ADDVOLUME USER	• Create TAPEVOL profile • Add access list built using the owner, user, and access information	No processing	As for TAPEVOL

Table 29. RACF Processing Performed by DFSMSrmm (continued)

Command or Function	TAPEVOL	TAPEDSN	TAPEVOL and TAPEDSN
ADDVOLUME MASTER PREVVOL	Add to tape volume set	No processing	As for TAPEVOL
ADDVOLUME USER PREVVOL	Add to tape volume set	No processing	As for TAPEVOL
ADDVOLUME SCRATCH	No processing	No processing	If TPRACF(P) • Create TAPEVOL profile • Add a TVTOC if SL or AL.
DELETEVOLUME FORCE / REMOVE	Delete TAPEVOL profile	If data set records, delete tape data set profiles	• Delete TAPEVOL profile • If data set records, delete tape data set profiles
DELETEVOLUME RELEASE	No processing	No processing	No processing
CHANGEVOLUME RACK Change of pool—RACF(Y) to RACF(N)	Delete TAPEVOL profile	If data set records, delete tape data set profiles	• Delete TAPEVOL profile • If data set records, delete tape data set profiles
CHANGEVOLUME RACK Change of pool—RACF(N) to RACF(Y)	• Create TAPEVOL profile • Add access list built using the owner, user, and access information	No processing	As for TAPEVOL
CHANGEVOLUME OWNER OWNERACC PROT USERS	Replace access list	No processing	As for TAPEVOL
CHANGEVOLUME USER / MASTER (not from SCRATCH)	No processing	No processing	No processing
CHANGEVOLUME USER / MASTER (from SCRATCH) GETVOLUME	• Delete TAPEVOL profile • Create TAPEVOL profile • Add access list	If data set records, delete tape data set profiles	As for TAPEVOL
CHANGEVOLUME PREVVOL	• Delete TAPEVOL profile • Add volume to tape volume set	No processing	As for TAPEVOL
SCRATCH mount processing	At close end-of-volume create a TAPEVOL profile if one does not exist and add OWNER as accessor	No processing	At close/end-of-volume create a TAPEVOL profile if one does not exist and create a TVTOC containing first file data set and add OWNER as accessor
MASTER / USER mount processing	No processing	No processing	No processing
Release processing When volume returns to scratch	Delete TAPEVOL profile	If data set records, delete tape data set profiles	• Delete TAPEVOL profile For TPRACF(P) • Create TAPEVOL profile • Add a TVTOC if SL or AL.
DELETEDATASET	No processing	Delete tape data set profile	As for TAPEDSN

Table 29. RACF Processing Performed by DFSMSrmm (continued)

Command or Function	TAPEVOL	TAPEDSN	TAPEVOL and TAPEDSN
DELETEOWNER NEWOWNER	As for CHANGEVOLUME OWNER	As for CHANGEVOLUME OWNER	As for CHANGEVOLUME OWNER

Recommendations for Using RACF Tape Profile Processing

For optimal security, we recommend you have TAPEVOL and TAPEDSN active with either TPRACF(P) or TPRACF(A). These solutions provides the following advantages:

- Full protection at volume and data set level
- No need to predefine volumes to individual users
- No need to use ADSP or PROTECT=YES, meaning elimination of exit code that is not standard
- Ability to use generic tape data set profiles

Although we discourage this, it is possible to have no tape protection, or to use only TAPEVOL profiles. If you have no tape security, you cannot control the creation and use of data on tape. If you use only TAPEVOL profiles to protect tape volumes, you must maintain the access lists in the TAPEVOL profiles to allow access to data. Consider the use of TAPEDSN so that access to tape data is covered by your normal, existing, generic data set profiles.

There is a potential security exposure with scratch volumes that have no RACF profile, but with DFSMSrmm active in protect mode, you can prevent reading of scratch tapes.

You can use TAPEDSN on its own to provide data set level security. RACF cannot,however, guarantee full data set name integrity (only the last 17 characters of the data set name are recorded in the tape label). Run DFSMSrmm in protect mode to ensure that it validates full 44 character data set names. With TAPEDSN only, you lack control of access to tape volumes at the volume level. If you do not use protect mode, your system security could be circumvented and tape data could be accessed.

Rejecting Volumes on Specific Systems in a System Complex

In a system complex where all systems share the RACF data set, the RACF profile provides the same protection for all systems. If you want to prevent a volume from being used on one system, you must prevent its use on all systems. However, you can prevent volume usage on individual systems by using the DFSMSrmm REJECT command in the EDGRMMxx parmlib member. You can reject volumes that are defined to DFSMSrmm based on your chosen pool prefix using the REJECT command in parmlib.

To protect several volumes across all systems in the complex, you can use generic RACF profiles. For example, to create a profile that would prevent any tape starting with a volume serial number prefix AB from being used on all systems in a system complex, create a tape profile as shown in Figure 75:

```
RDEFINE TAPEVOL AB* UACC(NONE)
```

Figure 75. Creating a Tape Profile

To prevent a pool of volumes from being used on one system in a multisystem complex, do not define generic RACF TAPEVOL profiles. Use the DFSMSrmm REJECT parmlib option as shown in Figure 76.

```
REJECT ANYUSE(AB*)
```

Figure 76. Using the REJECT Parmlib Option

Select the correct volume protection for your environment using a combination of generic TAPEVOL profiles that you create, the discrete TAPEVOL profiles that DFSMSrmm creates, and the DFSMSrmm REJECT commands that you define.

Maintaining the User Access List

For DFSMSrmm to maintain the access list, use the RMM TSO subcommands to change access lists, rather than RACF. You can use RACF commands to add users and owners if the times when DFSMSrmm updates, deletes, or creates the TAPEVOL profiles are well defined, and during the time a volume is not scratch the RACF profile is updated only if the DFSMSrmm volume access list is updated.

If you set a DFSMSrmm option for TPRACF, other than N, DFSMSrmm ensures that your tapes are protected by RACF. DFSMSrmm ensures that all non-scratch tapes are protected by a discrete RACF TAPEVOL profile. DFSMSrmm checks that a RACF profile exists whenever a data set is written on a tape. If a profile does not exist, DFSMSrmm creates one. Therefore you do not need to use RACF installation exits to set the JCL PROTECT=YES option or specify PROTECT=YES in your JCL. Additionally, because DFSMSrmm creates a TVTOC when the RACF TAPEDSN option is used, you can use generic data set profiles for all tape data sets without changes to JCL or installation procedures.

Be careful about using RACF profiles to maintain a list of users who own and can access volumes. When you use the RMM ADDVOLUME and CHANGEVOLUME subcommands, you can maintain up to 12 users and owners for each volume. If the volume is in a RACF-controlled pool and RACF TAPEVOL class is active, the TAPEVOL profile access list is maintained with the list of users who can access the volume and the owner's user ID. If you change the RACF TAPEVOL profile access list using RACF commands, the DFSMSrmm control data set does not reflect the changes. The next time that DFSMSrmm updates the RACF TAPEVOL profile, it creates the access list from the volume information, but does not include any users or owners you added using RACF commands.

RACF Considerations When Implementing DFSMSrmm

Despite the varied tape security support that RACF provides, many installations use RACF exits to control access to tape volumes and to tape data sets. Although there are likely to be many different implementations, these are some of the commonly implemented functions:

- Use of the RACHECK/RACDEF exits to test or set the PROTECT=YES option
- Use of the ability to model a TAPEVOL profile on another existing profile; either a model or data set profile
- Use of RACHECK post-processing exit to prevent use of tapes that are not protected by RACF (PROTECTALL for tape)

DFSMSrmm RACF Tape Security Support

The objective for DFSMSrmm RACF tape security support is to provide a complete interface with RACF for tapes so you can use any combination of valid RACF options, including use of any RACF installation exits you still have. You can tell DFSMSrmm not to provide any RACF support by specifying the DFSMSrmm EDGRMMxx parmlib OPTION TPRACF(N) command. You can set up the type of processing wanted by requesting automatic TPRACF(A) or predefined TPRACF(P) RACF profiles.You can also use the DFSMSrmm EDGRMMxx parmlib VLPOOL RACF command to provide control of RACF at the pool level.

DFSMSrmm Automatic Tape Security Support Processing

DFSMSrmm automatic tape security processing assumes that when a tape is mounted for output as a scratch tape it will not be RACF protected, but during the open processing for the tape data set that either DFSMSdfp or your installation exits will cause some RACF profiles to be created. DFSMSrmm predefined processing also ensures that, when TAPEVOL and TAPEDSN are active, RACF predefined TAPEVOL profiles with an empty TVTOC are created for scratch volumes. To enforce a DFSMSrmm standard, that all tapes are RACF protected when the data set is closed, DFSMSrmm checks that a RACF security profile exists for the volume. If a RACF security profile does not exist, DFSMSrmm creates one and places the owner of the tape in the access list for the TAPEVOL profile with ALTER authority. The process ensures that your current tape security mechanism should continue to work as long as it is based on TAPEVOL profiles.

Data Set Profile Processing Implications

If you only use data set profiles for tape data sets, you need to consider the implications which are described in this section.

The objective should be to get to standard RACF tape security without using installation exits. However, the introduction of the TAPEDSN option or use of TAPEDSN only can cause some complications. When TAPEDSN is in effect and a TAPEVOL profile with no TVTOC exists, any attempt to access the data set by a user other than the owner fails even if the user has access to a data set profile that would appear to give appropriate access. This happens because RACF does not use the data set profiles unless the TAPEVOL profile contains a TVTOC. To help with this situation, when no security profile has been created by DFSMSdfp or RACF installation exits, DFSMSrmm creates a TAPEVOL profile with a TVTOC, a UACC(NONE) and the volume owner in the access list. The first file is added to the TVTOC using RACFIND=NO so that any generic data set profiles your installation has can be used with tape data sets. Once the first file entry is created RACF will maintain the TVTOC for any future tape activity on the same volume.

Converting From RACF Installation Exits

Some installations use only data set profiles to protect tape data. They rely on the tape management system to ensure that only valid scratch tapes are used for output. If they use TAPEVOL class without TAPEDSN option in effect, they have RACF exits that change the RACHECK for TAPEVOL class to a RACHECK for the data set being processed. Consequently, they prevent RACDEF in the TAPEVOL class. If your RACDEF exit is used to dummy out the DFSMSdfp RACDEFs that would normally create TAPEVOL profiles, they will also prevent DFSMSrmm from defining TAPEVOL profiles. If this applies to your installation you will have to make changes to your RACF exits before making use of the DFSMSrmm RACF support.

This section contains examples for converting RACF installation exits.

TAPEVOL class active. PROTECT=YES JCL option used

Currently the installation uses RACF exits to model the creation of the RACF TAPEVOL profile on an existing RACF data set profile. Access to tape data is effectively based on data set profiles.

When the DFSMSrmm TPRACF option is activated, any volumes that are not covered by the PROTECT=YES option and the TAPEVOL profiles created using the data set modeling are protected by a TAPEVOL profile created by DFSMSrmm. Access to these data sets is based on the TAPEVOL profile which allows owner access only.

If the RACF exits modeling function is turned off, the volumes that were previously protected by a modeled profile are now only protected as described above for the DFSMSrmm created profiles. Most probably, users lose access to tape data.

The suggested approach is to activate the TAPEDSN RACF option. For those volumes where PROTECT=YES is specified, the TAPEVOL profiles have TVTOCs created and data access is via data set profiles which currently exist. The creation of the TAPEVOL profiles by DFSMSrmm is also affected, and DFSMSrmm ensures that a TVTOC is created. The protection for tape volumes protected by DFSMSrmm created profiles is also via data set profiles.

TAPEVOL class active. Exit requested PROTECT=YES option used

If your RACF installation exits are used to 'turn on' the PROTECT=YES option, and those exits are removed, no DFSMSdfp requests are made to RACF to protect tape data, even if TAPEDSN is activated. All volumes get protected at data set CLOSE time when DFSMSrmm creates TAPEVOL profiles.

Whether or not you choose to use the RACF TAPEDSN option, the results in creating a security environment for your installation are the same before and after you remove your installation exits.

TAPEVOL active. RACF exits using DATASET not TAPEVOL profiles

Conversion to standard options to remove the exits involves deactivating the TAPEVOL class and activating the TAPEDSN option. Using the PROTECTALL option also ensures complete security for tape data. Once the TAPEVOL class is inactive, DFSMSrmm no longer attempts to create TAPEVOL profiles for volumes, but cleans up any discrete data set profiles that might exist when a tape returns to scratch status. You can rely on DFSMSrmm to validate volumes that are mounted and prevent overwrites, validate 44 character data set names and manage data set and volume expiration.

Using the SAF Interface

DFSMSrmm does not provide any security functions itself but relies on installed security products to process requests. For example, DFSMSrmm relies on the installed security product to confirm that a user is authorized to perform a particular function using an RMM TSO subcommand.

DFSMSrmm uses the MVS SAF interface to perform authorization checks and other security processing. DFSMSrmm issues RACROUTE requests that RACF, or a functionally equivalent security product can process.

"Protecting DFSMSrmm Resources with RACF Profiles" on page 153 describes security profile names and class name. If you have not installed a security product, you could write a SAF router exit to handle the calls that DFSMSrmm makes to the interface.

DFSMSrmm also uses the SAF interface to create, update, and delete tape related security profiles and access lists. However, if you update the volume access list in the control data set, DFSMSrmm uses the RACF ICHEINTY macro to delete the entire access list and the SAF interface to add the required access list. If your system does not support this function, do not use or update the DFSMSrmm volume access lists contained in the control data set.

SAF Calls for Authorization Checking

DFSMSrmm issues RACROUTE calls to determine if a user is authorized to perform a DFSMSrmm function. The calls are issued in the address space and under the task of the command or utility user. Most SAF calls in the FACILITY class are issued regardless of the state of RACF, the SAF interface, or the FACILITY class.

DFSMSrmm prevents RACF users with the OPERATIONS and PRIVILEGED attributes from gaining authorization to the DFSMSrmm resources in the FACILITY class. Any user attempting to use DFSMSrmm functions must be authorized through the resource access list or through universal access. For all authorization checks, except for EDGRESET, DFSMSrmm issues the RACROUTE request with an ACEE address that identifies an ACEE that has had these attributes removed.

Figure 77 shows the RACROUTE call that DFSMSrmm issues to create an ACEE for a user that is defined to RACF. DFSMSrmm issues this call in the address space of the command issuer or batch utility.

```
RACROUTE REQUEST=VERIFY,ENVIR=CREATE,RELEASE=1.9,
      USERID=ACEEUSER,GROUP=ACEEGRP,PASSCHK=NO,SUBPOOL=(3)
```

Figure 77. Creating an ACEE for a User Defined to RACF

Figure 78 shows the RACROUTE call that DFSMSrmm issues to create an ACEE for a user that is not defined to RACF. DFSMSrmm issues the call using a blank USERID value. DFSMSrmm issues this call in the address space of the command issuer or batch utility.

```
RACROUTE REQUEST=VERIFY,ENVIR=CREATE,RELEASE=1.9,
      USERID=ACEEUSER,PASSCHK=NO,SUBPOOL=(3)
```

Figure 78. Creating an ACEE for a User Not Defined to RACF

Checking Authorization

Figure 79 shows authorization checking for issuers of RMM TSO subcommands and users of the utilities when a single RACROUTE is issued. The request is issued in the address space of the command issuer or batch utility.

```
RACROUTE REQUEST=AUTH,CLASS=class,ATTR=level,ENTITY=resource,
         LOG=ASIS
```

Figure 79. Checking Authorization When a Single RACROUTE Is Issued

Figure 80 shows authorization checking for issuers of RMM TSO subcommands and users of the utilities when multiple RACROUTEs are issued. The request is issued in the address space of the command issuer or batch utility.

```
RACROUTE REQUEST=AUTH,CLASS=class,ATTR=level,ENTITY=resource,
         LOG=NOFAIL
```

Figure 80. Checking Authorization When Multiple RACROUTEs are Issued

where:

class **- FACILITY**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

level **- READ, UPDATE, CONTROL**
access level as described in Table 21 on page 155.

resource
This field is 39 characters and contains the name of the resource to which access is being checked.

Checking Authorization to Ignore Volumes

Figure 81 is used to check that the current user is authorized to have DFSMSrmm ignore a volume.

```
RACROUTE REQUEST=AUTH,ENTITY=STGADMIN.EDG.IGNORE.TAPE.volser,
         ACCESS=value,LOG=ASIS
```

Figure 81. Checking Authorization to Ignore Volumes

where:

value **- READ,UPDATE**
One of these values is used, as described in Table 21 on page 155.

volser
This field is the volume serial number of the current mounted volume.

Checking Authorization to Create Label and No Label Volumes

Figure 82 is the RACROUTE call for the STGADMIN.EDG.LABEL.*volser* and STGADMIN.EDG.NOLABEL.*volser* profiles.

```
RACROUTE REQUEST=AUTH,ENTITY=STGADMIN.EDG.label.volser,
         ACCESS=value,LOG=ASIS
```

Figure 82. Checking Authorization to Create Labels and No Label Volumes

where:

label
The label is either LABEL or NOLABEL.

value **- UPDATE,ALTER**
One of these values is used, as described in Table 21 on page 155.

volser
This field is the volume serial number of the current mounted volume.

Removing DFSMSrmm from the System

When you do not have a security product installed, you can use the EDGRESET utility to remove DFSMSrmm from the system. To use the EDGRESET utility, you must use the SAF router exit.

Figure 83 is used to check that EDGRESET utility can be used. This request is issued in the address space of the EDGRESET utility.

```
RACROUTE REQUEST=AUTH,CLASS=class,ATTR=ATTR,ENTITY=resource,
         RELEASE=1.8
```

Figure 83. Checking for EDGRESET Usage

where:

class **- FACILITY**
: This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource **- STGADMIN.EDG.RESET.SSI**
: This field is 39 characters and contains the name of the resource to which access is being checked.

SAF and RACF Calls For Creating, Updating and Deleting Security Profiles

These are the SAF calls that DFSMSrmm issues to maintain the security protection of tape resources in your installation. They are not used to perform authorization checking. Authorization checking for access to tape data and tape volumes is still the responsibility of the OPEN macro and RACF. All these requests are issued from the DFSMSrmm started procedure address space.

When the requests are issued the RACF ACEE control block for the DFSMSrmm started procedure has the privileged bit on (ACEEPRIV), so that the requests made by DFSMSrmm are honored without authorization checking being performed.

Calls for TAPEVOL class are only issued if RACF is active and the TAPEVOL class is active. Calls for DATASET class are only issued if RACF is active and the TAPEDSN option is active.

For additional information on the following SAF calls, refer to Table 29 on page 165.

Checking for DATASET Class Resource

Figure 84 is used to check for the existence of discrete DATASET class resource.

```
RACROUTE REQUEST=AUTH,CLASS=class,ENTITY=(resource,PRIVATE),LOG=NONE,
         RELEASE=1.8,DSTYPE=T,FILESEQ=seq,VOLSER=vol
```

Figure 84. Checking for DATASET Class Resource

where:

class **- DATASET**
: This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 44 characters and contains the name of the data set for which the protecting resource is requested to be returned.

seq
The file sequence number for this data set.

vol
The volume on which the data set resides.

Checking for TAPEVOL Class Resource

Figure 85 is used to check for the existence of discrete TAPEVOL class resource.

```
RACROUTE REQUEST=AUTH,CLASS=class,ENTITY=(resource,PRIVATE),LOG=NONE,
         RELEASE=1.8
```

Figure 85. Checking for TAPEVOL Class Resource

where:

class **- TAPEVOL**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 6 characters and contains the name of the volume for which the protecting resource is requested to be returned.

Defining a TAPEVOL Class

Figure 86 is used to define a discrete TAPEVOL class resource.

```
RACROUTE REQUEST=DEFINE,CLASS=class,ENTITY=resource,TYPE=DEFINE,
         RELEASE=1.8,UACC=NONE
```

Figure 86. Defining a TAPEVOL Class

where:

class **- TAPEVOL**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 6 characters and contains the name of the volume for which the resource is being defined.

Defining TAPEVOL When TAPEDSN Is Active

If TAPEDSN option is active the request shown in Figure 87 is used to add the first entry to the TVTOC of the discrete TAPEVOL profile just created.

```
RACROUTE REQUEST=DEFINE,CLASS=class,ENTITY=resource,TYPE=DEFINE,
         RELEASE=1.8,UACC=NONE,RACFIND=NO,VOLSER=vol,
         DSTYPE=T,FILESEQ=1,TAPELBL=STD
```

Figure 87. Defining TAPEVOL When TAPEDSN is Active

where:

class **- DATASET**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 44 characters and contains the name of the data set for which the resource is being defined.

vol
The volume on which the data set resides.

Adding a Tape Volume

Figure 88 is used to add a tape volume to an existing tape volume set.

```
RACROUTE REQUEST=DEFINE,CLASS=class,ENTITY=resource,TYPE=ADDVOL,
         RELEASE=1.8,VOLSER=vol
```

Figure 88. Adding a Tape Volume

where:

class **- TAPEVOL**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 6 characters and contains the name of the volume for which the resource is being defined.

vol
The previous volume in the tape volume set.

Deleting a TAPEVOL Profile

Figure 89 is used to delete a discrete TAPEVOL profile.

```
RACROUTE REQUEST=DEFINE,CLASS=class,ENTITY=resource,TYPE=DELETE,
         RELEASE=1.8
```

Figure 89. Deleting a TAPEVOL Profile

where:

class **- TAPEVOL**
This field names a 9 character variable The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 6 characters and contains the name of the volume for which the resource is being deleted.

Deleting a DATASET Profile

Figure 90 is used to delete a discrete DATASET profile.

```
RACROUTE REQUEST=DEFINE,CLASS=class,ENTITY=resource,TYPE=DELETE,
         RELEASE=1.8,VOLSER=vol
```

Figure 90. Deleting a DATASET Profile

where:

class **- DATASET**
This field names a 9 character variable. The first byte contains the length of the class name, which follows in the next 8 bytes.

resource
This field is 44 characters and contains the name of the data set for which the resource is being deleted.

vol
The volume on which the data set resided.

Checking Authorization

Figure 91 is used to:

- Create or update the volume access list
- Give the volume a TVTOC
- Rebuild a tape volume set when a volume is removed from within, rather than from the end of the set, when a TVTOC is used

```
RACROUTE REQUEST=EXTRACT,CLASS=class,ENTITY=resource,TYPE=EXTRACT,
         RELEASE=1.8,SUBPOOL=0,SEGMENT=BASE,FIELDS=fields
ICHEINTY ALTER,TYPE='GEN',CLASS=class,ACTIONS=D,ENTRY=resource,
         RELEASE=1.8,OPTIONS=FLDEF
ICHEACTN FIELD=ACLCNT,FLDATA='DEL',GROUP=YES,
         RELEASE=1.8
RACROUTE REQUEST=EXTRACT,CLASS=class,ENTITY=resource,TYPE=REPLACE,
         RELEASE=1.8,SEGDATA=data,SEGMENT=BASE,FIELDS=fields
```

Figure 91. Checking Authorization

where:

class **- TAPEVOL**
This field is 8 characters and contains the class name.

resource
This field is 6 characters and contains the name of the volume whose profile is being processed.

fields
Defines which fields are being extracted and updated. The field names used include: TVTOCCNT,VOLCNT,ACLCNT,VOLSER,OWNER,UACC,ACL.

data
Defines which fields are being replaced. The field names used include: OWNER,UACC,ACL.

Chapter 9. Using DFSMSrmm Programming Interfaces

DFSMSrmm provides programming interfaces EDGLCSUX, EDGMSGEX, and EDG3X71 to use Object Access Method (OAM), DFSMSdfp and JES3 installation exits. DFSMSrmm uses the installation exits in Table 30. Before implementing DFSMSrmm, ensure that there are no conflicts between how DFSMSrmm uses these exits and how your installation currently uses them.

DFSMSrmm provides programming interface EDGTVEXT for use from DFSMShsm or Tivoli Storage Manager. DFSMSrmm provides programming interfaces EDGTVEXT and EDGDFHSM for use by applications that want to release tape volumes.

Table 30. Installation Exits Used by DFSMSrmm

Exit	DFSMSrmm Programming interface	DFSMSrmm's Use of the Exit
CBRUXCUA	EDGLCSUX	DFSMSrmm uses OAM's change use attribute exit to manage the volumes in system-managed tape libraries.
CBRUXEJC	EDGLCSUX	DFSMSrmm uses OAM's cartridge eject exit to manage the volumes in system-managed tape libraries.
CBRUXENT	EDGLCSUX	DFSMSrmm uses OAM's cartridge entry exit to manage the volumes in system-managed tape libraries.
CBRUXVNL	EDGLCSUX	DFSMSrmm uses OAM's volume-not-in-library installation exit to process tape volumes that are not resident in system-managed tape libraries but that are needed for processing to continue.
IGXMSGEX	EDGMSGEX	DFSMSrmm uses the DFSMSdfp MSGDISP exit to update tape drive displays and control the use of cartridge loaders.
IATUX71	EDG3X71	DFSMSrmm uses the JES3 exit to determine the processing needed for JES3 messages and tape drive display processing.

Releasing Tapes: EDGTVEXT

DFSMSrmm provides the programming interface EDGTVEXT that is used from DFSMShsm or any other APF authorized program that needs to obtain the same services as the DFSMShsm ARCTVEXT exit.

If you have a product with similar requirements for releasing tapes as DFSMShsm, you can use the EDGTVEXT program interface. You can also use the EDGDFHSM interface. The difference between EDGTVEXT and EDGDFHSM is that EDGTVEXT accepts the ARCTVEXT parameter list and the EDGDFHSM interface accepts only a single volume at a time in the parameter list.

To run DFSMShsm with DFSMSrmm, DFSMShsm must be defined to RACF. The DFSMShsm user ID should be defined in the started procedures table ICHRIN03 or with the 21st century STARTED class. See *z/OS DFSMShsm Implementation and Customization Guide*.

DFSMShsm issues the ARC0516I error message if DFSMShsm cannot successfully load the EDGTVEXT exit or if an ABEND occurs. The error message will not scroll off the screen until the operator responds to the message. The EDGTVEXT exit

© Copyright IBM Corp. 1992, 2001

gets disabled if an ABEND occurs so that you can correct the problem. The RELEASE RMM command should be issued to reactivate the DFSMShsm invocation of EDGTVEXT.

You can use DFSMSrmm parmlib option TVEXTPURGE to control the processing that EDGTVEXT performs. You can either release volumes or set the volume expiration date to the current date. Refer to TVEXTPURGE in “Defining System Options: OPTION” on page 122.

Invocation

Invoke EDGTVEXT from: LOAD and CALL macros or the LINK macro.

Input

The input is a parameter list that describes the volumes DFSMShsm is releasing and the actions required. The parameter list is identical to the one DFSMShsm passes to ARCTVEXT.

On entry, register 1 contains a pointer to the ARCTVEXT parameter list. See *z/OS DFSMS Installation Exits* for information on ARCTVEXT.

Output

EDGTVEXT issues messages when errors are encountered. EDGTVEXT sets the parameter list return code value to zero. EDGTVEXT does not always pass a zero return code in register 15 back to the caller. EDGTVEXT issues a non-zero return code in the register 15 return code from subsystem requests attempted by EDGTVEXT. You can obtain information about the return codes in *z/OS MVS Using the Subsystem Interface*.

Processing

EDGTVEXT ensures that DFSMSrmm is in use on your system before continuing with DFSMSrmm processing. If DFSMSrmm is not in use, EDGTVEXT sets return code zero and returns to the caller. If DFSMSrmm is in use or should be in use, EDGTVEXT calls EDGDFHSM to process the volumes passed to it in the ARCTVEXT parameter list.

Environment

EDGTVEXT must be link edited in an APF-authorized library. EDGTVEXT runs in AMODE(31) RMODE(ANY).

Managing DFSMShsm Tapes: EDGDFHSM

The EDGDFHSM programming interface is used by DFSMSrmm to release DFSMShsm tape volumes. The interface between DFSMShsm and DFSMSrmm is automatically in place when you install DFSMS/MVS so you do not need to take any action to activate it or to call it.

You can use this program interface from programs other that DFSMShsm that need to free up tape volumes.

You can use DFSMSrmm parmlib OPTION TVEXTPURGE operand to control the processing that EDGDFHSM performs. You can either release volumes or set the volume expiration date to the current date. Refer to TVEXTPURGE described in “Defining System Options: OPTION” on page 122.

Callers of EDGDFHSM can only request the processing of volumes when their RACF user ID is authorized as defined by the RACF FACILITY class profiles for DFSMSrmm.

Invocation

Invoke EDGDFHSM from: LOAD and CALL macros or the LINK macro.

Input

The input is a parameter list that describes the volume DFSMShsm is releasing and the actions required. The parameter list is similar to the one DFSMShsm passes to ARCTVEXT, except that DFSMSrmm's parameter list handles only a single volume at a time.

On entry, register 1 contains a pointer to an 8-byte field. The first 6 bytes are the volume serial number to be processed and the last 2 bytes are flag bytes. The contents of the flag bytes are the flag bytes DFSMShsm passes to the ARCTVEXT exit. See *z/OS DFSMS Installation Exits* for information on ARCTVEXT.

On entry, register 13 contains the address of a standard 18 word save area and register 14 contains the return address.

Output

A non-zero return code is the register 15 return code from the subsystem request attempted by EDGDFHSM. You can obtain information about the return codes in *z/OS MVS Using the Subsystem Interface*.

Processing

EDGDFHSM issues messages when it encounters errors, but it does not always pass a non-zero return code back to the caller.

Environment

EDGDFHSM must be link edited in an APF-authorized library. It runs in AMODE(31) RMODE(ANY).

Managing System-Managed Tape Library Volumes: EDGLCSUX

DFSMSrmm uses the OAM installation exits CBRUXCUA, CBRUXEJC, CBRUXENT, and CBRUXVNL as described in Table 31 on page 180 to manage the tape volumes defined in system-managed tape libraries. DFSMSrmm supplies Assembler source code for these installation exits, which is installed on your system as modules CBRUXCUA, CBRUXEJC, CBRUXENT, and CBRUXVNL. You can modify the source code to include your own function or merge with another product's supplied code.

DFSMSrmm uses EDGLCSUX to support:

- Tracking TCDB changes by updating the DFSMSrmm control data set.
- Updating the CBRUXxxx parameter list based on DFSMSrmm information.
- Partitioning a library.
- Handling volume-not-in-library conditions.
- Controlling the purging of TCDB volume entries at eject time.

You can use the DFSMSrmm EDGRMMxx OPTION SMSTAPE operand to control the support that DFSMSrmm provides. Refer to “Defining System Options: OPTION” on page 122 for information about the SMSTAPE operand.

Table 31. OAM Installation Exits

Exit	Description
CBRUXCUA	The CBRUXCUA exit is used to control return to scratch status and update the DFSMSrmm control data set with information from the TCDB.
CBRUXEJC	The CBRUXEJC exit is used to control ejecting a cartridge from a library and to update information in the DFSMSrmm control data set.
CBRUXENT	The CBRUXENT exit is used to control entry of a cartridge into a library, update information in the DFSMSrmm control data set, and update DFSMSrmm information in the TCDB.
CBRUXVNL	The CBRUXVNL exit is used to retrieve information from the DFSMSrmm control data set when a volume that is not in a tape library dataserver is needed for processing to continue.

The OAM exits that DFSMSrmm supplies call EDGLCSUX, the DFSMSrmm program that supports the OAM interface. EDGLCSUX is a callable program interface to DFSMSrmm that you can use only from the OAM installation exits.

If you do not have a license for DFSMSrmm, the DFSMSrmm OAM exits set a return code of 16, telling OAM to never call the exit again. For information on licensing, see “Ensuring DFSMSrmm is Enabled” on page 29. If you are licensed for DFSMSrmm, and you have performed some of the installation steps, but have not added EDGSSSI to the IEFSSNxx member of parmlib, or have not started the DFSMSrmm procedure, DFSMSrmm sets return code zero, allowing all OAM requests to be accepted. Once you have performed the installation steps, but do not start the DFSMSrmm subsystem, the OAM exits set a return code 8 and fail all requests.

Input

The input is a parameter list mapped by the macro EDGLCSUP, shown in “OAM Interface: EDGLCSUP” on page 365. The parameter list describes the OAM installation exit calling EDGLCSUX and provides the address of the information passed to the exit.

In the EDGLCSUP macro, the field LCSUP_LCSPL must contain the pointer to the OAM installation exit parameter list, which is the value in register 1 on entry to the OAM exit. The OAM installation exit parameter list macros are used to map this data. See *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries* for more information about CBRUXCPL, CBRUXEPL, CBRUXJPL, and CBRUXNPL.

Complete the LCSUP_FUNCTION field each time EDGLCSUX is called to indicate which OAM exit is calling it. Select from LCSUP_CUA, LCSUP_EJC, LCSUP_ENT, LCSUP_VNL, and LCSUP_ACTVNL.

The parameter list EDGLCSUP includes output fields for the OAM return code LCSUP_LCSRC and the DFSMSrmm reason code LCSUP_LCSRS. The fields LCSUP_LCSRC and LCSUP_LCSRS contain a reason code from DFSMSrmm and a return code to pass back to OAM. The LCSUP_LCSRC field contains the value that is recommended by DFSMSrmm to be returned for this OAM request. The

supplied DFSMSrmm OAM installation exits pass back these values. For example, if the LCSUP_LCSRC value is 4, DFSMSrmm has updated the OAM parameter list during processing. You can also use the return and reason codes set in register 15 and register 0 after the call to EDGLCSUX to determine the processing you might want to perform.

On entry, register 13 contains the address of a standard 18 word save area and register 14 contains the return address.

Output

The DFSMSrmm control data set and OAM parameter list are updated depending on the type of processing performed.

Register 15 contains the return code which indicates what processing should be performed next. Register 0 contains the reason code. Use the return code and the reason code to determine the processing DFSMSrmm has been able to perform. Table 32 shows the return and reason codes that EDGLCSUX sets in register 15 and register 0.

Table 32. EDGLCSUX Return and Reason Codes Returned in Register 15 and Register 0

Return Code	Reason Code	Description
0	0	Processing successful. LCSUP_LCSRC contains the return code for OAM. LCSUP_LCSRS contains a reason code that provides information about DFSMSrmm processing. The reason codes are described by variables LCSUP_RS_xxxx listed in the EDGLCSUP macro.
0	1	Processing successful. LCSUP_LCSRC contains the return code for OAM.
0	2	Processing successful. DFSMSrmm is not licensed for use on this processor. LCSUP_LCSRC contains the return code 16 for OAM.
4	0	Processing not performed because the DFSMSrmm subsystem was not available. LCSUP_LCSRC contains the return code for OAM.
8	0	Processing not performed because there was a logic error during processing. LCSUP_LCSRC contains the return code for OAM.
12	Various reason codes set	Processing is unsuccessful. The reason codes are described by variables LCSUP_RS_xxxx listed in the EDGLCSUP macro. The supplied exits set RC 8 for OAM to fail requests.

Table 33 on page 182 defines the return codes generated for each OAM function based on the reason codes set by DFSMSrmm in field LCSUP_LCSRS. The return code variables used in the table are defined in the OAM macros, CBRUXCPL, CBRUXEPL, CBRUXJPL, and CBRUXVNL.

Note: If the DFSMSrmm parmlib OPTION SMSTAPE(UPDATE(EXITS)) operand is not set or if DFSMSrmm is running in warning or record-only mode, the OAM return codes UXxFAIL are changed to UXxNOCHG.

Table 33. EDGLCSUX Return and Reason Codes Based on DFSMSrmm Reason Code Setting

Reason Code	Description	Related Message Number	Change Use Return Code	Volume Entry Return Code	Volume Eject Return Code	Volume- Not in- Library
0	DFSMSrmm accepted request	n/a	UXCNOCHG or UXCCHG[1]	UXENOCHG or UXECHG[1]	UXJNOCHG or UXJCHG[1]	UXNNORML or UXNCHG[1]
LCSUP_RS_DEB	Specified destination is not current library	EDG8192I	n/a	UXEFAIL	n/a	n/a
LCSUP_RS_DUPLV	Volume duplicates an existing logical volume	EDG8183I	n/a	UXEFAIL	n/a	n/a
LCSUP_RS_DUPPV	Volume duplicates an existing physical volume	EDG8182I	n/a	UXEFAIL	n/a	n/a
LCSUP_RS_DUPSV	The volume duplicates an existing stacked volume.	EDG8181I	UXCFAIL	UXEFAIL	UXJFAIL	n/a
LCSUP_RS_IRK	Volume rack number inconsistent	EDG8189I	UXCFAIL	UXEFAIL	UXJNOCHG	n/a
LCSUP_RS_IVU	User ID not valid for DFSMSrmm	EDG8195I	UXCFAIL	UXEFAIL	UXJNOCHG	n/a
LCSUP_RS_NMV	Volume not to be used with MVS	EDG8191I	UXCFAIL	UXEIGNOR	UXJFAIL	n/a
LCSUP_RS_NOTEXP	Imported volume is not exported	EDG8183I	n/a	UXEFAIL	n/a	n/a
LCSUP_RS_NRM	Volume not defined in a manual tape library	EDG8197I	UXCNOCHG	UXENOCHG	UXJNOCHG	UXNNORML
LCSUP_RS_PBD	Inconsistent parameter list	EDG8190I	UXCFAIL	UXEFAIL	UXJFAIL	UXNFAIL
LCSUP_RS_RIU	Rack to match volser not available	EDG8198I	UXCFAIL	UXEFAIL	UXJNOCHG	n/a
LCSUP_RS_RJP	Undefined volume rejected by reject prefix	EDG8193I	UXCFAIL	UXEIGNOR	UXJNOCHG	n/a

Table 33. EDGLCSUX Return and Reason Codes Based on DFSMSrmm Reason Code Setting (continued)

Reason Code	Description	Related Message Number	Change Use Return Code	Volume Entry Return Code	Volume Eject Return Code	Volume- Not in- Library
LCSUP_RS_RPX	Retention period exceeds installation maximum	EDG8196I	UXCFAIL	UXEFAIL	UXJNOCHG	n/a
LCSUP_RS_SCR	Private to scratch status not permitted	EDG8194I	UXCFAIL	UXEFAIL	UXJFAIL	n/a
LCSUP_RS_SMM	Entry status and DFSMSrmm status of volume mismatch	EDG8180I	n/a	UXENOCHG	n/a	n/a

Notes:

1. When the following conditions are true:
   - Status is private and no expiration date is supplied
   - Status is private and last read or write dates are lower than the DFSMSrmm equivalent dates
   - Status is scratch and owner information exists; the first 8 bytes are set to blanks
   - Volume entered into a system-managed tape library and DFSMSrmm has values for either storage group name, owner, or tape device selection information

Processing

For information about how DFSMSrmm works with system-managed tape libraries, see “Chapter 4. Running DFSMSrmm with System-Managed Tape Libraries” on page 77. For information about how DFSMSrmm running mode affects system-managed tape library support, see “Defining System Options: OPTION” on page 122.

DFSMSrmm Processing for OAM Support

DFSMSrmm processing is dependent on:

- The OPMODE processing mode specified in the DFSMSrmm EDGRMMxx parmlib member. When DFSMSrmm is running in manual mode, no DFSMSrmm processing is performed. When DFSMSrmm is running in warning mode, DFSMSrmm issues messages but does not fail any requests.
- The TCDB purge option specified in the DFSMSrmm EDGRMMxx parmlib member. Use the SMSTAPE(PURGE) option to control the processing that DFSMSrmm performs when a volume is ejected. DFSMSrmm can always keep the record, always purge the record, or accept the requestor’s decision. If the requestor did not make a decision, DFSMSrmm uses the ISMF default value. The ISMF default can be set at the library level. If the TCDB record is kept, DFSMSrmm adds the destination location and bin information to the OAM shelf location information. This avoids the WTOR to the operator prompting for shelf information. If the shelf location is still set to ’DEST=’ during entry processing, DFSMSrmm clears the field. Library partitioning driven by REJECT ANYUSE(prefix) and volume not for use on MVS, is performed by DFSMSrmm in all modes except manual mode.

- DFSMSrmm performing library partitioning driven by REJECT ANYUSE(prefix) and volume not for use on MVS when DFSMSrmm is running in all modes except manual mode.
- The DFSMSrmm EDGRMMxx parmlib OPTION SMSTAPE(UPDATE(EXITS)) operand. Information provided by OAM to the exits is used to enhance the information recorded by DFSMSrmm.You can decide whether the OAM information overrides the information already defined to DFSMSrmm. Use the SMSTAPE(UPDATE(EXITS)) option to specify that DFSMSrmm information overrides other information and that volume-not-library processing should be activated. When DFSMSrmm is running in protect mode, the DFSMSrmm information is always used to override the information from OAM and performs volume-not-library processing

See “Defining System Options: OPTION” on page 122 for information about the options.

Table 34 describes DFSMSrmm processing for OAM support.

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List

Variable	Field Name	Input	Output
Checkpoint volume indicator	UXCCHKPT UXECHKPT UXJCHKPT	Not used	Not used
Installation exit information	UXCEXITI UXEEXITI UXJEXITI	DFSMSrmm uses this for communication between different parts of DFSMSrmm.	Input only
Last entry or ejection date	UXCENTEJ UXEENTEJ UXJENTEJ	DFSMSrmm updates the control data set with this value if no date is recorded or if the input date is later than the existing date. DFSMSrmm uses this to set the movement tracking date.	Input only
Last mounted date	UXCMOUNT UXEMOUNT UXJMOUNT	DFSMSrmm records this date if no date exists or if this date is more current than the existing date.	DFSMSrmm returns a date in the parameter list if the date is less than the date already recorded by DFSMSrmm. DFSMSrmm sets return code UXyCHG to indicate that the parameter list has been changed.
Last written date	UXCWRITE UXEWRITE UXJWRITE	DFSMSrmm records this date if no date exists or if this date is later than the existing date.	If the date is less than the existing date, DFSMSrmm returns the last written date and sets return code UXyCHG to show that the parameter list has been changed.
Library console name	UXCLCON UXELCON UXJLCON	All error messages issued by DFSMSrmm to support the OAM functions are issued to the named console and to consoles using the correct routing codes.	Input only

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List (continued)

Variable	Field Name	Input	Output
Library description	UXCLDESC UXELDESC UXJLDESC	Not used	Input only
Library device type	UXCLDEV UXELDEV UXJLDEV	Not used	Input only
Library logical type	UXCLTYP UXELTYP UXJLTYP	If the volume is being defined to DFSMSrmm, and resides in a system-managed tape library, location type identifies if the volume resides in an automated tape library or manual tape library. For a volume that is already defined to DFSMSrmm, DFSMSrmm updates the location type with this value. **Note:** When volumes residing in a system-managed tape library are not defined to DFSMSrmm, DFSMSrmm creates a volume record. The latest information is recorded by DFSMSrmm when volumes are ejected from the system-managed tape library. This ensures information will be available if the volume is ever entered into any other library controlled by the same control data set.	Input only
Library name	UXCLIB UXELIB UXJLIB	Location name • If the volume is being defined for the first time, DFSMSrmm records this value as the home location and location name for the volume. • If the volume is already defined to DFSMSrmm, DFSMSrmm will update the volume location name to this value if the existing location name is different. If the rack number for the volume is not the same as the volume serial number, then DFSMSrmm sets a return code and reason code and issues message EDG8189I. If the rack number is not available, DFSMSrmm sets a return code and reason code and issues message EDG8198I.	Input only

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List (continued)

Variable	Field Name	Input	Output
New use attribute	UXCUSEA UXEUSEA UXJUSEA	The value can be: **S for scratch** For change use attribute and cartridge eject processing, if the volume currently is defined to DFSMSrmm as a master or user volume, then this request is rejected and DFSMSrmm does not change the use attribute. DFSMSrmm sets a reason code and return code and issues message EDG8194I. For cartridge entry processing, if the volume is currently defined as a master or user volume, then DFSMSrmm returns the volume status recorded in the control data set to the caller. **P for private** The volume information is changed or added to DFSMSrmm regardless of its current status.	This value is input only for change use attribute and cartridge eject processing. DFSMSrmm updates this information during cartridge entry processing if the volume is defined to DFSMSrmm and the status recorded in control data set is different.
Notification call	UXJNCALL	DFSMSrmm uses this field to avoid rejecting or failing an export of a logical volume.	Input only
Shelf location	UXCSHLOC UXESHLOC UXJSHLOC	Not used	Not used Cleared if the location name starts with DEST= Set to DEST=destination name, bin number, and medianame if TCDB record is kept.
Stacked volume	UXJSTKVS	DFSMSrmm uses this field as the 'in container' value.	Input only
Storage group name	UXCGROUP UXEGROUP UXJGROUP	DFSMSrmm updates the DFSMSrmm control data set with the storage group name, except during cartridge entry processing when the storage group name is already set.	DFSMSrmm updates this value during cartridge entry processing if the storage group name is already set.

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List (continued)

Variable	Field Name	Input	Output
Tape drive selection information	UXCTDSI UXETDSI UXJTDSI	DFSMSrmm uses this value to replace tape drive selection information during change use attribute and cartridge eject processing. Tape drive selection information corresponds to the DFSMSrmm recording format, media type, compaction, and special attributes.	DFSMSrmm uses this value to update tape drive selection information during cartridge entry processing. DFSMSrmm merges the known information from OAM with the information in the control data set to produce tape drive selection information.
Volume attribute	UXEVATTR	Volume type. DFSMSrmm uses the physical volume to process the volume as a real volume. DFSMSrmm uses the logical volume and imported logical volume attributes to identify the volume type as a logical volume. DFSMSrmm checks to see if logical volumes have been correctly imported or entered to control entry and import processing. For imported volumes, the volumes must not already be defined to DFSMSrmm or must be defined as an exported logical volumes. If the volumes are not correctly defined, DFSMSrmm issues message EDG8182I or EDG8184I and appropriate reason codes.	Input only
Volume expiration date	UXCEXPIR UXEEXPIR UXJEXPIR	DFSMSrmm records this value when a new private volume is added or when a volume is changed from scratch to master status. If the volume is already defined as a master volume, DFSMSrmm ignores this value. If the date exceeds the maximum retention period then DFSMSrmm fails the request and issues message EDG8196I and sets return code UXCFAIL.	If the input date is less than the existing date, DFSMSrmm returns the most recent date in the parameter list and sets return code UXyCHG to show that the parameter list has been changed. Note that this is an output field when changing the status to PRIVATE.

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List (continued)

Variable	Field Name	Input	Output
Volume location code	UXCLOC UXELOC UXJLOC	Values can be: **S for SHELF** The volume was ejected from the system-managed tape library and is in transit. **L for LIBRARY** The volume is resident in the system-managed tape library.	Input only
Volume owner information	UXCOWNER UXEOWNER UXJOWNER	The first 8 characters are used to identify the DFSMSrmm owner. If the volume is changing from scratch to master status or is being added as master then DFSMSrmm checks the owner information. If this is a valid DFSMSrmm owner then DFSMSrmm adds or updates the volume owner information in the control data set. If the owner is not a valid owner name, DFSMSrmm sets a default which is the DFSMSrmm user ID or its step name if the DFSMSrmm ACEE cannot be located. If DFSMSrmm is running in protect mode during change use attribute processing, DFSMSrmm rejects the request and issues message EDG8195I and sets the CBRUXCUA return code UXCFAIL. If the volume is a master volume, DFSMSrmm examines the first 8 characters of the owner information. If the owner information is valid but is different from the current DFSMSrmm owner then DFSMSrmm uses the information to update the owner information for the volume. If the owner information is not valid, DFSMSrmm sets a return code and issues message EDG8195I. During cartridge entry processing, or when owner information does not exist, DFSMSrmm returns owner information in the parameter list.	For volumes to be added as scratch volumes, there should be no owner information. If the first 8 characters of owner information are not null or blank, DFSMSrmm set a null owner name and sets CBRUXCUA return code to UXCCHG. During cartridge entry processing, or if the input owner information was not provided, DFSMSrmm returns the first 8 bytes of owner information.

Table 34. Processing for the Change Use Attribute, Cartridge Entry and Cartridge Eject Parameter List (continued)

Variable	Field Name	Input	Output
Volume record creation date	UXCCREAT UXECREAT UXJCREAT	Not used	Input only
Volume serial	UXCVOLSR UXEVOLSR UXJVOLSR	This value is used to identify the volume to be processed.	Input only
Write protection status	UXCWPROT UXEWPROT UXJWPROT	Not used	Not used

Change Use Attribute Specific Processing

Table 35 describes change use attribute processing.

Table 35. Processing for the Change Use Attribute Parameter List

Variable	Field Name	Input	Output
Current use attribute	UXCCUSEA	Not used	Input only

Cartridge Entry Specific Processing

Table 36 describes cartridge entry processing.

Table 36. Processing for the Cartridge Entry Parameter List

Variable	Field Name	Input	Output
		There are no cartridge entry specific parameter list fields for which DFSMSrmm does processing.	

Cartridge Eject Specific Processing

Table 37 describes cartridge eject processing.

Table 37. Processing for the Cartridge Eject Parameter List

Variable	Field Name	Input	Output
Volume serial	UXJVDISP	This is a volume record disposition which can be: **K for KEEP** Specifies that the volume record should be kept **P for PURGE** Specifies that the volume record should be purged	DFSMSrmm processing depends on the DFSMSrmm EDGRMMxx parmlib OPTION SMSTAPE(PURGE) operand value specified. If ASIS is specified, DFSMSrmm does not change the output field. If YES, we set to P, if NO we set to K.

Volume-Not-In-Library Specific Processing

The DFSMSrmm EDGLCSUX programming interface returns information for a volume, indicating whether the volume is a logical exported volume and the stacked volume on which it is exported. The sample CBRUXVNL exit is updated to call EDGLCSUX to issue a WTOR for all logical volumes. EDGLCSUX issues message EDG8123D to provide information about the stacked volume.

Table 38 describes volume-not-in-library processing.

Table 38. Processing for the Volume-Not-In-Library Parameter List

Variable	Field Name	Input	Output
Library name	UXNLIB	Contains library name into which the volume should be entered, or blanks. DFSMSrmm adds this library name to message EDG8121D so that the operator can enter the volume into the correct library. A value of blanks is displayed as the value **ANY**.	Input only

With volume-not-in-library processing, you can set flags to enable DFSMSrmm to retrieve volume information and to request that DFSMSrmm uses WTOR processing to communicate with the operator. When EDGLCSUX is called from CBRUXVNL, you can set either LCSUP_VNL flag or LCSUP_ACTVNL flag. You must first specify LCSUP_VNL to enable DFSMSrmm to retrieve volume information. Your second request, which is optional, must specify LCSUP_ACTVNL to request that DFSMSrmm uses WTOR processing to communicate with the operator. Between calls to EDGLCSUX from CBRUXVNL, do not modify any of the data returned by DFSMSrmm because the information is used in the messages sent to the operator.

When DFSMSrmm is first called from CBRUXVNL, DFSMSrmm retrieves information about the subject volume from the DFSMSrmm control data set if the volume is defined to DFSMSrmm. DFSMSrmm passes back volume location, movement, and status information in output fields in the EDGLCSUP parameter list. When DFSMSrmm is called a second time, and you have set the LCSUP_ACTVNL flag, DFSMSrmm issues the following messages which prompt the operator to enter the volume into the identified library. If the LCSUP_ACTVNL flag is not set, DFSMSrmm does not issue these WTORs for the operator to move the volume into the system-managed library.

- **EDG8121D** VOLUME *req_volser* RACK *rack_number* LOCATION *loc_name* BIN *bin_number* HOME LOCATION *home* - ENTER VOLUME INTO LIBRARY *lib_name* AND REPLY ″RETRY″, OTHERWISE REPLY ″CANCEL″ OR ″CONTINUE″
- **EDG8122D** VOLUME *req_volser* RACK *rack_number* LOCATION *loc_name* BIN *bin_number* HOME LOCATION *home* - ENTER VOLUME INTO LIBRARY *lib_name* AND REPLY ″RETRY″, OTHERWISE REPLY ″CANCEL″

For volumes residing in a VTS, DFSMSrmm issues the message EDG8123D.

- **EDG8123D** LOGICAL VOLUME *req_volser* EXPORTED IN STACKED VOLUME *stack_volser* LOCATION *loc_name* SHELF *shelf_number* HOME LOCATION *home* - IMPORT VOLUME TO LIBRARY *lib_name* AND REPLY ″RETRY″, OTHERWISE REPLY ″CANCEL″

Based on the reply, the return code for OAM, is set in field LCSUP_LCSRC ready to be passed back direct to OAM by the CBRUXVNL exit. The LCSUP_LCSRC field is set as follows:

Reply Return Code

CONTINUE
0 - UXNNORML

RETRY
4 - UXNRETRY

CANCEL
8 - UXNFAIL in PROTECT mode, UXNNORML in other modes.

Table 39 defines the OAM return codes generated when the EDGLCSUX return code is not zero. The return code is the value in register 15 on return from EDGLCSUX.

Table 39. DFSMSrmm OAM Return Codes from EDGLCSUX Register 15

Return Code	Description	Related Message Number	OAM Return Code
LCSUP_RC_OK R0 is LCSUP_RS_OK	Processing successful	none	See reason code in LCSUP_LCSRS field
LCSUP_RC_OK R0 is LCSUP_RS _NOACTION	Subsystem not required by installation	none	UX*x*NOCHG[1], UXNNORMAL
LCSUP_RC_OK R0 is LCSUP_RS_DONT	DFSMSrmm not licensed by installation	none	UX*x*DONT [1]
LCSUP_RC_SSNA	Subsystem not available	EDG8102D EDG8108D EDG8110D	UX*x*FAIL [1]
LCSUP_RC _LERR	Logic error in DFSMSrmm processing	EDG8105I EDG8106I EDG8107I	UX*x*FAIL [1]
LCSUP_RC_ENV	Environment error detected	EDG8101I EDG8111I EDG8112I	UX*x*FAIL [1]

Notes:

1. *x* can be:
   - C for change use return codes
   - E for volume entry
   - J for volume eject return codes
   - N for not in volume return codes
   - UX*x*NOCHG is issued for change use, volume entry and volume eject
   - UXNNORML is issued for not in library only

Environment

EDGLCSUX executes in the same environment as the OAM exits, but in AMODE(31) RMODE(ANY).

Processing Fetch and Mount Messages: EDGMSGEX

The system uses DFSMSdfp MSGDISP to update the display screens on tape drives. DFSMSrmm supplies Assembler source code for IGXMSGEX, the MSGDISP installation exit, that you can modify to include your own functions or to merge with another product's supplied exit code.

IGXMSGEX calls EDGMSGEX, the program that supports the MSGDISP interface. EDGMSGEX is a callable program interface to DFSMSrmm that you can use from the MSGDISP exit. The following sections describe how to use the interface.

Input

The invocation environment must be identical to that provided at entry to the MSGDISP exit IGXMSGEX.

Output

The output is MSGDISP parameters that are updated as appropriate. Register 15 is always zero.

Processing

For non-specific mount requests, where a specific scratch pool is required, DFSMSrmm updates the message text with the pool details. If you use the EDGUX100 installation exit to select a specific pool, DFSMSrmm updates the message text and checks the cartridge loader status. If you requested the loader be disabled for a specific pool, DFSMSrmm sets bit 7 of the format control byte to zero.

For specific mount requests, DFSMSrmm checks the volume and uses the volume serial number to determine the rack number and updates the message text with the rack number. If you use the installation exit EDGUX100 to specify a rack number or external volser for a volume that DFSMSrmm should ignore, DFSMSrmm uses the value you specify to update the message with the rack number.

Environment

EDGMSGEX runs only from the MSGDISP exit IGXMSGEX. It runs in AMODE(31) RMODE(31).

Processing JES3 Messages: EDG3X71

The DFSMSrmm-supplied IATUX71 USERMODcalls EDG3X71 which is the program that supports JES3 message processing. EDG3X71 is a callable program interface to DFSMSrmm that you can use from the IATUX71 exit. The following sections describe how to use the interface.

Input

The invocation environment must be identical to that provided at entry to the exit IATUX71.

Output

R15 on exit is determined by DFSMSrmm processing. The possible values for the return code are the same codes described for IATUX71 return code. The intention is that you pass the EDG3X71 return code to JES3 as the IATUX71 return code.

0	DFSMSrmm sets this return code when the volume is not managed by DFSMSrmm or when DFSMSrmm is not currently in use.
4	DFSMSrmm sets this return code when the volume serial number is to be replaced by the rack number or pool prefix. MSGDISP text is also provided. DFSMSrmm sets this return code when you have coded the MNTMSG definitions to specify that the rack number is to be placed within the JES3 message text.
8	DFSMSrmm sets this return code when the rack number or pool prefix is to be added to the end of the JES3 message. MSGDISP text is also provided. DFSMSrmm sets this return code when you have: • Coded MNTMSG definitions so that DFSMSrmm appends the rack number after the JES3 message text. • Have not coded a MNTMSG definition for this message.
16	DFSMSrmm never sets this return code.

Processing

EDG3X71 can only be called from the JES3 exit IATUX71. If EDG3X71 is called when DFSMSrmm is not started or in use, EDG3X71 sets return code 0 for IATUX71. EDG3X71 determines whether information should be inserted or appended for JES3 messages and determines the value to be used for MSGDISP tape drive display processing.

To check that the IATUX71 exit modification is installed correctly, you can run some batch jobs that use both specific and non-specific tape requests. You should check that messages displayed on the consoles, in SYSLOG, in DLOG and MLOG, and in JESMSG contains the expected DFSMSrmm updates.

Environment

EDG3X71 runs under a JES3 subtask in the JES3 address space on the JES3 global. EDG3X71 must be link edited in an APF-authorized library. It runs in AMODE(31) RMODE(31).

Chapter 10. Using DFSMSrmm Installation Exits

DFSMSrmm provides installation exits EDGUX100 and EDGUX200. For usage information, see “Using the DFSMSrmm EDGUX100 Installation Exit” and “Using the DFSMSrmm EDGUX200 Installation Exit” on page 220.

Using the DFSMSrmm EDGUX100 Installation Exit

Use the DFSMSrmm EDGUX100 installation exit to:

- Ignore foreign or duplicate volumes as described in “Using EDGUX100 to Ignore Duplicate or Undefined Volume Serial Numbers” on page 197 and optionally provide an external volume serial number for use in messages intercepted and updated by DFSMSrmm.
- Use JCL special expiration dates to manage volumes by setting vital record specification management values to retain data sets as described in “Using Vital Record Specification Management Values to Retain Tape Volumes” on page 199.
- Set any expiration date, including a zero value, for a data set as described in “Assigning Expiration Dates” on page 210.
- Perform pooling management as described in “Managing Scratch Pools” on page 201 to:
  - Manage scratch pools based on job name and data set name.
  - Select a pool to be used for a non-specific tape volume request.
  - Select a specific pool to be used for a non-specific tape volume request and request that the tape drive cartridge loader is disabled.
- Pass vital record specification management value and pooling decisions to pre-ACS processing that can be used in ACS routines to assign storage group and management class.
- Obtain information to modify input from DFSMSrmm disposition processing as described in “Creating Sticky Labels” on page 204.
- Request the recording of only the first file on a multi-file volume as described in “Controlling Tape Volume Data Set Recording” on page 206.
- Change the location for a volume as described in “Changing Location Information with EDGUX100” on page 207.
- Support the use of the storage group name for pooling for volumes that reside in manual tape libraries as described in “Using Storage Group for Manual Tape Library Pooling” on page 214.

Planning to Manage Scratch Pools with EDGUX100

You define pools to DFSMSrmm in parmlib that the EDGUX100 installation exit selects for new tape data sets that are to be created on non-specific volumes. During OPEN processing DFSMSrmm uses the pool that you specify to validate that a scratch volume has been mounted from the selected pool. Each pool can be defined with different attributes, and can either be a scratch pool or a rack pool. DFSMSrmm ACS storage group support can be used instead of the EDGUX100 exit selected pooling. Refer to “Using Storage Groups for DFSMSrmm Scratch Pooling” on page 63 for information about using the DFSMSrmm storage group support.

If you plan to use EDGUX100 to select volumes from specific scratch pools with DFSMSrmm you need to consider the following:

© Copyright IBM Corp. 1992, 2001

Pool Types

The pools that you select using the EDGUX100 installation exit must match to a VLPOOL rack number prefix defined in the DFSMSrmm parmlib member as described in “Defining Pools: VLPOOL” on page 148.

You can use EDGUX100 to set up a specific pool for a particular user of your systems. You can define a scratch or rack pool and can define any type of volume in that pool. You do not need to have two pools for a user; one for scratch volumes and one for private volumes. For example, you could define some volumes for use as scratch that will cycle between scratch and master status throughout their life, and you could also define specific, private volumes that are never to be used as scratch.

The difference between *rack* and *scratch* pools is unchanged. You use scratch pools with DFSMSrmm system based scratch pooling. You can define scratch volumes in rack pools and use the RMM GETVOLUME subcommand to claim them or assign them to a user. You can also use EDGUX100 to use rack pools or scratch pools for non-specific tape output requests.

When you define pools for use with EDGUX100, you also might need to prevent the pools from being used at the wrong times. For example, if your EDGUX100 exit does not make a pool selection you might want to ensure that DFSMSrmm accepts only scratch volumes which are not in your specific pools.

Here are three ways you can prevent pools from being used at the wrong time:

1. Ensure that your EDGUX100 exit always provides a specific pool. You could use a default pool prefix of ’*’ in the exit to ensure that the DFSMSrmm default pool is used for all requests that have no specific pool to be used.
2. Use only rack pools for your EDGUX100 scratch pools. You can also have DFSMSrmm scratch pools or a default scratch pool for use with those requests where your exit does not provide a specific pool.
3. Define all the specific scratch pools using a SYSID value that does not match any of your systems. This ensures that, if the exit does not supply a specific scratch pool and DFSMSrmm uses its own pooling, all the specific pools would be ignored.

Controlling Pool Selection

The sample EDGUX100 installation exit provides a working solution for application type scratch pools based on job names and data set names.

The exit does not validate the field contents, so be sure to follow the job naming conventions or your entry will never match real job names.

Tape Drive Availability

You can use the EDGUX100 exit to request DFSMSrmm to disable the tape drive cartridge loader to prevent specific scratch pool requests from emptying the loaders through volume rejection. Alternatively, you can direct requests to the correct drives or run the loaders in a mode that prevents them being automatically indexed when a mount is received.

Operator Messages and Tape Drive Displays

To use ACS routines or exit selected scratch pooling, you must define messages IEC501A, IEF233A, IAT5110, and IAT5210 using the DFSMSrmm MNTMSG commands in parmlib as described in “Defining Mount and Fetch Messages: MNTMSG” on page 119. These messages provide the pool identifiers to the operator, and the job name and data set name information to the EDGUX100 exit.

The sample EDGUX100 exit obtains the job name and data set name for a non-specific volume request from the text of the message. The data set name is only included if MONITOR DSNAME is in effect. If you plan to use the sample EDGUX100 you must activate the MONITOR DSNAME option through an operator command. See *z/OS MVS System Commands* for more information about the MONITOR command.

Using EDGUX100 to Ignore Duplicate or Undefined Volume Serial Numbers

DFSMSrmm ignores volumes that are not defined to DFSMSrmm for specific mount requests. For non-specific requests, DFSMSrmm ensures that a DFSMSrmm-managed scratch volume is mounted in response to the request. When DFSMSrmm ignores a volume, DFSMSrmm:

- Does not record information about it in the DFSMSrmm control data set
- Does not validate that the correct volume has been mounted
- Performs no management functions for the volume

You can also request that DFSMSrmm ignores volumes defined to it. In this case, DFSMSrmm does not track volume use and cannot provide management functions you might expect.

You must use the DFSMSrmm EDGUX100 installation exit to have DFSMSrmm ignore a volume, when either of the following conditions exist:

- REJECT ANYUSE(*) is used in the parmlib, resulting in an undefined volume being rejected
- The volume is in an automated tape library dataserver and is automatically defined to DFSMSrmm when it is used.

If these conditions are not present, DFSMSrmm automatically ignores all volumes that are not defined to it without using the DFSMSrmm sample installation exit.

When you use the EDGUX100 installation exit, DFSMSrmm calls the exit each time a volume is opened. You can modify the sample installation exit to use duplicate or undefined volumes. The sample installation exit checks the JCL specified EXPDT value for a special date of 98000, meaning that the volume should be ignored. If this special date is found, the exit then uses the installation exit parameter list to request that DFSMSrmm ignores the volume.

You can also request that DFSMSrmm ignores a volume by specifying the ACCODE parameter in the DD statement. The sample exit checks the JCL ACCODE value for the xCANORES special value that means that the volume should be ignored. If the special value is found, the exit processes the volume the same way it processes a volume when EXPDT=98000 is specified.

Before DFSMSrmm ignores the volume, it ensures that the user who opened the volume is authorized to request that DFSMSrmm ignore the volume. DFSMSrmm uses a security resource in RACF FACILITY class, and issues a SAF RACROUTE TYPE=AUTH request with an entity name of:

```
STGADMIN.EDG.IGNORE.TAPE.volser
```

where `volser` is the volume serial number of the mounted tape volume.

Step 1: Tailor the DFSMSrmm EDGUX100 Installation Exit

Based on the decisions you have made about how to manage duplicate or undefined volume serial numbers, tailor the supplied sample EDGUX100 installation exit as follows:

1. Make a copy of the sample installation exit to use as a base for your exit.
2. Update the exit. See “Assigning Expiration Dates” on page 210 for additional processing information.
   - Only perform your processing when the PL100_CAN_IGNORE bit is set to B'1'.
   - Decide whether to support the pre-ACS call to obtain a VRS management value or scratch pool prefix for use as the MSPOLICY and MSPOOL variables in ACS processing. You must ignore the call if the volume is to be ignored. During the pre-ACS call, an ACERO is passed instead of a JFCB. See *z/OS DFSMS Installation Exits* for information about the ACERO.
   - Use the value in the JFCB expiration date field, JFCBXPDT, to determine if a special date has been specified.You could also use the PL100_ACCODE field to check if the special ACCODE value has been supplied.
   - If the special date 98000 or the special ACCODE=xCANORES value has been specified, set the PL100_SET_IGNORE flag to B'1' to get this volume ignored.
   - If you want to provide a rack number for DFSMSrmm to use in the WTO messages it updates, place the rack number value in the PL100_RACKNO field.
   - You do not need to update the JFCB. The information will not be passed on to DFSMSrmm, and since it is a copy of the JFCB used solely by DFSMSrmm no other component can make use of your changes. However, because the EDGUX100 installation exit is called for system-managed volumes, but non-specific system-managed volumes cannot be ignored, you should clear the expiration date to prevent DFSMSrmm from using the 98000 date as a volume expiration date. The DFSMSrmm sample exit clears the expiration date.

Step 2: Activate the EDGUX100 Installation Exit

See “Installing the EDGUX100 Routine” on page 214 for information about building an SMP/E USERMOD to apply the updated source code for EDGUX100 so that it supersedes any old EDGUX100 USERMODs. Include the necessary JCLIN statements as shown in Figure 101 on page 215.

Step 3: Define a RACF FACILITY Class Entity to Check Authorization

Define a RACF FACILITY class entity, STGADMIN.EDG.IGNORE.TAPE.volser, which is used to check that the user trying to use a duplicate or undefined volume is authorized to request that DFSMSrmm ignore the volume. Only users with the correct authorization to STGADMIN.EDG.IGNORE.TAPE.volser can request that DFSMSrmm ignore volumes.

Define multiple resources as required for individual volumes or groups of volumes using RACF generic resource names. For example:

```
RDEFINE FACILITY STGADMIN.EDG.IGNORE.TAPE.X* UACC(NONE)
RALTER FACILITY STGADMIN.EDG.IGNORE.TAPE.X* GLOBALAUDIT(SUCCESS)
RDEFINE FACILITY STGADMIN.EDG.IGNORE.TAPE.810* UACC(NONE)
RALTER FACILITY STGADMIN.EDG.IGNORE.TAPE.810* GLOBALAUDIT(SUCCESS)
```

where; GLOBALAUDIT(SUCCESS) ensures that RACF maintains an audit trail of all successful uses of this facility.

Step 4: Authorize Users

Permit those users authorized in your installation to the appropriate STGADMIN.EDG.IGNORE.TAPE.volser resources. For example:

```
PE STGADMIN.EDG.IGNORE.TAPE.X* CLASS(FACILITY) ID(user1) ACCESS(level)
PE STGADMIN.EDG.IGNORE.TAPE.810* CLASS(FACILITY) ID(user2) ACCESS(level)
```

where

user1
Is the user ID of the user given access.

Level
Is the granted access level; one of READ or UPDATE.

READ access is required for a volume to be opened for input requests. UPDATE access is required for a volume to be opened for output requests.

Using Vital Record Specification Management Values to Retain Tape Volumes

You can use the EDGUX100 installation exit to assign vital record specification management values to new tape data sets. When a volume is opened, DFSMSrmm records the vital record specification management value you assign to new tape data sets. You then define vital record specifications using data set name masks that match the vital record specification management values you define for special dates. These vital record specifications define the management policies for volumes with special dates.

You can use vital record specification management values to be the basis for assigning management class for system-managed tape. DFSMSrmm calls EDGUX100 to obtain a vital record specification management value.

- During pre-ACS processing, the vital record specification management value is passed to your ACS routine to so that allocation decisions can be made.
- During OPEN processing for any new tape data set, this is an optional call that does not happen for a non-system-managed tape data set if you have assigned a management class during the RMMVRS ACS call.

Step 1: Define Vital Record Specification Management Values

A vital record specification management value is a single qualifier name you define in a vital record specification to tell DFSMSrmm how to manage and retain your tape data sets. The vital record specification management value can be up to eight alphanumeric characters, and must begin with an alphabetic character. DFSMSrmm matches a data set to a vital record specification management value during vital records processing when the data set does not match a vital record specification with a data set name mask and optionally a job name.

Use the RMM ADDVRS subcommand with the DSNAME operand or the DFSMSrmm Add Data Set VRS panel in the DFSMSrmm ISPF dialog to define data set vital record specifications. Use the data set name masks that match the vital record specification management values you have defined. See *z/OS DFSMSrmm Guide and Reference* for more information on defining vital record specifications.

For example, you can use the vital record specification management value D99000, for the special date 99000 and define a vital record specification using the data set name, D99000. Figure 92 on page 200 defines a vital record specification for managing the special date 99000.

```
RMM ADDVRS DSNAME('D99000') WHILECATALOG
```

Figure 92. Managing Special Date 99000 with Vital Record Management Value

You could also set the ACCODE=xCACATLG value in the DD statement to manage the special date 99000.

You could define a vital record specification data set name mask that matches multiple vital record specification management values. For example you could define a data set name mask of D9900% as shown in Figure 93 to cover several vital record specification management values. With this data set name mask you could manage special dates in the range 99001 through 99009.

```
RMM ADDVRS DSNAME('D9900%')
```

Figure 93. Specifying Data Set Masks for Vital Record Management Values

Step 2: Tailor the Sample EDGUX100 Installation Exit

Update the sample EDGUX100 installation exit based on vital record specification management values you define.

1. Copy the sample EDGUX100 installation exit and use the copy as a base for your exit.
2. Update the exit, bearing in mind the following:
   - Only perform your processing when the PL100_CAN_VRS bit is set to B'1'.
   - If an ACERO is passed to the exit, use the ACEROEXP and ACERORTP fields to decided if a special date is specified. If a JFCB is passed to the exit, use the value in the JFCB expiration date field, JFCBXPDT to determine if a special date has been specified. Test the JFCBEXP flag to determine if the user specified an expiration date or a retention period. You can also test to see if the user wants the date used as real expiration date by checking for the existence of the dummy file NOTKEYD8.

     The sample EDGUX100 installation exit includes code for using this method specifying the DD name NOTKEYD8. You can also use the PL100_ACCODE field to check if the special ACCODE value has been supplied. Specifying ACCODE=xCACATLG is the same as using EXPDT=99000.
   - Based on the special date like 99000 or the ACCODE value, select the chosen vital record specification management value and use it to set the field PL100_VRS.
   - If you want DFSMSrmm to use a true expiration date, rather than the special date from the JCL, update the JFCBXPDT field with the date or with zero. If you update the field with a zero, DFSMSrmm uses the default retention period to calculate an expiration date. See “Assigning Expiration Dates” on page 210 for additional information. If you use in JCL only the ACCODE value, you do not need to alter the JCL expiration date.

   The DFSMSrmm EDGUX100 sample provides support for catalog control special dates during pre-ACS and OPEN time and provides the checking necessary for true expiration dates. You need to modify the sample exit if you wish to support other special dates. DFSMSrmm provides a second sample for EDGUX100. This sample is called EDGCVRSX. It provides more function than the EDGUX100 sample but the special date and pooling function is table driven and you can change the table dynamically. Refer to EDGCMM01 and the IBM

Redbook *Converting to Removable Media Manager: A Practical Guide* for documentation on using EDGCVRSX for EDGUX100.

3. Make any changes required for using vital record management values before building the USERMOD.

Step 3: Activate the EDGUX100 Installation Exit

See “Installing the EDGUX100 Routine” on page 214 for information about building an SMP/E USERMOD to apply the updated source code for EDGUX100 so that it supersedes any old EDGUX100 USERMODs. Include the necessary JCLIN statements as shown in Figure 101 on page 215.

To apply vital record specification management values to a new tape data set, you can either specify the special date 99000 in the EXPDT keyword or use corresponding special values in the ACCODE keyword of the DD statement. The EDGUX100 sample installation exit checks the ACCODE value for xCACATLG. If there is a matching value, DFSMSrmm performs the same actions that it performs when it processes 99000. If both ACCODE and EXPDT are used to specify special values, then DFSMSrmm uses the ACCODE value.

Using the ACCODE keyword, you can use the xCAUSER and xCAPERM special values. EDGUX100 treats these two values the same as the never expire date 99365 specified in the EXPDT parameter. A vital record specification management value D99365 is assigned to the data set which ensures that the data set is retained indefinitely.

Step 4: Run DFSMSrmm Inventory Management Vital Record Processing

Run DFSMSrmm inventory management vital record processing to identify which volumes should be retained based on the vital record specification management values you define. DFSMSrmm uses the vital record specification management value assigned to the data set to select the appropriate vital record specification, if inventory management vital record processing does not find a match on the data set mask. See “How Vital Record Processing Works” on page 267 for information about vital record processing.

Managing Scratch Pools

You define pools to DFSMSrmm in parmlib that the EDGUX100 installation exit can select for new tape data sets which are to be created on non-specific volumes. During OPEN processing DFSMSrmm uses the pool that you specify to validate that a scratch volume has been mounted from the selected pool. Each pool can be defined with different attributes, and can either be a scratch pool or a rack pool.

You can specify if you want DFSMSrmm to disable the autoloader when the EDGUX100 installation exit selects a scratch pool. By using the exit to disable the loader, you can prevent the loader from being emptied when it contains volumes from another pool. If you are using multiple scratch pools and a tape drive is allocated for a request that requires a pool that has not been pre-loaded, DFSMSrmm rejects pre-loaded volumes from other pools.

You can pass the EDGUX100 exit selected scratch pool prefix to your ACS routines for making allocation decisions and for assigning storage group names for system-managed tape data sets. You can do this using the pre-ACS call to the EDGUX100 installation exit. See “Using the EDGUX100 Installation Exit from Pre-ACS Processing” on page 204 for information about using the EDGUX100 installation exit from pre-ACS processing. You can replace the EDGUX100 processing by using the DFSMSrmm calls to SMS ACS routines requesting a

storage group name. Refer to “Using Storage Groups for DFSMSrmm Scratch Pooling” on page 63 for information about DFSMSrmm ACS support for storage group.

Step 1: Define the Pools

For each pool you need to decide whether this pool is to be used only for specifically identified purposes or whether it can be also selected based on system scratch pools. The easiest way to prevent a pool from being used as a system based scratch pool is to use only rack pools for your exit driven scratch pooling. If you do not do this, or you do not use one of the other methods described in “Planning to Manage Scratch Pools with EDGUX100” on page 195, you must use the EDGUX100 installation exit to always set a scratch pool to prevent an incorrect scratch pool from being accepted by DFSMSrmm.

DFSMSrmm identifies pools using a pool prefix which is a one to five character name followed by an asterisk. See “Defining Pools: VLPOOL” on page 148 for more information.

For example, if you want to define a pool with a prefix of ABC* for use by a specific application, define the pool to DFSMSrmm in parmlib using one of the statements shown in Figure 94:

```
VLPOOL PREFIX(ABC*) TYPE(R) RACF(Y) EXPDTCHECK(N) -
                 DESCRIPTION('Application XyZ')
VLPOOL PREFIX(ABC*) TYPE(S) RACF(Y) EXPDTCHECK(N) -
     SYSID(NONE) DESCRIPTION('Application XyZ')
```

Figure 94. Defining Pools for a Specific Application

SYSID(NONE) coded in the second example prevents the pool being used by the DFSMSrmm system scratch pooling as long as no DFSMSrmm system is defined with SYSID(NONE).

For each pool, decide if you will run with scratch volumes from this pool loaded in a cartridge loader. For those pools which are not loaded, you should consider using the EDGUX100 installation exit to disable the cartridge loader whenever those pools are requested.

Step 2: Tailor the Sample EDGUX100 Installation Exit

Update the sample EDGUX100 installation exit based on the pools you define using the VLPOOL command in parmlib. The supplied sample EDGUX100 installation exit supports pooling based on job name and data set name. Modify the supplied exit if you pool based on other criteria.

To use the exit you must:

1. Copy the sample EDGUX100 installation exit. If you are already using the EDGUX100 installation exit to support another function, you need to start using your latest copy of the exit source, or merge in any changes you have previously made to the exit.
2. Update the exit, bearing in mind the following:
   - Only perform your processing when the PL100_CAN_POOL bit is set to B'1'.
   - Your decisions on pooling must be possible whether the exit is called for MNTMSG processing, pre-ACS processing, or for OPEN processing. Your pooling decisions must work when a WTO address is provided during MNTMSG processing, an ACERO is provided during pre-ACS processing, or a JFCB address is provided during OPEN processing.

- Based on your pooling decisions, optionally select a pool for the current request and set the PL100_POOL field. You must also set the PL100_SET_POOL flag to B'1' for DFSMSrmm to use the PL100_POOL field. You can optionally set the PL100_SET_ACLOFF flag to B'1' to request that the tape drive cartridge loader is not indexed for the request. See “Supplying a Scratch Pool Name” on page 211 and “Using the System Name to Select a Scratch Pool” on page 213 for additional information.

Step 3: Activate the EDGUX100 Installation Exit

See “Installing the EDGUX100 Routine” on page 214 for information about building an SMP/E USERMOD to apply the updated source code for EDGUX100 so that it supersedes any old EDGUX100 USERMODs. Include the necessary JCLIN statements as shown in Figure 101 on page 215.

Step 4: Define MNTMSG Parmlib Options

The sample MNTMSG parmlib options already include all the messages required for successful execution of the scratch pooling function provided by the sample exit. However, refer to “Operator Messages and Tape Drive Displays” on page 57 for information about the MNTMSG requirements so that you can ensure your system has the required options already in use.

Step 5: Set Up Cartridge Loaders

Ensure that cartridge loaders used with DFSMSrmm are set to system or manual mode.

Step 6: Updating JES3 Code (Optional)

This step is only required if you have JES3 managed tape devices and do not use deferred tape mounting. With deferred tape mounting, either allocation or OPEN processing issues the mount requests and the tape drive displays are correct.

JES3 updates the drive display before it issues the IAT5210 mount message, so the drive display might not contain the pool that you select in your exit.

You can use one of three methods for updating the IAT5210 message and the tape drive display. Using the DFSMSrmm supplied USERMOD EDGUX71 to IATUX71 is the preferred method for updating the IAT5210 message with the correct exit selected pool. The exit selected pool is used to update the tape drive displays when selection is based on the IAT5210 message.

See “Chapter 12. Running DFSMSrmm with JES3” on page 243 for information about installing and using DFSMSrmm-supplied JES3 USERMODs.

Step 7: Activate MONITOR DSNAME

The EDGUX100 installation exit depends on the system mount messages containing data set name information. If you plan to use data set name based pooling, you must issue the MONITOR DSNAME command.

For testing purposes, issue this command at an operator terminal. However, for production implementation, ensure that the command is always issued by including it as a command in the COMMNDxx member of the parmlib. Any other method that results in the monitor option being active before any tape requests are issued is also acceptable.

When a non-specific volume request is received, the exit can be used to determine the correct pool to be used.

Using the EDGUX100 Installation Exit from Pre-ACS Processing

You can use ACS routines to automatically determine the target storage group and assign data classes, storage classes, and management classes to SMS-managed data sets. You can use the pre-ACS interface to provide additional information like vault destination or pool information to the ACS routines. You can use the EDGUX100 installation exit for pre-ACS processing. When called during pre-ACS processing, values selected by the exit are used as input to the ACS routine. Then when the EDGUX100 installation exit is called at OPEN or when a volume is mounted, the exit can provide the same values it passed during the pre-ACS processing or provide different vital record specification management values and pool values.

The pre-ACS routine passes the address of the ACERO to the EDGUX100 installation exit. The ACERO is mapped by the IGDACERO macro and is the input to the pre-ACS installation exit IGDACSXT. You can use any of the values in the ACERO as input to the EDGUX100 installation exit. The sample EDGUX100 exit uses:

- ACEROJOB, which is the job name.
- ACERODSN, which is the data set name.
- ACEROEXP, which is the expiration date. The expiration date is used only if the retention period is not set.
- ACERORTP, which is the retention period.

The values are used to perform PL100_CAN_IGNORE, PL100_CAN_VRS, and PL100_CAN_POOL processing. All other functions are performed only when the EDGUX100 is not called by the pre_ACS routine.

If your installation's version of the EDGUX100 installation exit provides values for scratch pooling (PL100_POOL) or vital record specification management value (PL100_VRS), DFSMSrmm updates the the ACS input values for MSPOOL and MSPOLICY when they have not already been set by the IGDACSXT pre-ACS installation exit.

To perform pre-ACS processing, check the PL100_ACEROPTR field for the address of the ACERO.

Creating Sticky Labels

If you use DFSMSrmm disposition processing you do not need to use EDGUX100 to implement sticky label support because DFSMSrmm provides sticky label support as part of disposition processing. However, you can optionally use EDGUX100 to modify the default DFSMSrmm processing. Refer to "Chapter 20. Setting Up DFSMSrmm Disposition Processing" on page 347 for more information. If you do not use disposition processing, you can use the EDGUX100 installation exit to implement sticky label support:

- By using information that the installation exit provides for a sticky label routine you have written. The steps for tailoring the installation exit are described in "Step 1: Tailor the DFSMSrmm EDGUX100 Installation Exit" on page 205.
- For modifying the default labels produced by DFSMSrmm disposition processing described in "Modifying DFSMSrmm Label Output" on page 205.
- For suppressing the default labels produced by DFSMSrmm disposition processing described in "Modifying DFSMSrmm Label Output" on page 205.

Step 1: Tailor the DFSMSrmm EDGUX100 Installation Exit

You can implement sticky label support using the DFSMSrmm EDGUX100 installation exit and a sticky label routine you have written. DFSMSrmm calls the EDGUX100 installation exit whenever a tape data set is closed or reaches end of volume when the PL100_ITS_CLOSE option is set. When the exit is called with PL100_ITS_CLOSE set, there is information in the EDGPL100 parameter list that allows you to perform sticky label support. See “Installation Exit Mapping Macro: EDGPL100” on page 372.

If you want to change the sticky labels that DFSMSrmm generates for disposition processing, or create your own stickly labels, modify the supplied EDGUX100 code and either add your sticky label routine directly to the exit or add a LOAD or LINK statement to call your sticky label routine externally. Figure 95 shows where your routine for creating sticky labels can be called from EDGUX100.

```
JFCBPOOL EQU   *
*****************************************************************
* Now we'll check if we come from CLOSE/END OF VOLUME.
* If you want to perform sticky label support, add your code right
* before the statement 'NOTCLOSE  EQU  *'.
*****************************************************************
         TM    PL100_VALID,PL100_ITS_CLOSE Is it a call from C/EOV
         BZ    NOTCLOSE            No, continue
         L     R3,PL100_LABINFO    Address Label info block
         USING PL100_LABDS,R3      Addressability
         TM    PL100_OFLAG,PL100_FOUT Is it OUTPUT ?
         BZ    NOTCLOSE            No, continue
*  ...   your code here - continue at NOTCLOSE when finished
*        WTO   'Sticky label routine called . . . . '
*  Refer to PL100_LABDS DSECT in EDGPL100 macro for an explanation
*  of all the fields you may need for sticky label processing.
*
*****************************************************************
NOTCLOSE EQU   *
```

Figure 95. Sample EDGUX100 Installation Exit Sticky Label Support

Step 2: Activate the EDGUX100 Installation Exit

See “Installing the EDGUX100 Routine” on page 214 for information about building an SMP/E USERMOD to apply the updated source code for EDGUX100 so that it supersedes any old EDGUX100 USERMODs. Include the necessary JCLIN statements as shown in Figure 101 on page 215.

Modifying DFSMSrmm Label Output

Use the EDGUX100 installation exit to modify the label that DFSMSrmm produces as part of disposition control processing. You can set new values for the number of rows, the length of each row in the label. You cannot exceed the maximum label area size of 2000 characters. You can set an LRECL other than the default LRECL of 80. The LRECL you set must be the same length or less than the number of columns in each row in the label. You can change the values by modifying the label area passed to the EDGUX100 exit based on the PL100_LABDATA field.

You can also suppress the production of labels by setting the PL100_SET_NOLABEL bit to B'1'. DFSMSrmm checks for this bit at CLOSE time. See “Label Processing” on page 350 for information about modifying labels.

Controlling Tape Volume Data Set Recording

Use the EDGUX100 installation exit to request that DFSMSrmm records information about the first data set only and keeps track of the statistics at the volume level. DFSMSrmm then performs data set name checking on the first data set only. DFSMSrmm does not keep track of the number of data sets on the volume when data set recording is turned off for a volume. DFSMSrmm keeps track of some items like the use count to reflect the number of times the volume is read or written. You must request that DFSMSrmm records only the first data set each time you re-write the first data set. Otherwise DFSMSrmm resumes recording information about all the data sets on the volume.

You might want to limit DFSMSrmm recording of tape data set information because:

- A tape volume is assigned for use by a specific application and the application tracks the tape contents.
- A tape volume contains a large number of files and you do not need to know details of all the files.

Note: When the recording of data set information is suppressed, DFSMSrmm does not uncatalog these data sets during inventory management processing when the parmlib option UNCATALOG is specified as S or Y. Since DFSMSrmm cannot uncatalog the data sets, another method must be used to uncatalog them. Leaving non-existent data sets cataloged could lead to later processing problems. If you have applications that create multiple cataloged data sets on tape, and you suppress the DFSMSrmm recording of other than the first data set on the volume, it is your responsibility to ensure that the data sets other than the first data set are uncataloged.

Step 1: Tailor the DFSMSrmm EDGUX100 Installation Exit

During the OPEN processing for the first file on a volume, the EDGUX100 installation exit retrieves the data set name, job name and job step program name from system control blocks. The sample EDGUX100 installation exit then scans the EDMTAB table for a match. If there is a match, the EDGUX100 installation exit sets the PL100_SET_IGNORE_FILE2_TON bit to request DFSMSrmm only record data set details for the first file.

To use the EDGUX100 exit for this function, define a table as shown in Figure 96 on page 207. The order in which the table entries are listed is important because the exit scans the table until it finds the first entry where the job name, data set name and program name masks match the current request. You can change the priority of matching by changing the order of the table entries.

```
EDMTAB   DS    0F                  start of table
*                  jobname        data set name
         DC    CL8'*       ',CL44'BACKUP*'
         DC    CL8'ABC*'             program name
*
         DC    CL8'STSGWD* ',CL44'*'
         DC    CL8'A*'               program name
*
         DC    CL8'STSG%%* ',CL44'STSG%%.BACKUP.*'
         DC    CL8'DEF%MAIN'         program name
*
         DC    CL8'STSGDPW ',CL44'DAVE.TOOMUCH.DATA'
         DC    CL8'AB999*'           program name
*
         DC    CL8'EDMEND'         end of table marker
```

Figure 96. Sample Table for Controlling Data Set Recording

The table contains:

jobname
One to eight alphanumeric or national characters including % and *.
% can be used to ignore a positional character in the job name.
* can be used to ignore all remaining characters in the job name. A jobname of * means that the entry applies to all jobs.

data set name
Can be up to forty four characters, following MVS data set naming conventions, including % and *.
% can be used to ignore a positional character in the data set name.
* can be used to ignore all remaining characters in the data set name. A data set name of * means that the entry applies to all data sets.

The use of * is not the same as in the generic data set names supported by DFSMSrmm for vital records specifications and search data set masks. Here the * works like the *.*might in a generic data set name mask.

Program name
A value up to eight alphanumeric character including % and *.
% can be used to ignore a positional character in the program name.
* can be used to ignore all remaining characters in the program name. A program name of * means that the entry applies to all programs.

Step 2: Activate the EDGUX100 Installation Exit

See “Installing the EDGUX100 Routine” on page 214 for information about building an SMP/E USERMOD to apply the updated source code for EDGUX100 so that it supersedes any old EDGUX100 USERMODs. Include the necessary JCLIN statements as shown in Figure 101 on page 215.

Changing Location Information with EDGUX100

You can use the EDGUX100 installation exit to:

- Specify a new location name or location type for a volume.
- Clear the location name to prevent a volume from being assigned to a location.
- Add a location name when one was not originally assigned in the disposition control file.

You can change the contents of the PL100_NAME and PL100_LOCTYPE fields to change location or name information. On input, the fields contain values set from the disposition control file.

DFSMSrmm checks the storage location name and type you specify against the list of storage locations defined in the DFSMSrmm EDGRMMxx parmlib LOCDEF command. If you specified a storage location not defined to DFSMSrmm, DFSMSrmm treats the location like a loan location.

Use the PL100_INFO_CMOVE field to determine if a volume move is to be confirmed by checking for the bit that indicates that a later confirm move is required or is marked as already completed. Set PL100_SET_CMOVE or PL100_SET_NOCMOVE for move confirmation action. PL100_SET_CMOVE forces a later move. PL100_SET_NOCMOVE marks the move as already completed.

EDGUX100 Exit Routine Processing

EDGUX100 gets called at each of these points if DFSMSrmm does not already have the required information. For example, if the required information for the current data set and volume combination was provided in a previous call of the exit, EDGUX100 is not called again.

- At pre-ACS processing time for new allocations, a pointer to the ACERO is passed in PL100_ACEROPTR.
- At OPEN time in the address space of the program issuing the OPEN request. During OPEN processing the address of a copy of the JFCB is provided in PL100_JFCBPTR.

  EDGUX100 can also be called at CLOSE or EOV if the information that DFSMSrmm requires for processing is not available. For example, EDGUX100 can be called if DFSMSrmm is restarted while tape volumes are in use.
- At CLOSE and EOV time in the address space of the program processing the tape file. PL100_ITS_CLOSE is set and PL100_LABINFO provides information useful for creating labels.
- When DFSMSrmm updates a write to operator message defined by the EDGRMMxx parmlib MNTMSG command.

  You use the MNTMSG operands to identify the write to operator messages that you want DFSMSrmm to update with external volume serial number and pool information. Messages are processed for both specific and non-specific volume serial numbers. If the JES3 IATUX71 exit is used with the DFSMSrmm EDG3X71 exit, EDGUX100 is called during JES3 fetch and mount message processing.

  EDGUX100 can also be called from MSGDISP processing if the information that DFSMSrmm requires for processing is not available. For example, EDGUX100 can be called if DFSMSrmm is restarted while tape volumes are in use.

DFSMSrmm has not yet checked if the volume is defined in its control data set, if the volume will be rejected, or if the volume is subject to any other DFSMSrmm processing.

After the installation exit has been called, DFSMSrmm performs the following processing:

- The DFSMSrmm sample EDGUX100 installation exit performs no function when the supplied JFCB address, supplied ACERO address, and the supplied WTO address are zero.
- If the expiration date is updated by the exit, EDGUX100 updates the date in the copy of the JFCB for the current request. DFSMSrmm does not update the real JFCB control block.
- If a vital record specification management value is returned, DFSMSrmm records this value together with other details for the data set in the DFSMSrmm control data set, for use during inventory management.

- During pre-ACS processing if a pool or vital record specification management value is returned, DFSMSrmm sets the MSPOOL and MSPOLICY variables into the ACERO if the pre-ACS installation exit IGDACSXT has not already done so.
- If a specific pool name is returned and it meets the pool naming conventions, DFSMSrmm uses the value to update messages intercepted for MNTMSG processing, to update tape drive displays through MSGDISP processing and to perform pool validation of scratch volumes at OPEN time. If JES3 is used and IATUX71 is in use, the pool is also passed to JES3 for use in JES3 fetch and mount messages. If you request that DFSMSrmm prevents the tape drive cartridge loader from being indexed, DFSMSrmm resets the automatic cartridge load flag during MSGDISP processing. If the selected pool does not meet the naming conventions, DFSMSrmm uses the pool it has already selected.
- If the volume must be ignored, DFSMSrmm ensures that the current user is authorized to request that DFSMSrmm ignores this volume. A SAF request is used to check authorization:

```
RACROUTE REQUEST=AUTH,ENTITY=STGADMIN.EDG.IGNORE.TAPE.volser,
         ACCESS=value,LOG=ASIS
```

Figure 97. Checking Authorization to Ignore a Volume

  where:

  volser
  Is the current volume serial number of the mounted volume

  value
  Is either READ or UPDATE

  If the user is authorized, DFSMSrmm ignores all further activity for this volume until end-of-volume processing or until a data set on the volume is closed. This means that DFSMSrmm does not validate that the correct volume is mounted, does not record volume usage in its control data set and cannot provide any management functions for the volume based on the data about to be created.

  If authorization fails and DFSMSrmm is running in protect mode, DFSMSrmm rejects the volume. For non-specific mount requests, another volume is requested. For specific volume requests the OPEN request fails.

  If the resource does not exist, the request is treated as not authorized.

  If authorization fails and DFSMSrmm is running in record-only mode, DFSMSrmm ignores the volume and issues the information message, EDG4047I.

  If authorization fails and DFSMSrmm is running in warning mode, DFSMSrmm ignores the volume but issues error and warning messages.
- If a rack number is returned, DFSMSrmm uses this value as if it were a normal DFSMSrmm rack number for use in messages that are updated as defined by the parmlib MNTMSG definitions.
- DFSMSrmm validates the information you set in the parameter list as follows:

  PL100_VRS
  Must meet the MVS data set naming standards for a single data set qualifier.

  PL100_RACKNO
  For specific volume requests, this value must be uppercase, alphanumeric characters, or $, #, or @.

PL100_POOL
For non-specific volume requests the pool prefix must be uppercase, one to five alphanumeric characters ending in *.

PL100_LOCATION
If the location type is set to store or library, DFSMSrmm uses the EDGRMMxx LOCDEF definitions to validate the location. If the location name is not valid, DFSMSrmm treats the location name as a loan location.

- If you request no data set recording for a volume, DFSMSrmm updates the volume record during OPEN processing to identify that the volume does not record all data sets.
- If you specify the DFSMSrmm EDGRMMxx OPTION DISPDDNAME operand, DFSMSrmm uses the location, location type, and volume move confirmation values from the PL100 parameter list to update the volume record location and destination fields. If you request ″no confirm move″, DFSMSrmm sets the location, otherwise DFSMSrmm sets the destination for the volume. If the location type is a loan location, DFSMSrmm only records the loan location.
- If the EDGUX100 exit abnormally ends or if the exit detects an incorrect parameter list and sets return code 16, DFSMSrmm initiates an SDUMP and issues a WTOR EDG0303D which prompts the operator to reply RETRY, CANCEL, CONTINUE, or DISABLE.

  If the operator replies CANCEL, DFSMSrmm fails the current request, but processes all other requests. If the operator replies DISABLE, DFSMSrmm continues with the current request. All future requests are processed by DFSMSrmm without use of the installation exit. The installation exit is disabled. Tape processing continues. If the reply is CONTINUE, DFSMSrmm processes the current request ignoring the failure of the installation exit. All future requests are processed using the installation exit. If the reply is RETRY, DFSMSrmm retries the current request.

Assigning Expiration Dates

When a JFCB address is supplied, the sample EDGUX100 installation exit checks to see if an expiration date, rather than a retention period, is specified by the user. If an expiration date was specified:

- If the JCL expiration date is 98000, EDGUX100 clears the expiration date so that DFSMSrmm uses the DFSMSrmm parmlib default retention period to calculate the expiration date. This prevents DFSMSrmm from treating a special expiration date as an actual expiration date. If the exit parameter list indicates that the exit can request the volume is ignored, EDGUX100 requests that DFSMSrmm ignores the volume.
- If the JCL expiration date is 99000, the sample EDGUX100 installation exit clears the expiration date field, so that DFSMSrmm uses the DFSMSrmm parmlib default retention period to calculate an expiration date. This prevents DFSMSrmm from treating a special expiration date as an actual expiration date. If the exit parameter list indicates that the exit can specify a vital record specification management value, the sample EDGUX100 installation exit returns a vital record specification management value of D99000.
- Before checking for any other expiration date values, EDGUX100 checks to see if you want the expiration dates to be used as actual expiration dates or special dates. EDGUX100 checks for the existence of a dummy DD statement with the name NOTKEYD8.

  ```
  //NOTKEYD8 DD DUMMY
  ```

Code a NOTKEYD8 dummy DD statement to indicate that the date is an actual expiration date. If you do not code the NOTKEYD8 DD statement in the current job step or if it is not coded as a dummy DD statement, the expiration date is treated as a special date.

If you want to use a DD name other than NOTKEYD8, change the DD name that is coded in the sample EDGUX100 installation exit. Ensure that you specify a DD name padded to 8 characters with trailing blanks

The sample EDGUX100 installation exit does not perform any further special date processing. However, if you want to add checks for additional special dates you can do so.

Supplying a Scratch Pool Name

When the JFCB address, ACERO address, or the WTO address is supplied, and the EDGUX100 installation exit can supply a scratch pool name:

- If the supplied ACERO address is non-zero, the jobname and data set name are taken from the ACERO.
- If the supplied JFCB address is non-zero, the job name and data set name are extracted from system control blocks.
- If the supplied WTO address is non-zero, the job name and data set name are extracted from the WTO message text.

To use the EDGUX100 installation exit for pool selection, enter the job names and data set names into a table in the assembler source code as shown in Figure 98 on page 212.

DFSMSrmm scans a scratch pool table for the extracted job name and data set name to determine if this request requires a specific scratch pool. If a specific scratch pool is required, the exit requests that DFSMSrmm use the pool selected by the exit. If the cartridge loader is not to be used for the selected pool the exit requests that DFSMSrmm prevent the cartridge loader being indexed.

Specify the entries in the table in the order you want them to be matched by the exit. The exit scans the table until it finds an entry where both the job name and data set name masks match the current request. You can change the priority of matching by changing the order of the table entries.

```
POOLTAB  DS    0F                  start of pool table
*                  jobname        data set name
         DC    CL8'*       ',CL44'BACKUP*'
         DC    CL6'A02*'             pool name
         DC    AL1(PL100_SET_ACLOFF) do not use loader
*
         DC    CL8'STSGWD* ',CL44'*'
         DC    CL6'A*'               pool name
         DC    AL1(0)                use loader
*
         DC    CL8'STSG%%* ',CL44'STSG%%.BACKUP.*'
         DC    CL6'12*'              pool name
         DC    AL1(0)                use loader
*
         DC    CL8'STSGDPW ',CL44'DAVE.POOL1.DATA'
         DC    CL6'AB999*'           pool name
         DC    AL1(PL100_SET_ACLOFF) do not use loader
*
         DC    CL8'POOLEND'        end of pool table marker
```

Figure 98. Sample EDGUX100 Pool Selection Table

Each table entry consists of:

jobname
An 8-byte field that can contain up to 8 alphanumeric or national characters including % and *.
% to ignore a positional character in the job name.
* to ignore all remaining characters in the job name. A job name of * means that the entry applies to all jobs.

Examples of job names in the table are: STSGWD*, STSG%%*, STSGDPW.

data set name
A forty four byte field that can contain up to forty four characters, following MVS data set naming conventions, including % and *.
% to ignore a positional character in the data set name.
* to ignore all remaining characters in the data set name. A data set name of * means that the entry applies to all data sets.

The use of * is not the same as in the generic data set names supported by DFSMSrmm for vital records specifications and search data set masks. The * works like the *.** might in a generic data set name mask.

Examples of data sets in the table are: STSGWD*, STSG%%.BACKUP.*, DAVE.POOL1.DATA.

pool name
A 6-byte field that can contain up to five alphanumeric characters ending in *. If the pool name you specify does not match the pool naming conventions, DFSMSrmm ignores the exit selected pool and uses the DFSMSrmm selected pool.

If your exit selects a pool that does not match a VLPOOL prefix value, all volumes that are mounted are rejected.

Examples of pool names in the table are: A*, 12*, AB999*.

loader status
A 1-byte field that contains a flag indicating whether the tape drive cartridge loader is to be disabled for the named pool.

The sample EDGUX100 installation exit ORs this flag byte into the EDGUX100 parameter list PL100_FUNCTION field.

The valid values are either X'00' or X'01'. You can set the correct value using one of the following assembler statements:

```
DC   AL1(0)
DC   AL1(PL100_SET_ACLOFF)
```

You can use EDGUX100 exit selected pools for your non-system-managed volumes including volumes managed using BTLS. See "Using the EDGUX100 Installation Exit from Pre-ACS Processing" on page 204 for information about using the EDGUX100 exit to manage non-system-managed volumes using pre-ACS processing.

For system-managed volumes, use ACS routines to assign SMS constructs to new tape data sets at allocation time. If the exit selects a pool for a system-managed allocation it is ignored by DFSMSrmm during volume validation because DFSMSrmm does not perform pool validation for system managed volumes.

If the operator mounts a volume which is not from the pool the exit specifies, the volume is rejected and DFSMSrmm issues message EDG4021I.

```
EDG4021I VOLUME volser REJECTED. IT IS NOT IN AN ACCEPTABLE SCRATCH POOL
```

Using the System Name to Select a Scratch Pool

You can specify multiple scratch pool selection tables in your EDGUX100 installation exit. This allows you to select scratch pools based on the name of the running system.

The sample installation exit uses the SYSNAME value from the IEASYSxx parmlib member to determine the system name. This is the CVTSNAME field.

Figure 99 is an example of adding system names to the existing system name table in the EDGUX100 installation exit. You can add system names in any order. If you want to remove a system from the list, delete the entry or blank out the system name.

```
SYSTAB   DS    0F                  start of SYSTEM table
SYSCOUNT DC    A(SYSTABL/SYSTENTL) count of entries
SYSENT1  DS    0F                  DO NOT CHANGE THIS LINE
         DC    CL8'        ',A(PTBLSYS1)    Add the names of the
         DC    CL8'        ',A(PTBLSYS2)    systems you want to
         DC    CL8'W98MVS1 ',A(PTBLSYS3)    use into the
         DC    CL8'        ',A(PTBLSYS4)    prepared entries on
         DC    CL8'        ',A(PTBLSYS5)    the left. There is no
         DC    CL8'SYSA    ',A(PTBLSYS6)    need to change table
         DC    CL8'        ',A(PTBLSYS7)    names on the right.
         DC    CL8'        ',A(PTBLSYS8)
*    To add more system names to the table, just repeat the last
*    table entry, specify a new system name, and the name of
*    new pool table. For example:
*        DC    CL8'ANOTHER ',A(PTBLSYS9)
*    Then build the new table by copying how one of the existing
*    PTBLSYSx tables are defined.
SYSEND   DS    0F                  end of table
SYSTABL  EQU   SYSEND-SYSENT1      length of table
```

Figure 99. Sample EDGUX100 Installation Exit System Name Table

You can have a pool selection table for each system name that contains data set names, pool names, and automatic cartridge loader controls as shown in Figure 98 on page 212. If you do not specify any system names, or there is no match found in the system table for the current system, DFSMSrmm uses the default selection pool POOLTAB. Figure 100 is an example of a selection table for a specific system.

```
*****************************************************************
* POOL TABLE For 3rd System
*****************************************************************
PTBLSYS3 DS    0F                  start of pool table
*                  jobname        data set name
         DC    CL8'WOODMW* ',CL44'WOODMW.SYS3.*'
         DC    CL6'S03*'           pool name
         DC    AL1(PL100_SET_ACLOFF) bypass acl load flag
*
         DC    CL8'POOLEND'        end of pool table marker
```

Figure 100. Pool Selection Table for System 3

Using Storage Group for Manual Tape Library Pooling

The sample EDGUX100 exit is written to prevent the use of storage groups for manual tape library scratch pools. If you chose to use the EDGUX100 exit without making any modifications, pooling for manual tape library volumes is based on DFSMSrmm system-based pooling or on exit-selected pooling. To use the storage group assigned at allocation to make pooling decisions, you cannot use the sample EDGUX100 exit or you must modify the exit.

To modify the sample EDGUX100 exit, remove the code that overrides using storage group for pooling decisions by ensuring that parameters PL100_SET_IGNORE_SGNAME or PL100_SET_POOL are not set when the request is for a tape drive in a manual tape library.

Environment

To reactivate the exit you can either stop and restart the DFSMSrmm procedure once you have corrected any error in your exit, or you can use the F DFRMM,REFRESH EXITS operator command. See *z/OS DFSMSrmm Guide and Reference* for information.

Installing the EDGUX100 Routine

Perform the following actions to update or replace the exit.

1. Build and install an SMP/E USERMOD to apply the updated source code for the EDGUX100 installation exit. Include the necessary JCLIN statements to get the EDGUX100 load module added to the LINKLIB target library.

   You can apply the exit using an SMP/E USERMOD as shown in Figure 101 on page 215. Modify the FMID and PRE to reflect the release you are running.

   a. Allocate a user SAMPLIB data set. In Figure 101 on page 215 the user samplib data set is defined as MY.RMM.SRCLIB and allocated to DD card SRCLIB.

   b. Copy the shipped EDGUX100 source from SAMPLIB to the user SAMPLIB and modify as needed for your installation.

   c. SMP/E RECEIVE the usermod.

   d. SMP/E APPLY the usermod. Make sure that a DD card exists for the user SAMPLIB in the APPLY job or as a DDDEF to SMP/E in the target zone.

After performing these steps, the modified version of the EDGUX100 exit resides in both the user SAMPLIB and SYS1.SAMPLIB. IBM's original copy is only in the distribution libraries at this point. If you accept the usermod, only the modified version of the exit exists. The SMP/E target zone reflects RMID indicators of VMRMM01 for all of the following records:

```
SAMP EDGUX100 RMID=VMRMM01 SYSLIB=SAMPLIB
SRC  EDGUX100 RMID=VMRMM01 SYSLIB=SAMPLIB
MOD  EDGUX100 RMID=VMRMM01 LMOD=EDGUX100
LMOD EDGUX100              SYSLIB=LINKLIB
```

The RMID of VMRMM01 for the SAMP record prevents IBM service from being installed. This results in an ID search and notification to you that IBM is the servicing exit.

```
//RMMSTUFF  JOB  ,'SLIP IT IN',MSGCLASS=H,MSGLEVEL=(1,1)
//STEP1     EXEC SMPEMVS,REGION=6120K
//SYSIN     DD   *
 SET BDY(GLOBAL) .
 RECEIVE .
/*
//SMPPTFIN  DD   DATA,DLM=##
++USERMOD (VMRMM01) REWORK(1997082) .
++VER (Z038) FMID(HDZ11D0) .
++JCLIN .
//EDGUX100  EXEC PGM=IEWL,PARM='LET,NCAL,RENT,REUS,REFR,LIST,XREF'
//SYSLMOD   DD   DISP=SHR,DSN=SYS1.LINKLIB
//SRCLIB    DD   DISP=SHR,DSN=MY.RMM.SRCLIB
//AEDGMOD1  DD   DISP=SHR,DSN=SYS1.AEDGMOD1
//SYSPRINT  DD   SYSOUT=*
//SYSLIN    DD   *
  INCLUDE AEDGMOD1(EDGUX100)
  ENTRY   EDGUX100
  NAME    EDGUX100(R)
++SRC(EDGUX100) TXLIB(SRCLIB) DISTLIB(ASAMPLIB) .
++SAMP(EDGUX100) TXLIB(SRCLIB) DISTLIB(ASAMPLIB) .
##
/*
```

Figure 101. Building an SMP/E USERMOD to Apply the Updated EDGUX100 Exit

2. Copy the new exit load module into the LNKLST library.
3. Refresh LLA.
4. Refresh the exit by issuing:

   ```
   F DFRMM,REFRESH EXITS
   ```

   If DFSMSrmm is running in a shared environment, you must repeat this step on each system.

The EDGUX100 installation exit is loaded by DFSMSrmm each time DFSMSrmm is started and stays loaded until DFSMSrmm is stopped. It can be refreshed at any time by using the operator MODIFY command to refresh exits:

```
F DFRMM,REFRESH EXITS
```

To remove EDGUX100 from the system, you can delete the EDGUX100 load module from the LNKLIST libraries, and refresh LLA before issuing the operator MODIFY command.

If DFSMSrmm is running in a shared environment, you must repeat this step on each system.

Writing the EDGUX100 Routine

EDGUX100 runs in SYSTEM KEY 0 or 5 AMODE(31) RMODE(ANY) in the user's address space. KEY 0 is used when a WTO address or an ACERO address is provided, and KEY 5 is used when a JFCB address is provided. It is loaded using the MVS LOAD macro, and can be contained in any APF authorized LNKLST library.

You can write your installation to issue commands or call other programs to get external inventories updated.

You can also code the exit to issue a WTOR if required. Be careful not to issue messages that are contained in the MNTMSG table or you could cause the EDGUX100 installation exit to be called recursively.

Registers on Entry to the EDGUX100 Exit Routine

Register	Contents
0	Not applicable
1	Address of a parameter list mapped by the macro EDGPL100
2-12	Not applicable
13	Address of register save area
14	Caller's return address
15	Address of EDGUX100 entry point

EDGUX100 Parameter List

All communication is done using the parameter list. The parameter list is mapped by the macro EDGPL100 as shown in "Installation Exit Mapping Macro: EDGPL100" on page 372.

The parameter list input values are:

PL100_VALID
This field defines the functions you can request during this call of the installation exit.

PL100_CAN_IGNORE
If set to B'1' you can request that DFSMSrmm ignores the volume.

PL100_CAN_VRS
If set to B'1' you can provide a vital record specification management value for DFSMSrmm to use for this data set.

PL100_CAN_RACKNO
If set to B'1' you can provide an external volume serial number or rack number for DFSMSrmm to use for this volume in any WTO messages DFSMSrmm updates.

PL100_CAN_IGNORE_FILE2_TON
If set to B'1' you can request that DFSMSrmm record the data set details only for the first file on a tape volume.

PL100_CAN_POOL
If set to B'1' you can provide a specific pool name for DFSMSrmm to use for this volume in any WTO messages DFSMSrmm updates. Also the pool name is used to validate that a correct scratch volume is mounted for a request.

PL100_ITS_CLOSE
If set to B'1', this indicates that DFSMSrmm called EDGUX100 because a tape data set was closed or an end-of-volume condition occurred.

PL100_REQ_VOLSER
This field contains one of: PRIVAT, SCRTCH or a volume serial number. For a non-specific request PL100_REQ_VOLSER can contain either PRIVAT or SCRTCH. For a specific request PL100_REQ_VOLSER contains the actual volume serial number requested.

PL100_MOUNT_VOLSER
This field contains the volume serial number of the volume mounted to satisfy this request. This volume serial number is only available when a data set on the volume is opened or closed.

PL100_WTOPTR
This field contains the address of the WTO message that has been intercepted by MNTMSG processing. The address is zero during OPEN processing. See the PL100_WTOPTR field for information on the operator message being updated.

PL100_JFCBPTR
This field can contain the address of the JFCB copy or is set to zero. You can use it to locate the expiration date field JFCBXPDT. You can determine if the user specified an expiration date rather than a retention period by checking the JFCB for the JFCBEXP flag. If the exit is called during OPEN processing, the JFCB address is provided. During MNTMSG processing the JFCB address is set to zero and no JFCB is available.

PL100_POOL
When PL100_JFCBPTR is zero and PL100_CAN_POOL is set to B'1', this field contains the scratch pool that DFSMSrmm has already determined should be used for this request. It is determined using the VLPOOL definitions that you specify in the DFSMSrmm parmlib member. If you do not provide a replacement value and set the PL100_SET_POOL flag, this is the pool that DFSMSrmm uses.

PL100_LABINFO
When PL100_ITS_CLOSE is set to B'1', this field points to a data area mapped by PL100_LABDS. The data area contains information about the volume and file being processed.

PL100_ACCODE
This field contains either the value of the JCL specified ACCODE parameter or blanks if the ACCODE is specified in the reduced form 'ACCODE=' or if the JCL does not contain ACCODE. The field can be 1 to eight characters as described in *z/OS MVS JCL Reference*. The first character is the ISO/ANSI accessibility code. The remaining characters can be any characters you choose. If the ACCODE value specifies a special value, then your EDGUX100 exit can process the ACCODE value rather than the special date in the EXPDT keyword if it exists.

PL100_INFO
This field defines additional information.

PL100_INFO_IGNORE
If set to B'1' The volume is to be ignored by the EDGUX100 installation exit.

PL100_INFO_NOTRMM
If set to B'1', the volume is not defined to DFSMSrmm. This is only set at CLOSE or EOV time.

PL100_INFO_DISPDD
If set to B'1', a disposition file was found and has been processed for this DD name.

PL100_INFO_CMOVE
If set to B'1', a confirm must be performed and the location requested is set as the volume's destination, not the location.

PL100_INFO_USERDATA
If set to B'1', userdata was provided from the disposition file. The user data has been included in the default label created by DFSMSrmm processing.

PL100_INFO_MTL
If set to B'1', indicates that the allocated tape drive is an manual tape library tape drive and a storage group has been set by SMS ACS processing. DFSMSrmm uses the storage group name as the specific scratch pool unless you select a specific scratch pool or request that DFSMSrmm ignore the storage group name.

PL100_ACEROPTR
This field contains the address of the ACERO system control block during pre-ACS processing.

PL100_LAB_USERDATA
This field contains the user data from the disposition processing file for use in sticky labels.

PL100_LABPTR
This field contains the address of the sticky label prepared by DFSMSrmm.

PL100_LOCATION
This field contains the name of the location specified in the disposition file.

PL100_LOCTYPE
This field contains the type of the location.

The parameter list can be updated as follows:

PL100_FUNCTION
Use this field to request functions of DFSMSrmm

PL100_SET_IGNORE
Set the PL100_SET_IGNORE bit to indicate that you want this volume ignored until the current file reaches end-of-volume or is closed.

PL100_SET_IGNORE_FILE2_TON
Set the PL100_SET_IGNORE_FILE2_TON bit to indicate that DFSMSrmm is only to record data set details for the first file on the tape volume.

PL100_SET_POOL
Set the PL100_SET_POOL bit to indicate that you want to use a specific pool for the current non-specific volume request. When you set PL100_SET_POOL and provide a pool prefix for a tape drive in a manual tape library, DFSMSrmm does not use the storage group assigned by SMS ACS processing.

PL100_SET_ACLOFF
Set the PL100_SET_ACLOFF bit to indicate that you want DFSMSrmm to disable the cartridge loader for this request.

The other functions you can request are determined by the presence of data in the output fields.

PL100_JFCBPTR

If a JFCB address was provided as input, set the JFCB expiration date field to the new expiration date value you want DFSMSrmm to use for this data set.

You can update the JFCB expiration date even if you do not provide a vital record specification management value. We recommend that you zero the expiration date field in the JFCB copy to allow DFSMSrmm to calculate a default expiration date.

Remember that if you do not ask for the volume to be ignored, the exit can be called multiple times for each volume.

PL100_VRS

Set the DFSMSrmm vital record specification management value you have selected. The values you use in this field should correspond to the RMM ADDVRS DSNAME subcommands you have used. The vital record specification management value you specify is only used during inventory management vital records processing once it has been established that use of the data set name has not produced a match.

Only update this field if the PL100_CAN_VRS flag is set, as it is only when this flag is set that DFSMSrmm makes use of the value you specify. DFSMSrmm records the vital record specification management value you specify in the control data set when:

- A new data set is created
- An existing data set is rewritten with DISP=OLD
- A data set not yet recorded by DFSMSrmm is read

When an existing data set is extended, and the data set already has a vital record specification management value, DFSMSrmm ignores the new value you specify and propagates the existing vital record specification management value.

In all other cases, the vital record specification management value you specify is not used by DFSMSrmm.

PL100_RACKNO

You can provide a 6 character value for DFSMSrmm to use as the rack number or external volser for adding to the mount messages that DFSMSrmm intercepts and updates. Provide this value when requesting that DFSMSrmm ignores the volume. This helps your operators retrieve the correct volume.

Only update this field if the PL100_CAN_RACKNO flag is set, as it is only when this flag is set that DFSMSrmm makes use of the value you specify.

PL100_POOL

You can use this field to provide a specific pool name to be used with a non-specific output request.

Provide a 6 character pool identifier for DFSMSrmm to use for adding to the mount messages and tape drive display requests that DFSMSrmm intercepts and updates and for use during volume validation. Provide this value when requesting that DFSMSrmm use a specific scratch pool. This helps your operators retrieve the correct volume.

Only update this field if the PL100_CAN_POOL flag is set. Also set PL100_SET_POOL to B'1', as it is only when this flag is set that DFSMSrmm makes use of the value you specify.

If your exit selects a pool that does not meet the pool naming conventions, DFSMSrmm uses the DFSMSrmm selected pool, and ignores the setting of the PL100_SET_ACLOFF flag.

If your exit selects a pool that does not match a VLPOOL prefix value, all volumes that are mounted are rejected.

PL100_LOCATION
The value is set by DFSMSrmm depending on the keyword LOC=, or OUT= used in the disposition control file. You can change the value during EDGUX100 processing and it will be validated by DFSMSrmm on return from the exit.

PL100_FUNCTION2
You can use this field to change the confirm move processing decision that DFSMSrmm has already made. Based on this field, DFSMSrmm sets the location as the destination or the current location. When set as a destination, you must complete the move of the volume by confirming the move.

PL100_SET_IGNORE_SGNAME
Set this field to B'1' when you want to use DFSMSrmm system-based pooling instead of the storage group name set by SMS ACS processing when the tape drive is in a manual tape library.

Registers on Return from the EDGUX100 Exit Routine

Register	Contents
0	Not applicable
1-14	Restored to contents at entry
15	Return code

EDGUX100 Installation Exit Return Codes

Table 40 shows the contents of register 15 upon return from the exit.

Table 40. EDGUX100 Installation Exit Return Codes

Return Code	Description
0	Processing was successful. The parameter list might have been updated by the exit.
16	The exit determined that the parameter list passed to it did not conform to the correct specifications.

Using the DFSMSrmm EDGUX200 Installation Exit

Use the DFSMSrmm EDGUX200 installation exit to:
- Return a volume to scratch status in an external inventory
- Prevent a volume from returning to scratch status
- Request that DFSMSrmm ignores data set information recorded for a volume

EDGUX200 Exit Routine Processing

The DFSMSrmm sample EDGUX200 installation exit:

- Validates the parameter list
- Returns immediately for a system-managed volume

The EDGUX200 installation exit is called during inventory management expiration processing in the DFSMSrmm started procedure address space. It is called by DFSMSrmm each time a volume is identified for the return to scratch action. The volume has not yet been returned to scratch in either the TCDB or the DFSMSrmm control data set.

- If the exit requests that the volume is not returned to scratch status, DFSMSrmm leaves the volume in pending release status.
- If the exit requests that DFSMSrmm ignores the data set name information, all data set information for the volume is removed from the DFSMSrmm control data set and the volume is returned to scratch status.

If the exit abnormally ends or if the exit detects an incorrect parameter list and sets return code 16, DFSMSrmm initiates an SDUMP and issues a WTOR EDG0303D which prompts the operator to reply RETRY, CANCEL, CONTINUE, or DISABLE. If the operator replies CANCEL, the volume is not returned to scratch. If the operator replies CONTINUE or DISABLE, the volume is returned to scratch and any functions that were set in the parameter list by the exit are ignored.

Environment

To reactivate the exit you can either stop and restart the DFSMSrmm procedure once you have corrected any error in your exit, or you can use the `F DFRMM,REFRESH EXITS` operator command. See *z/OS DFSMSrmm Guide and Reference* for information.

Installing the EDGUX200 Exit Routine

Perform the following actions to update or replace the exit.

1. Build and install an SMP/E USERMOD to apply the updated source code for the EDGUX200 installation exit.

   Include the necessary JCLIN statements to get the EDGUX200 load module added to the LINKLIB target library.

   You can apply the exit using an SMP/E USERMOD as shown in Figure 102 on page 222. Modify the FMID and PRE to reflect the release you are running.

   a. Allocate a user SAMPLIB data set. In Figure 102 on page 222 the user SAMPLIB data set is defined as MY.RMM.SRCLIB and allocated to DD card SRCLIB.
   b. Copy the shipped EDGUX200 source from SAMPLIB to the user SAMPLIB and modify as needed for your installation.
   c. SMP/E RECEIVE the usermod.
   d. SMP/E APPLY the usermod. Make sure that a DD card exists for the user SAMPLIB in the APPLY job or as a DDDEF to SMP/E in the target zone.

   After performing these steps, the modified version of the EDGUX200 exit resides in both the user SAMPLIB and SYS1.SAMPLIB. IBM's original copy is only in the distribution libraries at this point. If you accept the usermod, only the modified version of the exit exists. The SMP/E target zone reflects RMID indicators of VMRMM02 for all of the following records:

```
SAMP EDGUX200 RMID=VMRMM02 SYSLIB=SAMPLIB
SRC  EDGUX200 RMID=VMRMM02 SYSLIB=SAMPLIB
MOD  EDGUX200 RMID=VMRMM02 LMOD=EDGUX200
LMOD EDGUX200              SYSLIB=LINKLIB
```

The RMID of VMRMM02 for the SAMP record prevents IBM service from being installed. This results in an ID search and notification to you that IBM is the servicing exit.

```
//RMMSTUFF  JOB  ,'SLIP IT IN',MSGCLASS=H,MSGLEVEL=(1,1)
//STEP1     EXEC SMPEMVS,REGION=6120K
//SYSIN     DD   *
 SET BDY(GLOBAL) .
 RECEIVE .
/*
//SMPPTFIN  DD   DATA,DLM=##
++USERMOD (VMRMM02) REWORK(1997082) .
++VER (Z038) FMID(HDZ11D0) .
++JCLIN .
//EDGUX200  EXEC PGM=IEWL,PARM='LET,NCAL,RENT,REUS,REFR,LIST,XREF'
//SYSLMOD   DD   DISP=SHR,DSN=SYS1.LINKLIB
//SRCLIB    DD   DISP=SHR,DSN=MY.RMM.SRCLIB
//AEDGMOD1  DD   DISP=SHR,DSN=SYS1.AEDGMOD1
//SYSPRINT  DD   SYSOUT=*
//SYSLIN    DD   *
  INCLUDE AEDGMOD1(EDGUX200)
  ENTRY   EDGUX200
  NAME    EDGUX200(R)
++SRC(EDGUX200) TXLIB(SRCLIB) DISTLIB(ASAMPLIB) .
++SAMP(EDGUX200) TXLIB(SRCLIB) DISTLIB(ASAMPLIB) .
##
/*
```

Figure 102. Building an SMP/E USERMOD to Apply the Updated EDGUX200 Exit

2. Copy the new exit load module into the LNKLST library.
3. Refresh LLA.
4. Refresh the exit by issuing:

   ```
   F DFRMM,REFRESH EXITS
   ```

   If DFSMSrmm is running in a shared environment, you must repeat this step on each system.

The EDGUX200 installation exit is loaded by DFSMSrmm each time DFSMSrmm is started and stays loaded until DFSMSrmm is stopped. It can be refreshed at any time by using the operator MODIFY command to refresh exits:

```
F DFRMM,REFRESH EXITS
```

To remove EDGUX200 from the system, you can delete the EDGUX200 load module from the LNKLIST libraries, and refresh LLA before issuing the operator MODIFY command.

If DFSMSrmm is running in a shared environment, you must repeat this step on each system.

Writing the EDGUX200 Exit Routine

EDGUX200 runs in PROBLEM KEY, SUPERVISOR STATE AMODE(31) RMODE(ANY) in the address space of the DFSMSrmm started procedure. It is loaded using the MVS LOAD macro, and can be contained in any APF authorized LNKLST library.

You can write your installation exit to issue commands or call other programs to get external inventories updated.

Registers on Entry to the EDGUX200 Exit Routine

Register	Contents
0	Not applicable
1	Address of a parameter list mapped by the macro EDGPL200
2-12	Not applicable
13	Address of register save area
14	Caller's return address
15	Address of EDGUX200 entry point

EDGUX200 Parameter List

All communication is done using the parameter lists fields. The parameter list is mapped by the macro EDGPL200 as shown in "Installation Exit Mapping Macro: EDGPL200" on page 377.

The parameter list input values are:

PL200_VALID
This field defines which functions you can request during this call of the installation exit.

PL200_CAN_SCRTCH
If set to B'1' DFSMSrmm is returning the volume to scratch and you can request DFSMSrmm not to do this or can request DFSMSrmm to ignore data set name information for the volume.

PL200_VOLSER
This field contains the volume serial number of the volume being returned to scratch.

PL200_RACK_NUMBER
This field contains the rack number of the volume being returned to scratch.

PL200_MEDIA_NAME
This field contains the media name used for the volume being returned to scratch.

PL200_LOCATION
This field contains the location name used for the volume being returned to scratch. It can be any value that is valid for volumes in the installation media library, but can never be a storage location name.

PL200_DSNAME
This field contains the name of the first data set on the volume. There might be other data sets on the volume, but this information is not available to the exit.

PL200_VOLUME_FLAGS
This flag byte is used to give you information about the volume.

PL200_SMS_VOL
If set to B'1' this volume is a system-managed volume. For system-managed volumes DFSMSrmm dynamically updates the TCDB so you do not need to.

The parameter list can be updated as follows:

PL200_FUNCTION
This field describes functions that can be updated.

PL200_SET_NOSCRTCH
Set the PL200_SET_NOSCRTCH bit if you do not want DFSMSrmm to return the volume to scratch status at this time. You can control return to scratch processing each time inventory management expiration processing is run.

PL200_SET_IGNORE_DSN
Set the PL200_SET_IGNORE_DSN bit if you do not want DFSMSrmm to use the data set information for this volume. Setting this flag allows you to control the validation that DFSMSrmm performs at OPEN time. If DFSMSrmm cannot use the data set name information it cannot ensure that the volume has not changed since it was last used. DFSMSrmm will still use the internal volume label for validation.

Registers on Return from the EDGUX200 Exit Routine

Register	Contents
0	Not applicable
1-14	Restored to contents at entry
15	Return code

EDGUX200 Installation Exit Return Codes

Table 41 shows the contents of register 15 upon return from the exit.

Table 41. EDGUX200 Installation Exit Return Codes

Return Code	Description
0	Processing was successful. The parameter list might have been updated by the exit.
16	The exit determined that the parameter list passed to it did not conform to the correct specifications.

Chapter 11. Running DFSMSrmm with DFSMShsm

DFSMSrmm can provide enhanced management functions for the tape volumes that DFSMShsm uses for each of its tape functions. The way the two products work together depends on how you are using each of them in your installation. Run DFSMSrmm with DFSMShsm to enhance the management of the volumes DFSMShsm uses. For example, DFSMSrmm can manage the movement of tapes that must be sent out of the library for disaster recovery. Using DFSMSrmm and DFSMShsm together, you can use the scratch tape pool rather than a DFSMShsm tape pool.

DFSMSrmm provides the DFSMSrmm EDGTVEXT and EDGDFHSM programming interfaces for use by products like DFSMShsm and Tivoli Storage Manager for using DFSMSrmm tape management. DFSMSrmm treats DFSMShsm like any other user and retains volumes based on retention period and vital record specifications. DFSMShsm automatically calls EDGTVEXT so you no longer need to use ARCTVEXT to communicate with DFSMSrmm. A benefit of this interaction is that DFSMSrmm can prevent DFSMShsm from overwriting its own control data set backup, automatic dump, ABARS, and copies of backup or migration tapes. Although DFSMShsm checks its own migration and backup tapes, DFSMSrmm checks them as well.. The DFSMSrmm EDGTVEXT and EDGDFHSM programming interfaces support products that require DFSMSrmm to maintain the correct volume status. For more information on these programming interfaces, see “Managing DFSMShsm Tapes: EDGDFHSM” on page 178 and “Releasing Tapes: EDGTVEXT” on page 177.

Authorizing DFSMShsm to DFSMSrmm Resources

Before you can use DFSMSrmm with DFSMShsm, you are required to authorize DFSMShsm to STGADMIN.EDG.MASTER, STGADMIN.EDG.OWNER.user, and STGADMIN.EDG.RELEASE.

If you have multiple DFSMShsm USER IDs, for example in a multi-system or multi-host environment, and any DFSMShsm ID can create tapes or return tapes to scratch status or return tapes to the DFSMShsm tape pool, you must authorize each DFSMShsm USER ID. Define STGADMIN.EDG.OWNER.hsmid for each DFSMShsm USER ID and give the other DFSMShsm USER IDs UPDATE access to it.

See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for information about authorizing resources.

Table 42 shows the authorization required to use scratch tapes with DFSMShsm.

Table 42. Authorization Required to Use Scratch Tapes with DFSMShsm

Resource	Access Required
STGADMIN.EDG.RELEASE	READ
STGADMIN.EDG.MASTER	READ
STGADMIN.EDG.OWNER.hsmid	UPDATE

© Copyright IBM Corp. 1992, 2001

Table 43 shows the authorization required to use DFSMShsm with a DFSMShsm-managed scratch tape pool.

Table 43. Authorization Required to Use DFSMShsm with a DFSMShsm Scratch Pool

Resource	Access Required
STGADMIN.EDG.MASTER	UPDATE
STGADMIN.EDG.OWNER.hsmid	UPDATE

Authorizing ABARS to DFSMSrmm Resources

To use DFSMSrmm with DFSMShsm ABARS, you must assign ABARS IDs the correct levels of authorization to STGADMIN.EDG.MASTER, STGADMIN.EDG.OWNER.user, and STGADMIN.EDG.RELEASE.

If you have multiple ABARS USER IDs, for example in a multi-system environment, and any ABARS ID can return tapes to scratch status, you must authorize each ABARS USER ID. Define STGADMIN.EDG.OWNER.abarsid for each ABARS USER ID and give the other ABARS USER IDs UPDATE access to it. This allows one ABARS ID to release the tapes initially obtained from scratch by the other ABARS ID.

See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for information about authorizing resources.

Table 44 shows the authorization required to use DFSMSrmm with ABARS.

Table 44. Authorization Required to Use DFSMSrmm with ABARS

Resource	Access Required
STGADMIN.EDG.RELEASE	READ
STGADMIN.EDG.MASTER	READ
STGADMIN.EDG.OWNER.abarsid	UPDATE

Setting DFSMSrmm Options When Using DFSMShsm

You use the DFSMSrmm parmlib EDGRMMxx to specify the installation options for DFSMSrmm as described in “Defining System Options: OPTION” on page 122. If you are using expiration dates to manage tapes, you should consider the values you specify for the parmlib OPTION command MAXRETPD operand and the VLPOOL command EXPDTCHECK operand.

- The MAXRETPD operand specifies the maximum retention period that a user can request for data sets on volumes and is described in “Defining System Options: OPTION” on page 122.
- The TVEXTPURGE operand specifies how you want to handle the release of DFSMShsm tape volumes and is described in “Defining System Options: OPTION” on page 122.
- The VLPOOL command EXPDTCHECK operand described in “Defining Pools: VLPOOL” on page 148 tells DFSMSrmm how to manage a volume based on the expiration date field in the volume label. See “A Pooling Example” on page 66 for information about setting up pools.

When DFSMShsm sets 99365 as the expiration date to manage its tapes, 99365 means permanent retention or to never expire. If you choose to use DFSMShsm

expiration date protected tape volumes, DFSMShsm sets the date 99365 to prevent DFSMSrmm from considering the volumes for release at any time. You must specify the MAXRETPD(NOLIMIT) operand to ensure that DFSMSrmm honors the 99365 date.

You also use the DFSMSrmm parmlib MAXRETPD operand value to reduce the expiration date for all volumes including DFSMShsm volumes. If you want to reduce the 99365 permanent retention expiration date, specify the MAXRETPD with a value between 0 and 9999 days. We recommend using DFSMSrmm vital record specifications instead of using the 99365 permanent retention date to retain DFSMShsm volumes. See “Defining Vital Record Specifications to Manage DFSMShsm Tapes” on page 229 for information on setting up vital record specifications.

If you use expiration dates see “Retaining DFSMShsm Tapes Using Expiration Dates” on page 228 for details on how DFSMSrmm provides facilities to avoid reinitializing tapes before reuse or having the operator reply to IEC507D messages.

Setting DFSMShsm Options When Using DFSMSrmm

As DFSMShsm uses a tape volume, DFSMSrmm records information about data sets and multivolume data sets at OPEN time. DFSMSrmm can use this information to manage the volumes based on the DFSMSrmm policies you define.

DFSMShsm uses the DCB Open/EOV volume security and verification exit to ensure that an acceptable volume is mounted for DFSMShsm’s use. DFSMShsm uses this exit to reject unacceptable volumes. For example, DFSMShsm rejects volumes already in use by DFSMShsm and volumes not authorized for use by DFSMShsm. DFSMSrmm records information only for those volumes not rejected by DFSMShsm.

DFSMSrmm provides facilities so that DFSMShsm can tell DFSMSrmm when it no longer requires a tape volume or when a tape volume changes status. The benefit is that DFSMShsm cannot mistakenly overwrite one of its own tape volumes if an operator mounts a tape volume in response to a request for a non-specific tape volume.

Setting DFSMShsm System Options

The DFSMShsm system options that relate to using a tape management system with global or private scratch pools are shown in Figure 103:

```
SETSYS EXITON(ARCTVEXT)/EXITOFF(ARCTVEXT) -
       SELECTVOLUME -
       TAPEDELETION -
       TAPESECURITY -
       PARTIALTAPE
```

Figure 103. DFSMShsm System Options

Setting DFSMShsm Dump Definitions

Dump definitions are shown in Figure 104 on page 228:

```
DEFINE DUMPCLASS(class -
       AUTOREUSE -
       TAPEEXPIRATIONDATE(date) -
       RETENTIONPERIOD(day))
```

Figure 104. DFSMShsm Dump Definitions

DFSMSrmm Support for DFSMShsm Naming Conventions

DFSMSrmm supports all DFSMShsm options and any of the naming conventions for DFSMShsm tape data sets except for password security on tape volumes. See “Recommendations” on page 241 for information about the DFSMShsm options to use with DFSMSrmm.

Beginning in Version 2 Release 6 of DFHSM, the format of DFHSM tape data set names was changed to work easier with tape media managers. You can use the new naming conventions to enable DFSMSrmm to provide additional tape management functions. See “Using Old Data Set Naming Conventions to Retain and Move DFSMShsm Tapes” on page 238 for examples of specifying names using the old naming convention.

DFSMSrmm Support for Retention and Pooling

With DFSMShsm, you can use DFSMSrmm system based scratch tape pools, exit selected scratch pools, or DFSMShsm-managed tape pools. We recommend that you use a DFSMSrmm scratch pool and use the DFSMShsm-managed pool only when necessary. For example, use the DFSMShsm-managed pool if you want to keep DFSMShsm-managed pools for Enhanced Capacity Cartridge System Tapes, as DFSMShsm fully uses a tape’s capacity.

You must let DFSMShsm decide whether a tape volume contains valid data and whether it should return to the DFSMSrmm scratch pool or DFSMShsm-managed tape pool.

Define vital record specifications to retain tape volumes until DFSMShsm finishes with them. DFSMSrmm uses the retention period determined by the vital record specification to extend any expiration date or retention period previously set for the volume. Additionally, you can use vital record specifications to identify volumes that should be moved out of the installation media library for safe keeping, or moved from an automated to manual library.For DFSMShsm-managed tapes, you do not have to respond to the IEC507D messages that are issued for expiration data protected tapes because DFSMShsm can override expiration for its own tapes. If you choose to use DFSMShsm expiration date protected tape volumes, DFSMShsm sets the expiration date 99365 which means permanent retention to prevent DFSMSrmm from considering the volumes for release at any time.

Retaining DFSMShsm Tapes Using Expiration Dates

To use DFSMShsm expiration date protection, specify the DFSMShsm startup option as shown in Figure 105:

```
SETSYS TAPESECURITY(EXPIRATION)
```

Figure 105. Specifying the DFSMShsm Startup Option

If you use a system scratch tape pool for DFSMShsm tapes, you need a way to manage tapes protected with expiration dates set by DFSMShsm. To help you

manage this situation, DFSMSrmm lets you automate the responses to expiration date protection messages for scratch pool tape volumes. Use the parmlib member VLPOOL command to setup this automation. Set the VLPOOL EXPDTCHECK operand to EXPDTCHECK(N) as described in “Defining Pools: VLPOOL” on page 148. DFSMSrmm automatically lets your users reuse the volumes in the pool without operator intervention and without creating data integrity exposures.

If you use a DFSMShsm-managed tape pool, DFSMShsm validates and overrides expiration dates on its emptied, previously used tapes.

Defining Vital Record Specifications to Manage DFSMShsm Tapes

Movement and retention policies are defined using vital record specifications by specifying data set names or volume serial numbers. To define vital record specifications, use the RMM ADDVRS subcommand.See *z/OS DFSMSrmm Guide and Reference* for information about the RMM ADDVRS subcommand and the operands you can specify.

When specifying the RMM ADDVRS command operands, it might be helpful to think about the operands in three categories.

- Operands to define retention policies including COUNT and CYCLES used in the following examples
- Operands to define movement policies including DELAY, LOCATION, and STORENUMBER used in the following examples
- Operands to manage the vital record specification itself including DELETEDATE and OWNER which are defaults in the RMM ADDVRS subcommand
  - DELETEDATE(1999/365) specifies the date when the vital record specification no longer applies. The default value is 1999/365 which means the vital record specification is permanent. It can only be manually deleted if it is no longer appropriate.
  - OWNER(*owner*) specifies the user ID that owns the vital record specification.

As shown in the examples that follow, you can specify data set name masks in vital record specifications to manage migration, backup, dumps, TAPECOPY, DUPLEX tape feature, tapes written by ABARS, ABARS accompany tapes, and control data set version backups. You can tailor the examples to define policies for your DFSMShsm tapes. As you gain more experience defining vital record specifications, you will see that there might be several ways to define the retention and movement policies you desire.

The examples use the current DFSMShsm data set naming formats. Some old name formats were in use prior to APAR OY20664. APAR OY20664 required you to use PATCH commands to use the new format. The new format is standard in DFSMShsm. If you have occurrences of the old naming formats, you might need to define vital record specifications using both naming formats. Delete the vital record specifications with the old naming format once the old names no longer exist. See “Using Old Data Set Naming Conventions to Retain and Move DFSMShsm Tapes” on page 238 for examples of specifying names using the old naming convention. See the *z/OS DFSMShsm Implementation and Customization Guide* for current DFSMShsm data set naming formats.

Retaining All DFSMShsm Tapes

You can retain all DFSMShsm tapes that require no movement, with the exception of tapes written by ABARS, as shown in Figure 106 and Figure 107. See “Retaining and Moving Tapes Written by ABARS” on page 236 and “Retaining and Moving ABARS Accompany Tapes” on page 237 for examples for moving and retaining ABARS tapes.

```
RMM ADDVRS DSNAME('mprefix.**') COUNT(99999) CYCLES
RMM ADDVRS DSNAME('bprefix.**') COUNT(99999) CYCLES
RMM ADDVRS DSNAME('authid.**') COUNT(99999) CYCLES
```

Figure 106. Retaining DFSMShsm Tapes Requiring No Movement

DSNAME('*mprefix*.')**
Specifies the DFSMShsm-defined migrated data set prefix.

DSNAME('*bprefix*.')**
Specifies the DFSMShsm-defined backup and dump data set prefix.

DSNAME('*authid*.')**
Specifies the DFSMShsm prefix used for control data set backups.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Open Data Sets

You can define vital record specifications to control the retention of data sets that might have been left open by a system failure or that might be open during DFSMSrmm inventory management. Using the OPEN or ABEND data set name masks in a vital record specification allows you to you define specific policies for these data sets so that they are not retained like normal data sets.

We recommend that you specify the JOBNAME operand with the DFSMShsm and ABARS procedure names in the vital record specifications that you define to manage open data sets. This ensures that DFSMShsm and ABARS volumes are always retained permanently under DFSMSrmm until DFSMShsm releases them.

```
RMM ADDVRS DSNAME('ABEND') JOBNAME(hsm_proc) COUNT(99999) CYCLES
RMM ADDVRS DSNAME('ABEND') JOBNAME(abars_proc) COUNT(99999) CYCLES
RMM ADDVRS DSNAME('OPEN') JOBNAME(hsm_proc) COUNT(99999) CYCLES
RMM ADDVRS DSNAME('OPEN') JOBNAME(abars_proc) COUNT(99999) CYCLES
```

Figure 107. Retaining DFSMShsm Tapes with the DFSMShsm and ABARS Procedure Name

DSNAME('ABEND')
A reserved data set name mask to manage all data sets closed as a result of an abnormal end in a task.

DSNAME('OPEN')
A reserved data set name mask to manage all data sets open when inventory management vital record processing is run or open when the system failed.

JOBNAME(*hsm_proc*)
DFSMShsm procedure name.

JOBNAME(*abars_proc*)
ABARS procedure name.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Single File Format Migration Tapes

Figure 108 shows how to retain all single file format tapes created as original tapes by DFSMShsm migration until DFSMShsm releases the tapes.

```
RMM ADDVRS DSNAME('mprefix.HMIGTAPE.DATASET') -
    COUNT(99999) CYCLES
```

Figure 108. Keeping All Single File Format Migration Tapes

mprefix
Specifies the DFSMShsm-defined migrated data set prefix.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Multifile Format Migration Tapes

Figure 109 shows how to keep multifile format migration tapes. Multifile format applies to reels and not to cartridges.

```
RMM ADDVRS DSNAME('mprefix.HMIG.T%%%%%%.**') -
    COUNT(1) CYCLES
```

Figure 109. Keeping Multifile Format Migration Tapes

mprefix
Specifies the DFSMShsm-defined migrated data set prefix.

% Represents one character of a data set name.

****** Represents zero or more qualifiers of a data set name.

COUNT(1)
Specifies to keep a single cycle. There should never be more than one cycle as DFSMShsm generates the data set names using dates and times. COUNT(99999) can be specified and provide the same results.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Single File Format Backup Tapes

Figure 110 shows how to retain all single file format tapes created as originals by DFSMShsm backup until DFSMShsm releases the tapes.

```
RMM ADDVRS DSNAME('bprefix.BACKTAPE.DATASET') -
    COUNT(99999) CYCLES
```

Figure 110. Keeping Single File Format Backup Tapes

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Multifile Format Backup Tapes

The example in Figure 111 shows how to keep multifile format backup tapes. Multifile format applies to reels and not to cartridges.

```
RMM ADDVRS DSNAME('bprefix.BACK.T%%%%%%.**') -
    COUNT(1) CYCLES
```

Figure 111. Keeping Multifile Format Backup Tapes

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

% Represents one character of a data set name.

****** Represents zero or more qualifiers of a data set name.

COUNT(1)
Specifies to keep a single cycle. There should never be more than one cycle as DFSMShsm generates the data set names using dates and times. COUNT(99999) can be specified and provide the same results.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining and Moving TAPECOPY Tapes or DUPLEX Tapes

The DFSMShsm TAPECOPY command and the DUPLEX tape feature create tapes called alternate tapes. Both the TAPECOPY command and the DUPLEX tape feature use the same naming convention for the alternate tapes.

To retain alternate tapes and to move them to another location,you can define two vital record specifications, one for backup copies and one for migration copies as shown in Figure 112 on page 233.

```
RMM ADDVRS DSNAME('mprefix.COPY.HMIGTAPE.DATASET') -
    COUNT(99999) CYCLES LOCATION(REMOTE) STORENUMBER(99999)

RMM ADDVRS DSNAME('bprefix.COPY.BACKTAPE.DATASET') -
    COUNT(99999) CYCLES LOCATION(REMOTE) STORENUMBER(99999)
```

Figure 112. Keeping Tapes Created by the DFSMShsm TAPECOPY Command and DUPLEX Tape Feature

mprefix
Specifies the DFSMShsm-defined migration data set prefix.

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(99999)
Specifies that all copies should be kept in the specified storage location until they are returned to scratch by DFSMShsm. Specifying STORENUMBER as 99999 in the two examples ensures that when DFSMShsm release the original volumes, it also returns the alternate tapes.

As you create copies of migration and backup tapes with the DFSMShsm TAPECOPY command, DFSMSrmm recognizes the tapes, retains them, and identifies them for movement to the named storage location. During DFSMShsm RECYCLE processing, DFSMShsm releases an alternate tape when it releases the original tape. DFSMSrmm identifies that these volumes should return to the library after DFSMShsm releases the volume. You can use this mechanism to get copy tapes ejected from an automated tape library dataserver after creation and returned to the library after RECYCLE.

Using DFSMSrmm to manage movement is only available for those alternate volumes you have created since implementing the new DFSMShsm TAPECOPY data set name format. The old naming format used for alternate volumes was the same as that used for the base volumes. If you have copies which were created with the old naming convention we suggest that you use DFSMShsm RECYCLE against the base volumes or take a new copy of the base volume. See “Disaster Recovery Using DFSMShsm Alternate Tapes With DFSMSrmm” on page 240 for information on use of alternate tapes during recovery.

Retaining and Moving Dump Tapes

When defining vital record specifications for retaining dump tapes, consider:

- The dump class definitions because the dump classes and the vital record specifications you define must work together.
- The dump class and DASD volume serial numbers when you define the data set names you use in the data set name masks.

The data set name format used by DFSMShsm for dump tapes includes the dump class and the DASD volume serial number. These are the two most likely variables in the data set name on which you will base your retention and movement policies.

- The dump classes that are managed the same.
- The dump classes that require separate management.
- The dump classes that need to be stored off site.
- The need to define additional vital record specifications to support the old data set naming conventions for a period of time.

Figure 113 is the minimum you are required to specify in a vital record specification for DFSMSrmm to keep dump tapes and to prevent DFSMSrmm from releasing DFSMShsm volumes.

```
RMM ADDVRS DSNAME('bprefix.DMP.**') -
    COUNT(1) CYCLES
```

Figure 113. Keeping Tapes Used for Dump

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

****** Represents zero or more qualifiers of a data set name.

COUNT(1)
Specifies to retain a single cycle. In the example, the COUNT(1) is used to retain a single dump cycle. Since DFSMShsm generates a unique name for each dump cycle, COUNT(1) retains all dump cycles.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

If you want to be more specific and manage cycles of dumps, using differing policies you can extend the data set name mask as shown in Figure 114.

```
RMM ADDVRS DSNAME('bprefix.DMP.class.V%%%%%%.**') -
    COUNT(1) CYCLES
```

Figure 114. Managing Cycles of Dumps

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

class
Specifies the DUMPCLASS you have defined to DFSMShsm.

V%%%%%%
The six character volume serial number.

****** Represents zero or more qualifiers of a data set name.

COUNT(1)
Specifies to retain a single data set that matches the filter mask.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

You can also define vital record specifications to manage different types of dump classes having different cycles. Figure 115 shows the use of a pseudo-GDG data set name to identify dump cycles for movement to storage locations for disaster recovery.A DFSMSrmm pseudo-GDG is a collection of data sets, using the same data set name, that DFSMSrmm manages like a GDG. A pseudo-GDG data set name contains the ¬ as a placeholder for the characters in the pattern that change with each generation.

In the example, ¬ is used to mask the DFSMShsm generated date and time in the data set names so that all generations of a dump can be logically managed together.

```
RMM ADDVRS DSNAME('bprefix.DMP.class.V%%%%%%.T¬¬¬¬¬¬.D¬¬¬¬¬') -
    COUNT(100) CYCLES LOCATION(REMOTE) STORENUMBER(2) -
    DELAY(1)
```

Figure 115. Retaining and Moving Volumes by Cycles

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

V%%%%%%
The six character volume serial number.

¬ Is a place holder for a single character in a data set name mask for a pseudo-GDG data set name. When ¬ is used in a data set name mask, DFSMSrmm manages the data sets matching the data set name mask like a generation data group.

COUNT(100)
Specifies to retain all dump cycles managed by DFSMShsm. 100 is the limit for the number of dump cycles.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(2)
Two cycles are kept in the storage location REMOTE. All other cycles up to the COUNT(100) value are retained in the HOME location.

DELAY(1)
The current cycle is kept in the library for one day before being removed to the storage location.

In Figure 115 all 100 cycles of a dump taken for a specific volume and class combination are kept if produced by DFSMShsm. For each matching vital record group:

- The current cycle is kept in the library for one day before being removed to the storage location.
- Two cycles are kept in the storage location.
- All other cycles are returned to and kept in the library until DFSMShsm releases them.

- You can use any combination of LOCATION, STORENUMBER, NEXTVRS and DELAY to provide the required level of service.
- COUNT(100) is coded so DFSMSrmm keeps all cycles that DFSMShsm produces. You can tailor the example by using different values for the class name.

You might need to define additional vital record specifications to support the old data set naming conventions for a period of time.

Retaining and Moving Tapes Written by ABARS

Figure 116 shows how to keep 10 tapes written by ABARS that were created under DFSMS, and provide storage location management for them based on cycles as if they are a generation data group definition.

When you define a vital record specification as shown in Figure 116, DFSMSrmm keeps 10 versions of each of the aggregate backup output data sets and any copies ABARS created. DFSMSrmm retains the latest 10 versions in the REMOTE location and any others in the home location. If there is only one copy of each aggregate backup version produced, and there are 10 versions of each aggregate backup, DFSMSrmm keeps 10 versions of each aggregate backup. If there are 2 copies of each, DFSMSrmm keeps 10 versions of each copy of each aggregate backup.

In the example, the COUNT and STORENUMBER are the same. You could use different values where STORENUMBER is less than or equal to COUNT when you want to store a number of tapes offsite.

```
RMM ADDVRS DSNAME('outputdatasetprefix.%.C%%V¬¬¬¬') -
    COUNT(10) CYCLES -
    LOCATION(REMOTE) STORENUMBER(10) -
```

Figure 116. Keeping ABARS Tapes

outputdatasetprefix
Specifies the same value as entered in the ISMF aggregate processing application as the prefix to be used for output data set.

% Represents the characters D, C, O, and I used by DFSMShsm ABARS processing.

C%%
Represents the copy number.

V¬¬¬¬
Represents the version number DFSMShsm maintains as a pseudo-generation data group.

COUNT(10)
Specifies the number of versions of the aggregate backup to retain.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(10)
Represents a number of versions to be kept in a storage location.

Retaining and Moving ABARS Accompany Tapes

Retaining ABARS accompany tapes applies equally to old ABARS tapes and ABARS tapes created under DFSMS/MVS. You can retain and manage ABARS accompany tapes based on the naming conventions your installation uses. Modify the example shown in Figure 117 with data set names, COUNT and STORENUMBER values for your installation. In the example shown in Figure 117, we assume that all accompany tapes end with '.COPY'.

To keep ABARS accompany tapes, specify:

```
RMM ADDVRS DSNAME('app11.**.COPY') COUNT(10) CYCLES -
    LOCATION(REMOTE) STORENUMBER(10) DELAY(1)
```

Figure 117. Keeping ABARS Accompany Tapes

app11..COPY**
Specifies the data set name mask that identifies the application data set names to retain. DFSMSrmm keeps all data sets that begin with prefix app11 and end with COPY. You can use any data set name you choose and can select vital record specification options to best match those selected for your aggregate groups or other retention and movement policies.

COUNT(10)
Specifies the number of versions of the data set to retain.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(10)
Represents a number of versions to be kept in a storage location.

Retaining DFSMShsm Control Data Set Backup Tapes

To keep all cycles of DFSMShsm control data set and journal backup tapes until DFSMShsm releases them, issue RMM ADDVRS subcommands as shown in Figure 118:

```
RMM ADDVRS DSNAME('authid.%CDS.BACKUP.V¬¬¬¬¬¬¬') -
    COUNT(99999) CYCLES
RMM ADDVRS DSNAME('authid.JRNL.BACKUP.V¬¬¬¬¬¬¬') -
    COUNT(99999) CYCLES
```

Figure 118. Keeping DFSMShsm Control Data Set and Journal Backup Tapes

*authid***.****
Specifies the DFSMShsm prefix used for control data set backups.

% Represents the characters M, B, or O used by DFSMShsm for each of its control data sets.

V¬¬¬¬¬¬¬
Represents the version number DFSMShsm maintains as a pseudo-generation data group.

COUNT(99999)
Specifies to retain all data sets forever or until DFSMShsm releases the volume by notifying DFSMSrmm through the EDGTVEXT installation exit.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

All versions of each of the control data set and journal backups are retained until released when DFSMShsm calls DFSMSrmm to release the tape volume. You can optionally use any of the RMM ADDVRS subcommand operands to meet your movement and retention requirements. For example, you can use the LOCATION and STORENUMBER operands to identify that movement is required.

Using Old Data Set Naming Conventions to Retain and Move DFSMShsm Tapes

You can also specify vital record specifications using the old data set naming conventions, used prior to Version 2 Release 6 of DFHSM. The following sections provide some examples of using the old data set naming conventions to define vital record specifications for dump and ABARS backup tapes.

Retaining Dump Tapes

To manage cycles of dumps, you can use a data set mask as shown in Figure 119:

```
RMM ADDVRS DSNAME('bprefix.DMP.T*.class.D*.V%%%%%%') -
    CYCLES
```

Figure 119. Managing Cycles of Dumps

bprefix
Specifies the DFSMShsm-defined backup and dump data set prefix.

T* Is the time mask to mask the time the dump was created.

class
Specifies the DUMPCLASS you have defined to DFSMShsm.

D* Is the date mask to mask the date the dump was created.

V%%%%%%
The six character volume serial number.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

Retaining Cycles of Dump Tapes

You can move dump cycles to storage locations for disaster recovery. Use additional options for pseudo-generation data groups, to retain and move by CYCLES using the old naming format as shown in Figure 120 on page 239:

```
RMM ADDVRS -
DSNAME('bprefix.DMP.T¬¬¬¬¬¬.class.D¬¬¬¬¬.V%%%%%%') -
    COUNT(100) CYCLES LOCATION(REMOTE) STORENUMBER(2) -
    DELAY(1)
```

Figure 120. Moving Dumps to Storage Locations

bprefix
Specifies the data set name mask that identifies the application.

T* Is the time mask to mask the time the dump was created.

class
Specifies the DUMPCLASS you have defined to DFSMShsm.

D* Is the date mask to mask the date the dump was created.

V%%%%%%
The six character volume serial number.

COUNT(100)
Specifies to retain all dump cycles managed by DFSMShsm. 100 is the limit for the number of dump cycles.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(2)
Represents a number less than the total number of versions to be kept. All other cycles are retained, up to the COUNT value in the HOME location.

DELAY(1)
The current cycle is kept in the library for one day before being removed to the storage location.

You might need to use both types of dump vital record specifications until you have replaced all old retained volumes.

Retaining ABARS Backup Tapes

For ABARS backups taken prior to DFSMS/MVS, the naming convention was different and used true GDG names. Figure 121 shows an example for keeping 10 ABARS backup tapes using GDG names.

```
RMM ADDVRS DSNAME('outputdatasetprefix.%') GDG -
    COUNT(10) CYCLES LOCATION(REMOTE) STORENUMBER(10) -
    DELAY(1)
```

Figure 121. Keeping ABARS Backup Tapes Using GDG Names

outputdatasetprefix
Specifies the same value as entered in the ISMF aggregate processing application as the prefix to be used for output data set.

% Represents the characters D, C, O, and I used by DFHSM ABARS processing.

GDG
Specifies that the data set name is a generation data group name.

COUNT(10)
Specifies the number of versions of the aggregate backup to retain.

CYCLES
Specifies that DFSMSrmm retain data sets based on cycles or copies of a data set.

LOCATION(REMOTE)
Specifies the storage location called REMOTE to which the number of volumes for the data sets specified in STORENUMBER should be moved.

STORENUMBER(10)
Represents a number of versions to be kept in a storage location.

DELAY(1)
The current cycle is kept in the library for one day before being removed to the storage location.

Retaining DFSMShsm Tapes Extra Days Retention

You can use DFSMSrmm to release DFSMShsm tapes that are requested to be purged by DFSMShsm. By default, the expiration date protection for DFSMShsm tapes is done by DFSMShsm. DFSMShsm uses 1999/365 as the expiration date for permanent retention. To enable extra days retention for purged DFSMShsm tape volumes, you need to set up retention options in the vital record specifications that are used to retain the tape volumes.

1. Ensure the DFSMSrmm EDGRMMxx parmlib OPTION MAXRETPD operand is set to NOLIMIT to prevent DFSMSrmm from reducing the expiration date used for the DFSMShsm tape volumes. See “Defining System Options: OPTION” on page 122 for information about the MAXRETPD, VRSEL, and TVEXTPURGE operands.
2. Specify the DFSMSrmm EDGRMMxx parmlib OPTION VRSEL(NEW) operand and the OPTION TVEXTPURGE(EXPIRE) operand.
3. Define a name vital record specification that specifies the EXTRADAYS retention type and chain the name vital record specification to the vital record specifications used to retain DFSMShsm tape volumes. Also use the COUNT operand to specify the number of days you would like the tape volumes to be retained.
4. Include the UNTILEXPIRED retention type in the vital record specifications you use to retain DFSMShsm tape volumes and chain these vital record specifications to the name vital record specifications that include the EXTRADAYs retention type.

```
RMM ADDVRS DSNAME('mprefix.**') UNTILEXPIRED NEXTVRS(HSMEXT)
RMM ADDVRS DSNAME('bprefix.**') UNTILEXPIRED NEXTVRS(HSMEXT)
RMM ADDVRS DSNAME('authid.**') UNTILEXPIRED NEXTVRS(HSMEXT)
RMM ADDVRS NAME(HSMEXT) EXTRADAYS COUNT(N)
```

Disaster Recovery Using DFSMShsm Alternate Tapes With DFSMSrmm

DFSMShsm supports the creation of a duplicate cartridge tape, called an alternate, for each migration or backup tape. The major use of this is to support remote storage of the alternate so that it can easily be used in case of a disaster.

The recommended process includes the following steps related to tape usage:

1. Have a copy of the DFSMShsm control data sets at the disaster site.
2. Perform a TAPEREPL specifying the DISASTERALTERNATE parameter. This flags each existing alternate tape as a disaster alternate.

3. Place DFSMShsm in DISASTER mode. When in disaster mode DFSMShsm dynamically checks before mounting an input tape whether the needed data resides on a tape having a disaster alternate. If it does, the disaster alternate is requested.

DFSMSrmm recognizes when DFSMShsm is opening tape data set s and tolerates the data set names that DFSMShsm uses as long as the last 17 characters of the data set name match.

When you perform a true replacement using the TAPEREPL command, without the DISASTERALTERNATE keyword, DFSMShsm uses the data set name it uses for the original tapes.

Securing Tapes When Running DFSMShsm and DFSMSrmm

How you use the DFSMShsm SETSYS option TAPESECURITY influences the TPRACF value in the DFSMSrmm parmlib member EDGRMMxx.DFSMShsm uses RACF TAPEVOL profiles to secure its volumes. You can combine the DFSMShsm method for securing volumes with DFSMSrmm RACF options as described in “Defining System Options: OPTION” on page 122 to ensure complete security for your tape data.

Select the appropriate combinations for your environment from the following options:

- Use RACF with TAPEVOL and TAPEDSN.
- Use DFSMShsm TAPESECURITY with RACF or EXPIRATIONINCLUDE.
- Use DFSMSrmm TPRACF with A, P, or N and VLPOOL RACF with Y or N.

Recommendations

Our recommendations for running DFSMSrmm with DFSMShsm are:

- Run DFSMShsm with scratch tapes that DFSMSrmm manages so you can have a single scratch pool for all users of tape and so you can gain any benefits available from pre-mounting of scratch tapes in cartridge loaders.
- Use RACF tape security to ensure data security on your system.
- Refer to *z/OS DFSMShsm Implementation and Customization Guide* for details on DFSMShsm data set naming formats.
- Set the following suggested DFSMShsm parameters.

  For the system options, specify:

```
SETSYS EXITOFF(ARCTVEXT) -
       SELECTVOLUME(SCRATCH) -
       TAPEDELETION(SCRATCH) -
       TAPESECURITY(RACF) -
       PARTIALTAPE(MARKFULL)
```

  Specify EXITOFF(ARCTVEXT) if DFSMSrmm is your only tape management product because DFSMShsm always calls the DFSMSrmm programming interface EDGTVEXT.

  Specify SELECTVOLUME(SCRATCH) to cause DFSMShsm to issue a non-specific mount request for output tapes which can be satisfied by any empty tape acceptable to both DFSMShsm and DFSMSrmm.

  Specify PARTIALTAPE(MARKFULL):

- If you are using automatic cartridge loaders so DFSMShsm marks partially used volumes as full. This allows the first output tape of each task to be a non-specific mount, which means you get faster tape mounts. You can specify migration and backup options separately.
- If you want to get migration and backup data duplicated and moved to a storage location in a timely manner. Marking the tapes full prevents a task's last tape, that is only partially filled, from remaining in the library an additional 24 hours before being duplicated the next day for disaster protection.
- If you use TAPECOPY or the DUPLEX tape feature to duplicate tapes and ship them to a storage location, use MARKFULL to end one day's cycle and begin another day's cycle. TAPECOPY only processes full volumes which means that the original tapes have no copy until they are full. This means that a copy might not be available at the storage location as quickly as expected. Using the DUPLEX tape feature means that both the original and copy tapes are created at the same time. DFSMSrmm ships the DUPLEX copy to the storage location as quickly as possible. This might create problems if DFSMShsm expects to continue writing to the tape the next day. Marking the DUPLEX tapes full allows DFSMSrmm to process both TAPECOPY copies and DUPLEX tapes in the same way.

For dump definitions, specify:

```
DEFINE DUMPCLASS(class -
       AUTOREUSE -
       RETENTIONPERIOD(days))
```

Use RETENTIONPERIOD instead of TAPEEXPIRATIONDATE to allow the tapes to be reused or written to by any other program without their needing to be reinitialized after DFSMShsm expires them.

Use AUTOREUSE to have the tapes returned to a scratch pool as soon as the data on the tape are invalidated. This option is necessary for DFSMShsm to call DFSMSrmm to release the tape volume. Without AUTOREUSE, a DELVOL command must be issued for each tape after it is returned to the locale of the tape drives.

Do not use AUTOREUSE for a DFSMShsm-managed pool when also removing tapes from the vicinity of the tape drives. This is because DFSMShsm might select a remotely located tape before DFSMSrmm is able to cause the tape's physical return to the locale of the tape drives.

Chapter 12. Running DFSMSrmm with JES3

DFSMSrmm provides SMP/E USERMODs in SAMPLIB that you can apply to the standard JES3 user exits and other JES3 modules. The USERMODs can be used to prevent JES3 from validating certain volume mounts, to update JES3 fetch and mount messages, and to enable the use of no label tape volumes with JES3. We recommend using EDG3UX71, EDG3UX39, and EDG3UX62 to set up DFSMSrmm with JES3.

In a JES3 system, JES3 validates volume mounts when JES3 is managing tape drives and performing pre-processing setup. JES3 ensures that scratch tapes have reached their expiration date and that volumes are correctly write-enabled or protected. JES3 validation can conflict with DFSMSrmm and RACF processing. For example, you can use 'logical write protect' with IBM tape drives to prevent a user from writing to a tape even if the tape is physically write-enabled. Since DFSMSrmm ensures that all scratch tapes are valid and provides features to ignore the expiration dates on volumes, you might want to prevent JES3 from validating certain volume mounts.

Preventing JES3 from Validating Volumes

Use the EDG3UX29 USERMOD to prevent JES3 from validating volumes to avoid conflicts with DFSMSrmm validation.

In a JES3 system, the default value for EXPDTCHK is YES which can conflict with the tape management system function that allows expiration date protected tapes to be used. EDG3UX29 sets EXPDTCHK=NO.

In a JES3 system, the default value for RINGCHK is YES which can conflict with the tape management system function, DFSMSdfp and RACF function that forces logical write protect or allows a user to open a tape data set for READ even though the tape is write enabled. EDG3UX29 sets RINGCHK=NO.

Updating JES3 Fetch and Mount Messages

DFSMSrmm provides these USERMODs for use when updating JES3 fetch and mount messages with shelf location and pool information.

When you are using EDGUX100 for scratch pooling as described in "Using the DFSMSrmm EDGUX100 Installation Exit" on page 195, we recommend the use of the EDG3UX71 USERMOD to ensure the correct tape pool is requested.

In a JES3 complex all systems running DFSMSrmm must have the same EDGUX100 installation exit and the same parmlib VLPOOL operand values to ensure that a scratch volume is not rejected because it is from the wrong pool. DFSMSrmm also provides USERMODs EDG3LVVR and EDG3IIP1 that you can use to ensure that the correct tape pool is requested. If you do not use one of the USERMODs which allows DFSMSrmm to update a message or tape display, DFSMSrmm cannot provide tape pool information and the wrong tape pool might be requested. Any incorrect tape mounted is rejected by DFSMSrmm volume validation and a remount requested. The remount request does use the correct pool.

© Copyright IBM Corp. 1992, 2001

Using the EDG3UX71 USERMOD

DFSMSrmm supplies a USERMOD to IATUX71 called EDG3UX71 in SAMPLIB. Use EDG3UX71 to update IATUX71 to replace and append text to JES3 fetch and mount messages and to provide text for tape drive displays. Use the EDG3UX71 USERMOD to update the IAT5210 message.

Install the USERMOD using SMP/E after validating that the USERMOD does not conflict with any other modifications to the IATUX71 exit. The USERMOD updates IATUX71 to call the DFSMSrmm EDG3X71 program interface under a JES3 subtask. EDG3X71 as described in “Processing JES3 Messages: EDG3X71” on page 192 updates the IATUX71 parameter list based on DFSMSrmm processing.

1. Install the JES3 APAR OW14239.
2. Set the SETPARAM DSN option in the JES3 initialization deck to a value other than 0. For exit selected scratch pooling, EDGUX100 depends on the data set name being included in the fetch and mount messages. Ensure that you have the DSN keyword coded on the JES3 SETPARAM statement in the initialization deck and the data set name length value is sufficient to provide selection control in EDGUX100. For example, set the keyword using a value of 9 if you use only the first qualifier for pooling. The value is the length of the data set name to be included in mount and fetch messages issued by JES3. We recommend using a value of 31 so there is enough data set name information for the EDGUX100 installation exit to use the data set name for pool selection.

Using the EDG3IIP1 USERMOD

Use the EDG3IIP1 USERMOD in SAMPLIB to update IATIIP1 to force DEFER for all tape requests. If you use EDGUX71, you do not need to use EDG3IIP1. The EDG3IIP1 USERMOD updates IATIIP1 to mark tape allocations for deferred processing. This is equivalent to coding UNIT=(unit,,DEFER) as a JCL keyword.

Install the USERMOD using SMP/E after validating that it does not conflict with any other modifications to the IATIIP1 module.

Using the EDG3LVVR USERMOD

Use the EDG3LVVR USERMOD in SAMPLIB to update the tape drive display with the correct exit selected pool. The EDG3LVVR USERMOD updates IATLVVR to AWAIT MSGDISP for scratch mount. If you use EDG3UX71, you do not need to use EDG3LVVR. The EDG3LVVR USERMOD updates IATLVVR to add a short wait to the verify function. The wait allows the setup function time to issue the IAT5210 message. A JES3 MCS console is required when using this USERMOD.

1. Define a JES3 MCS console.

   Refer to *z/OS JES3 Initialization and Tuning Guide* for details on how to define MCS consoles for use with JES3. You need to define an MCS console with logical association to JES3 and use it as the tape operator console to receive the mount messages as updated by DFSMSrmm. Use the JES3 CONSOLE statement with the TYPE=MCS keyword.

   Use the MCS console routing codes to select which JES3 issued messages are seen on the MCS console. JES3 routes the tape messages to MCS consoles with a route code of 3.

   This method cannot be used in a multi-system JES3 complex where tape drives are attached to a JES3 local processor, because DFSMSrmm can only correctly update the tape drive display on the global processor.
2. Install the USERMOD using SMP/E after validating that it does not conflict with any other modifications to the IATLVVR module.

Enabling the Use of No Label Tapes

Use the EDG3UX62 USERMOD in SAMPLIB to allow a volume with standard labels to be mounted for a non-specific NL request. Installing EDG3UX62 is optional and should be done when you are using JES3 pre-execution setup for tape volumes and when you plan to allow users to create NL tape volumes from scratch volumes.

During JES3 verify processing, JES3 ensures that the mounted volume matches the requested volume. If an NL tape is requested, JES3 ensures that an NL tape is mounted. For specific volume requests this is correct processing, but for non-specific requests DFSMSrmm forces all scratch volumes to contain a standard volume label. As a result, JES3 rejects any scratch volume that is mounted.

The EDG3UX62 USERMOD updates IATUX62 to override the JES3 decision to reject a tape when a non-specific NL tape is requested, a standard label tape is mounted, and the tape is write enabled.

If you do not implement EDG3UX62, you can only use non-specific NL requests when using deferred tape mount processing.

Install the USERMOD using SMP/E after validating that it does not conflict with any other modifications to the IATUX62 module.

Chapter 13. Performing Inventory Management

DFSMSrmm Samples Provided in SAMPLIB

- EDGJHSKP Sample JCL for Using the EDGHSKP Utility
- EDGPHKPA Sample OPC Procedure for Allocating the Data Sets Required for Inventory Management

DFSMSrmm provides the EDGHSKP utility to help you perform inventory management. Inventory management functions can be run in a single job step, but can be split into multiple steps and jobs if required. Running inventory management as a single step allows DFSMSrmm to optimize processing. The default processing for EDGHSKP is to run all inventory management functions in sequence as described in “EXEC Parameters for EDGHSKP” on page 253. Use this chapter to set up and run inventory management activities and to schedule all DFSMSrmm utilities.

Scheduling DFSMSrmm Utilities

You can schedule each DFSMSrmm utility to run on its own, or schedule many activities to run together in a sequence. You can schedule activities to be perform daily like vital records processing and other activities less frequently maybe on a weekly basis. You can use a job scheduling product like Tivoli OPC to run the utilities. See “Chapter 21. Running DFSMSrmm with Tivoli OPC” on page 353 for information about using Tivoli OPC for scheduling DFSMSrmm utilities.

Table 45 suggests how frequently to run DFSMSrmm utilities. References are listed to help you locate the information about the utilities.

Table 45. Scheduling DFSMSrmm Utilities

Activity	Frequency	Reference
Processing vital records	Daily	“JCL for EDGHSKP” on page 253 and “Running Vital Record Processing” on page 260
Performing expiration processing	Daily	“JCL for EDGHSKP” on page 253 and “Running Expiration Processing” on page 274
Performing storage location management	Weekly	“JCL for EDGHSKP” on page 253 and “Running Storage Location Management Processing” on page 271
Creating an extract data set	Daily	“JCL for EDGHSKP” on page 253
Creating volume movement and inventory reports	Weekly	See *z/OS DFSMSrmm Reporting*

© Copyright IBM Corp. 1992, 2001

Table 45. Scheduling DFSMSrmm Utilities (continued)

Activity	Frequency	Reference
Creating security and audit reports	Monthly	See *z/OS DFSMSrmm Reporting*
Backing up the DFSMSrmm control data set	Daily	"JCL for EDGHSKP" on page 253, "Backing Up the Control Data Set" on page 278, and "Backing Up and Restoring the Control Data Set: EDGBKUP" on page 287
Backing up the DFSMSrmm journal	Daily	"JCL for EDGHSKP" on page 253, "Backing Up the Control Data Set" on page 278, and"Backing Up the DFSMSrmm Control Data Set and Journal" on page 289
Verifying the control data set	Monthly	"Creating and Verifying the Contents of the Control Data Set: EDGUTIL" on page 299
Initializing and erasing volumes	Weekly	"Chapter 17. Initializing and Erasing Volumes" on page 311

Running Inventory Management

If you decide to run inventory management in multiple steps, we suggest you run inventory management as follows::

1. Run vital record processing first before expiration and storage location management processing. This is to identify which volumes to retain and where volumes should be moved, based on vital record specifications.
2. Run expiration processing to identify those volumes not required for vital records that are ready to expire. During expiration processing, release actions for volumes are noted.
3. Run storage location management to set a destination location for a volume. Optionally run storage location management to assign shelf locations in storage locations for volumes that are being sent out of or returned to the removable media library. You must run storage location management processing after vital record processing has been successfully run, but not necessarily in the same run of EDGHSKP.
4. Set up an EDGINERS job to run after expiration processing completes to ensure that volumes that are waiting to be released and waiting to be initialized are returned to scratch. Use automatic processing to request EDGINERS to initialize and erase any volumes flagged in the control data set. We recommend you run EDGINERS before and after each run of EDGHSKP.

5. Create an extract data set to use as input to the DFSMSrmm report utility, EDGRPTD, and create a report that shows the new volume movements required.
6. Back up the control data set and journal and keep multiple backup generations to aid recovery.

DFSMSrmm prevents expiration processing from releasing volumes that have been updated since the last run of vital records processing. You normally need a minimum of two EDGHSKP runs to process an expired volume and return it to scratch, which involves at least a 24 hour delay if you are running expiration processing daily. During this time, you can reclaim an expired volume from pending release status by setting a new expiration date. You can also reclaim an expired volume from scratch status by using the RMM CHANGEVOLUME subcommand to change the volume status to master or user. When you use DFSMSrmm to reclaim a volume that resides in a system-managed tape library to master or user status, the volume is changed to PRIVATE in the TCDB.

Inventory Management Considerations

You can perform some activities only under specific conditions:

- In an environment where the DFSMSrmm control data set is shared, and you use system-managed tape, you must run inventory management on a system that has access to the TCDB. If the TCDB is not shared by each system sharing the control data set, and there are multiple TCDBs you must run inventory management at least once against each TCDB on a system that has access to that TCDB.
- You must run inventory management on a system that has access to the catalogs when the DFSMSrmm control data set is shared and you want to retain data sets based on the catalog information or if you specify the parmlib OPTION command UNCATALOG coded with Y or S to indicate that catalog processing is required.
- Use the DFSMSrmm EDGRMMxx parmlib OPTION command CATSYSID operand to use DFSMSrmm in an unshared user catalog environment. When you use unshared catalogs you must run with the DFSMSrmm control data set and the user catalogs synchronized. You must run inventory management expiration processing on each different catalog environment.
- You can reorganize the control data set only when DFSMSrmm is inactive.
- The DFSMSrmm subsystem address space performs all inventory management functions, except backing up the control data set. During inventory management processing, the address space running EDGHSKP waits. Once the subsystem processing completes, EDGHSKP backs up the DFSMSrmm control data set.
- When inventory management functions are active, you can continue using RMM TSO subcommands and DFSMSrmm continues to record tape usage.
- You can run DFSMSrmm control data set backup processing using the DFSMSdss DUMP command or the access method services REPRO command.

  When you use DFSMSdss concurrent copy for backup, DFSMSrmm continues to process commands and update the control data set. As an alternative to use of concurrent copy capable hardware, you can use snapshot capable hardware. When you request backup using DFSMSdss, DFSMSdss uses CC-compatible snapshot instead of concurrent copy.

  When you use the access method services REPRO command or DFSMSdss without concurrent copy for backup, DFSMSrmm does not allow updates to the control data set during control data set backup. Certain DFSMSrmm requests wait until the backup completes. DFSMSrmm fails RMM TSO subcommand

requests that update the DFSMSrmm control data set. For example, if you start backup using the AMS REPRO backup method, command processing can be interrupted. DFSMSrmm functions like the DFSMSrmm TSO SEARCH subcommands, that only read the control data set, continue uninterrupted.

For example, you issue the RMM ADDRACK subcommand to add 2000 new shelf locations as shown in Figure 122.

```
RMM ADDRACK RK0000 COUNT(2000)
```

Figure 122. Adding New Shelf Locations

If back up processing starts before the request completes, DFSMSrmm issues the messages shown in Figure 123.

When backup completes, you could use the ADDRACK subcommand shown in

```
EDG3212E REQUEST REJECTED - DFSMSrmm BACKUP
          CURRENTLY IN PROGRESS
EDG3017I THE ERROR OCCURRED WHILE ADDING RACK NUMBER RK0700
EDG3018I 700 RACK NUMBER(S) ADDED
```

Figure 123. DFSMSrmm Messages Issued during Processing

Figure 124 to add the remainder of the shelves:

```
RMM ADDRACK RK0700 COUNT(1300)
```

Figure 124. Resume Adding New Shelf Locations

- Any tape usage during inventory management results in updates to the control data set. However, any open or close request for a tape data set while the control data set is being backed up using AMS REPRO waits for the backup to complete. DFSMSrmm waits for the backup to complete before updating its control data set.
- At least one vital record specification must be defined in order to run DFSMSrmm vital record processing. The EDGRMMxx parmlib OPTION command VRSMIN operand provides control over this processing.Use the RMM ADDVRS subcommand to define a vital record specification such as the one shown in Figure 125.

```
RMM ADDVRS DSN('**') WHILECATLG
```

Figure 125. Defining a Vital Record Specification

- To use DFSMSdss concurrent copy, you must authorize the DFSMSrmm batch inventory management backup job to the RACF profile STGADMIN.ADR.DUMP.CNCURRNT. See z/OS DFSMSdss Storage Administration Guide for information about protecting DFSMSdss keywords with RACF.

Allocating Data Sets for Inventory Management

DFSMSrmm Samples Provided in SAMPLIB

- EDGJHKPA Sample JCL for Allocating the Data Sets Required for Inventory Management
- EDGPHKPA Sample OPC for Allocating the Data Sets Required for Inventory Management

Before running EDGHSKP, define several data sets as described in Table 46 . The data sets that are used by both the EDGHSKP utility and the DFSMSrmm subsystem address space must be pre-allocated and cataloged as shown in Table 46.

To avoid enqueue contention,

- These data sets cannot be created in the same job as they are used. If you plan to retain multiple versions of these data sets, consider using a subsequent job step to copy the data sets to a new GDG generation.
- The JCL used to run EDGHSKP should specify DISP=SHR for these data sets. To avoid problems that might occur when multiple EDGHSKP jobs are running together, we recommend adding a DD statement to the job step that runs EDGHSKP as shown in Figure 126:

```
//ENQDSN   DD DISP=OLD,DSN=RMM.HSKP.ENQ
```

Figure 126. JCL for Adding a DD Statement to the EDGHSKP Job Step

Alternatively you can use the sample RMM OPC application which uses OPC special resources to prevent multiple jobs running together as described in “Chapter 21. Running DFSMSrmm with Tivoli OPC” on page 353.

To protect the data sets that must be preallocated, cataloged, and on DASD, ensure that the RACF user ID associated with the DFSMSrmm subsystem has authority to write to the data sets.

Table 46. DFSMSrmm EDGHKSP Data Sets

DD Statement	Preallocated, Cataloged, DASD Data Set	Description
ACTIVITY	Yes	Contains detailed information about data set related changes DFSMSrmm makes to the control data set during inventory management. This data set is required when you specify the VERIFY parameter.
BACKUP	No	Contains the backup copy of the DFSMSrmm control data set. This data set is required when you specify the BACKUP parameter. You can back up directly to tape when you specify the BACKUP(DSS) parameter even when DFSMSdss concurrent copy is not available.
DSSOPT	No	Contains DUMP or RESTORE command options used by DFSMSdss during backup processing. See “Customizing the DSSOPT DD Statement” on page 279 for information about changing the commands.

Table 46. DFSMSrmm EDGHKSP Data Sets (continued)

DD Statement	Preallocated, Cataloged, DASD Data Set	Description
JRNLBKUP	No	Contains the backup copy of the DFSMSrmm journal. This data set is optional when you specify the BACKUP parameter. DFSMSrmm uses IDCAMS to back up the journal when you specify the BACKUP(AMS) or BACKUP(DSS) parameter. Note that you can back up the journal directly to tape when you specify the BACKUP(DSS) parameter.
MESSAGE	Yes	Lists the messages the DFSMSrmm subsystem issues during inventory management. This data set is required.
REPORT	Yes	Contains a detailed report of DFSMSrmm vital record specification processing. Specify if you want a report when you have specified the VRSEL parameter.
REPTEXT	Yes	Contains the extract copy of the DFSMSrmm control data set. The extract copy is called the extract data set. The extract data set is required when you specify the RPTEXT parameter.
SYSPRINT	No	Contains the utility program messages that IDCAMS and ADRDSSU issue when backing up the DFSMSrmm control data set. The SYSPRINT data set is required when you specify the BACKUP parameter. This data set can be a SYSOUT file.

Assessing DASD Space and Placement for the Extract Data Set

You can request an extract data set that contains information about the location where a volume resides, volume information, data set, software product, owner, and vital record specification information.

The extract data set can be sorted and used to create reports or lists of executable commands. See *z/OS DFSMSrmm Reporting* for information on creating reports.

You can place the extract data set on any volume.

Table 47 helps you calculate DASD space requirements for the extract data set specified by the REPTEXT DD statement.

Table 47. DFSMSrmm Extract Data Set DASD Space Requirements

Extract Data Set Content	DASD Space
Data sets	368KB for every 1000
Shelf locations in the library that do not contain volumes	11KB for every 1000
Shelf locations in storage locations	11KB for every 1000
Owners	35KB for every 1000
Software products	17KB for every 100
Volumes	719KB for every 1000
Vital record specification	20KB for every 1000

Convert the final figure into a space allocation. The extract data set has a record format of variable-length blocked records. Choose either a system-determined block size, or a block size suitable for the device your installation uses.

To calculate the space required:

1. Divide the total KB of space by 4. This calculation gives you the number to use in the space allocation.
2. Use a fraction of this total space as secondary space if you want to have an extract data set that extends to multiple extents.

You can use JCL as shown in Figure 127 to create the extract data set prior to running EDGHSKP.

```
//REPTEXT DD DISP=(NEW,CATLG),DSN=RMM.EXTRACT.DSET,
//        UNIT=SYSDA,AVGREC=U,SPACE=(4096,(pp,ss))
```

Figure 127. JCL for Specifying the Extract Data Set

where:

pp Specifies the calculated primary space.

ss Specifies a fraction used for secondary space.

JCL for EDGHSKP

Figure 128 shows example JCL for EDGHSKP:

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='VRSEL,EXPROC,DSTORE,BACKUP(DSS),RPTEXT,DATEFORM(E)'
//SYSPRINT DD SYSOUT=A
//DSSOPT   DD *
    CONCURRENT OPTIMIZE(1) VALIDATE
/*
//BACKUP   DD DSN=BACKUP.FILE.NAME,DISP=(NEW,CATLG),
//            UNIT=SYSDA,AVGREC=U,SPACE=(4096,(1000,500)),
//            LRECL=9000,BLKSIZE=32000,RECFM=VB
//JRNLBKUP DD DSN=JOURNAL.BACKUP.FILE.NAME,DISP=(NEW,CATLG),
//            UNIT=SYSDA,AVGREC=U,SPACE=(4096,(1000,500)),
//            LRECL=32756,BLKSIZE=32760,RECFM=VB
//MESSAGE  DD DSN=MESSAGE.FILE.NAME,DISP=SHR
//REPORT   DD DSN=REPORT.FILE.NAME,DISP=SHR
//ACTIVITY DD DSN=ACTIVITY.FILE.NAME,DISP=SHR
//REPTEXT  DD DSN=REPORT.EXTRACT.FILE.NAME,DISP=SHR
/*
```

Figure 128. Example of JCL for EDGHSKP

EXEC Parameters for EDGHSKP

Figure 129 on page 254 shows the EXEC parameters for EDGHSKP. DFSMSrmm uses all the parameters except CATSYNCH, DATE, and VERIFY if you do not specify PARM on the EXEC statement.

You can specify the EXEC parameters in any order, but DFSMSrmm processes them in the following sequence:

1. CATSYNCH processing
2. VRSEL vital record processing
3. DSTORE storage location management processing
4. EXPROC expiration processing
5. RPTEXT extract data set creation
6. BACKUP control data set back up processing



production_run_parameters:

trial_run_parameters:



Figure 129. EDGHSKP EXEC Parameters

The EXEC parameters are:

BACKUP(AMS|DSS)
Specify BACKUP to back up the control data set and optionally back up the journal when you include the BACKUP and JRNLBKUP DD statements in your EDGHSKP JCL.

BACKUP(AMS) is the default. DFSMSrmm uses the access method services REPRO command to perform backup processing. Specifying BACKUP(AMS) prevents DFSMSrmm from updating the control data set during control data set backup processing. Backup cannot be direct to tape.

Specify BACKUP(DSS) with the DFSMSdss concurrent copy environment set up to permit the update of the DFSMSrmm control data set during backup processing. This ensures that all tape activities can continue during backup processing. You can specify BACKUP(DSS) without setting up the concurrent copy environment. If you specify BACKUP(DSS), backup can be direct to tape.

For journal backup, DFSMSrmm uses IDCAMS to back up the journal even when BACKUP(DSS) is specified.

CATSYNCH
Specify CATSYNCH to request that DFSMSrmm updates the DFSMSrmm control data set with information from available user catalogs. Before you can

synchronize the DFSMSrmm control data set with user catalogs, you must first define system IDs using the EDGRMMxx parmlib OPTION CATSYSID operand as described in “Defining System Options: OPTION” on page 122.

If you specify the EDGRMMxx parmlib OPTION CATSYSID(*) to indicate that catalogs are fully shared and that any data set can be processed by DFSMSrmm on any DFSMSrmm system, DFSMSrmm checks that the control data set has been synchronized prior to performing vital record processing or expiration processing. DFSMSrmm dynamically adds the CATSYNCH execution option when the control data set and catalogs are not synchronized and the EDGHSKP VRSEL or EXPROC parameters are specified.

If CATSYSID is specified with specific system IDs, you cannot run vital record processing until the control data set is synchronized with all user catalogs and you have run EDGUTIL with the SYSIN statement CONTROL CATSYNCH(YES). See “Creating or Updating the Control Data Set Control Record” on page 303 for information about marking the control data set for synchronization.

Prior to synchronizing the DFSMSrmm control data set with available user catalogs, you can specify the VERIFY parameter with the CATSYNCH parameter to find differences between the DFSMSrmm control data set and the user catalogs. DFSMSrmm reports all the differences so you can make updates, if required, to catalog information before running CATSYNCH without the VERIFY parameter.

DFSMSrmm adds information about the data sets that are synchronized in the ACTIVITY report.

DATE(*date***, +***nnnn***)**
Specify DATE to set the date used for VERIFY processing.

To specify a date with *date*, supply the year and day in one of two forms:

- yyddd, where yy is the last two-digit number for the year and ddd is the three-digit number for the day of the year, such as 93001.
- yyyy/ddd, where yyyy is the four-digit number for the year and ddd is the three-digit number for the day of the year, such as 1993/001. The slash is required.

For dates in the year 2000 and or in the 21st century or higher, you can only use the yyyy/ddd format. If you use the yyddd format, DFSMSrmm defaults to the 20th century.

To specify a number of days to add to the current date, supply *+nnnn* to determine the actual date to be used for VERIFY processing. You specify the value as a plus sign and the number of days, for example, to use the date in 7 days time specify DATE(+7).

The current date is the default.

DATEFORM (*A***|***E***|***I***|***J***|***D***)**
Specify DATEFORM to set the date format for records written to the extract data set, records written to the ACTIVITY file, and any messages issued during inventory management.

Value	Language	Format	Example
A	American	mm/dd/yyyy	12/15/1994
E	European	dd/mm/yyyy	15/12/1994
I	ISO	yyyy/mm/dd	1994/12/15
J	Julian	yyyy/ddd	1994/349
D	Default	Installation's default in EDGRMMxx	Initially set to Julian

The default date format for all date fields is the value specified in the parmlib member EDGRMMxx. The value is initially set to J for Julian. To change the date format for each run of EDGHSKP, use the DATEFORM parameter.

DSTORE
Specify DSTORE for storage location management processing.

EXPROC
Specify EXPROC for expiration processing.

RPTEXT
Specify RPTEXT to create records in the extract data set.

VERIFY
Specify VERIFY to request that DFSMSrmm performs a trial run of selected processing. You can run a trial run for vital record processing and catalog synchronization. When you specify VERIFY, DFSMSrmm performs the requested processing but does not update the control data set as a result of the processing.

You could specify VERIFY to perform a trial run to test new vital record specifications that you define to DFSMSrmm. Run VERIFY to confirm that your new and changed retention and movement policies achieve the expected results. If all you want to perform is a trial run of vital record processing, you can specify VERIFY with or without the VRSEL parameter. You can use the DATE parameter with VERIFY to set a date to perform VERIFY processing. When you request VERIFY you can use all the inventory management parameters except DSTORE and EXPROC. The ACTIVITY file is required when you select the VERIFY option.

Note: The DFSMSrmm parmlib OPTION VRSCHANGE operand default of VERIFY prevents inventory management vital record processing when there are policy changes that have not been tested. You only need one successful run of VERIFY, before you can continue with inventory management processing. If VERIFY completes successfully, but you do not obtain the vital record specification results you expected, you must continue to modify policies and make further VERIFY runs until results are acceptable.

VRSEL
Specify this parameter for vital record processing. To perform a trial run of vital record processing, you can also specify the VERIFY parameter and optionally the DATE parameter. Performing a trial run allows you to see how DFSMSrmm vital record processing changes affect data set and volume information before the control data set is updated.

How Inventory Management Works

You use the EDGHSKP utility to request that DFSMSrmm perform inventory management processing. The utility performs parameter validation, checks that the correct files are allocated and can be used, requests that the DFSMSrmm subsystem perform the functions you asked for, and finally uses the EDGBKUP utility to perform backup processing.

During DFSMSrmm subsystem inventory management processing, you can see the address space executing EDGHSKP waiting for the subsystem processing to complete. You can use the RMM LISTCONTROL subcommand with the CNTL operand to see which inventory management functions are active, and the dates and times when the individual functions were last successfully processed. If the batch job requesting an inventory management function is cancelled after the function has started, the function continues to run in the DFSMSrmm address space until it completes.

During inventory management the DFSMSrmm subsystem issues messages describing processing. Messages are in the MESSAGE data set. During expiration processing, DFSMSrmm identifies data sets that might be open and puts them in a list in the MESSAGE file. See Figure 138 on page 276 for an example of this output.

Running DFSMSrmm Catalog Synchronization

DFSMSrmm always tracks tape data set catalog activity independently of the CATSYSID parameter. When you enable catalog synchronization, DFSMSrmm synchronizes the DFSMSrmm control data set and available user catalogs. You enable catalog synchronization by specifying the DFSMSrmm EDGRMMxx OPTION CATSYSID operand described in “Defining System Options: OPTION” on page 122. When you specify the CATSYSID operand, DFSMSrmm uses the catalog search interface to obtain catalog information used for DFSMSrmm vital record processing. DFSMSrmm performs checking to determine that the catalog search interface catalog environment does not have any errors that might prevent successful processing. DFSMSrmm issues messages EDG2235E, EDG2236I, or EDG2237E when an error is encountered. If you do not specify the DFSMSrmm EDGRMMxx OPTION CATSYSID operand, DFSMSrmm vital record processing uses catalog locates to determine if data sets are still cataloged.

You must re-synchronize the DFSMSrmm control data set and user catalogs when:

- DFSMSrmm is not active when catalog activity for tape data sets is taking place. DFSMSrmm issues messages EDG8200E and EDG8201E when DFSMSrmm cannot track catalog updates.
- A DFSMSrmm failure occurs during catalog processing. DFSMSrmm issues EDG8200E and EDG8201E when an error is detected in processing.
- Catalog maintenance has been performed, such as using IDCAMS REPRO to copy or duplicate catalog entries, or connecting or disconnecting user catalogs to the master catalog.

We recommend that you use EDGUTIL with the UPDATE parameter and with the SYSIN command CONTROL CATSYNCH(NO) parameter when you think the DFSMSrmm control data set and the catalogs are no longer synchronized. This prevents DFSMSrmm from relying on the catalog information in the control data set. Later you can re-synchronize the information or DFSMSrmm will do it automatically at inventory management time when the catalogs are fully shared.

You can automate the response to the DFSMSrmm messages EDG8200E and EDG8201E to force re-synchronization before any inventory management functions dependent on catalog information are run. Run EDGUTIL UPDATE with the SYSIN command CONTROL CATSYNCH(NO) parameter to set up this automation.

There are some limitations to using DFSMSrmm catalog synchronization including:

- You must define data sets to DFSMSrmm before you create catalog entries for them.
- If either of the following applies to you, do not rely on DFSMSrmm for maintaining catalog synchronization. However, you can exploit the status tracking DFSMSrmm performs, by always specifying the EDGHSKP CATSYNCH option when running expiration processing or vital record processing functions.
  - If you use the DFSMSrmm TSO subcommands to add data sets to the DFSMSrmm control data set, you should do so before cataloging the data sets. If you have to add cataloged data sets you can run EDGHSKP with CATSYNCH to synchronize the catalogs with DFSMSrmm.
  - If you create cataloged tape data sets by writing to tape volumes but do not allocate the file using the catalog entry, DFSMSrmm cannot track the catalog status. DFSMSrmm relies on intercepting the catalog and uncatalog activity and the data set information being already recorded by DFSMSrmm at the time of the catalog activity.

You control how DFSMSrmm performs catalog synchronization using the EDGRMMxx parmlib OPTION CATSYSID operand. If you specify the CATSYSID(*) operand, you must ensure that the catalog environment is shared. If you specify CATSYSID(*) without ensuring that catalogs are shared, you can lose data. If you specify the CATSYSID operand with system IDS, you cannot run DFSMSrmm inventory management until the DFSMSrmm control data set and user catalogs are synchronized.

If catalogs are not fully shared, and you specify the EDGRMMxx parmlib OPTION UNCATALOG(Y/S) operand, you must run expiration processing on each system. This ensures that DFSMSrmm uncatalogs data sets in the correct catalogs on return to scratch. You must run expiration processing on each system to avoid running low on scratch volumes because DFSMSrmm only returns volumes to scratch when processing in the correct catalog environment.

To ensure that DFSMSrmm processes the return to scratch, you must also specify the EDGRMMxx parmlib OPTION CATSYSID operand with the system IDs on which the volumes were created. DFSMSrmm uses the CATSYSID operand to determine the systems to which volumes can be returned to scratch status. DFSMSrmm checks the system creation ID for the first file on the volume with the list of IDs specified for the CATSYSID operand. If there is a match, DFSMSrmm processes the return to scratch.

DFSMSrmm Catalog Processing

When you run DFSMSrmm with user catalogs and the DFSMSrmm control data set unsynchronized, DFSMSrmm issues catalog locates as required to check if data sets are cataloged. Catalog locates use the standard catalog search to find if a data set is cataloged. Any data sets cataloged using JOBCAT or STEPCAT might not be found to be cataloged because standard catalog search might not find them.

When you run DFSMSrmm with user catalogs and the DFSMSrmm control data set synchronized, DFSMSrmm does not need to issue catalog locates to find if a data

set is cataloged. The catalog status tracked by DFSMSrmm in the control data set is used to determine if a data set is cataloged. When DFSMSrmm tracks catalog status, it does so regardless of whether JOBCAT or STEPCAT is used. During catalog synchronization DFSMSrmm uses the Catalog Search Interface (CSI) to retrieve data set catalog information. CSI returns catalog information for all data sets in all catalogs that are in or connected to the master catalog. Because of this, DFSMSrmm can detect a data set is cataloged even if it cannot be found using the standard catalog search.

JCL for Catalog Synchronization

To request catalog synchronization, specify the CATSYNCH parameter. You can submit a job with JCL similar to Figure 130.

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='CATSYNCH'
//MESSAGE  DD DSN=MESSAGE.FILE.NAME,DISP=SHR
//ACTIVITY DD DSN=ACTIVITY.FILE.NAME,DISP=SHR
```

Figure 130. Example of JCL for Catalog Synchronization Processing

Specify the CATSYNCH and the VERIFY parameter to perform a trial run of catalog synchronization. You can submit a job with JCL similar to Figure 131.

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='CATSYNCH,VERIFY'
//MESSAGE  DD DSN=MESSAGE.FILE.NAME,DISP=SHR
//ACTIVITY DD DSN=ACTIVITY.FILE.NAME,DISP=SHR
```

Figure 131. Example of JCL for Trial Run Catalog Synchronization Processing

Synchronizing the DFSMSrmm Control Data Set with User Catalogs in a Fully Shared Catalog Environment

DFSMSrmm fully supports shared user catalogs whether or not the control data set and user catalogs are synchronized. Synchronizing the DFSMSrmm control data set and user catalogs helps DFSMSrmm avoid locating catalog information for every data set that is managed using catalog control. To synchronize the DFSMSrmm control data set with user catalogs:

1. Ensure that all systems sharing the control data set are running the DFSMSrmm level of code that supports catalog tracking and catalog synchronization. When you have correct level of DFSMSrmm code installed, DFSMSrmm dynamically records all catalog updates for tape data sets in the control data set.
2. Specify the DFSMSrmm EDGRMMxx parmlib OPTION CATSYSID(*).
3. Set up automatic synchronization by automating the responses to DFSMSrmm messages EDG8200E and EDG8201E running the EDGUTIL UPDATE with the SYSIN command CONTROL CATSYNCH(NO).
4. Run the DFSMSrmm EDGHSKP utility with the PARM=CATSYNCH parameter to synchronize all data set records in the control data set with the status from the catalog. DFSMSrmm sets the 'last catalog synchronize date and time' in the control record. When the CATSYSID operand is specified in the EDGRMMxx parmlib member, you cannot run VRSEL or EXPROC processing unless the control data set is synchronized or CATSYNCH is specified in the same processing run.

5. When running EDGHSKP expiration processing or vital record processing, if CATSYSID(*) is specified in parmlib and the control data set is not synchronized with the catalogs, DFSMSrmm initiates catalog synchronization even if you have not specified it.

Synchronizing the DFSMSrmm Control Data Set with User Catalogs when Catalogs Are Not Fully Shared

The DFSMSrmm control data set and user catalogs must be synchronized for DFSMSrmm to support unshared user catalogs. To synchronize the DFSMSrmm control data set with user catalogs:

1. Ensure all systems that share the control data set are running the DFSMSrmm level of code that supports catalog tracking and catalog synchronization. When you have correct level of DFSMSrmm code installed, DFSMSrmm dynamically records all catalog updates for tape data sets in the control data set.
2. Specify the DFSMSrmm EDGRMMxx parmlib OPTION CATSYSID operand with the system IDs that are common to the set of user catalogs on the system.
3. Set up automatic synchronization by automating the responses to DFSMSrmm messages EDG8200E and EDG8201E running the EDGUTIL UPDATE with the SYSIN command CONTROL CATSYNCH(NO).
4. Run the DFSMSrmm EDGHSKP utility with the PARM=CATSYNCH parameter to partially synchronize all data set records in the control data set with the status from the accessible catalogs. Run CATSYNCH on other systems that share the control data set until all the catalogs have been synchronized.
5. Run EDGUTIL with PARM=UPDATE parameter and CONTROL CATSYNCH(YES) to set the 'last catalog synchronization date and time' in the DFSMSrmm control dataset control record.
6. Run inventory management functions on any one system at any time. However, if you run expiration processing to return volumes to scratch status, DFSMSrmm only processes a subset of volumes.
7. You must run EDGHSKP expiration processing on multiple systems if you specify the EDGRMMxx parmlib OPTION UNCATALOG(Y or S). You should run expiration processing once for each set of user catalogs on a system with access to those user catalogs.

Running Vital Record Processing

Vital records processing identifies the volumes that should be retained and how they show be moved based on the vital record specifications you define. Use the EDGRMMxx parmlib OPTION VRSMIN operand to specify the minimum number of vital record specifications that must be defined in order to run inventory management vital record processing. The default number of vital record specifications is 1. You can also set other parmlib OPTION operands to control how DFSMSrmm performs vital record processing as described in "Defining System Options: OPTION" on page 122. You can retain data sets and volumes in several ways. For example, you can retain volumes by generic volume serial number, data sets for as long as they are cataloged, or by the job name that created the data set. For more information about moving and retaining volumes with vital record specifications, see *z/OS DFSMSrmm Guide and Reference*.

DFSMSrmm can create a report describing data sets and volumes being retained and the location where the data set or volume resides. See Figure 134 on page 262 for an example of this report.

You can also request an ACTIVITY file as described in “Using the Inventory Management ACTIVITY File” on page 266. DFSMSrmm can write details to the ACTIVITY file about changes to data set information made during vital record processing The ACTIVITY file is optional except when the VERIFY EXEC parameter is used to request that DFSMSrmm performs a trial run of vital record processing.

JCL for Vital Record Processing

To request vital record processing, specify the VRSEL parameter. You can submit a job with JCL as shown in Figure 132:

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='VRSEL'
//MESSAGE  DD DISP=SHR,DSN=HSKP.MESSAGES
//REPORT   DD DISP=SHR,DSN=HSKP.VRS.REPORT
//ACTIVITY DD DISP=SHR,DSN=HSKP.ACTIVITY
```

Figure 132. Example of JCL for Vital Record Specification Processing

To run a trial run of vital record processing, you can submit a job with JCL as shown in Figure 133:
You can request that DFSMSrmm create a REPORT file shown in “Using the Vital

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='VRSEL,VERIFY'
//MESSAGE  DD DISP=SHR,DSN=HSKP.MESSAGES
//REPORT   DD DISP=SHR,DSN=HSKP.VRS.REPORT
//ACTIVITY DD DISP=SHR,DSN=HSKP.ACTIVITY
```

Figure 133. Example of JCL for Trial Run Vital Record Specification Processing

Records Retention Report” on page 262. When the REPORT file is specified, DFSMSrmm creates a detailed report of data sets and volumes being retained, the vital record specification that is retaining the data set or volume, and the required location for the data set or volume.

You can specify the LRECL for the REPORT file. The LRECL can be a value from 133 to 255. If you specify an LRECL that is 148 or higher, only a single line is displayed for a retained data set. If you specify a value less than 148, DFSMSrmm uses two lines to display data set information. The page, date, and time fields in the report are right aligned assuming a record length of 133 characters.

The minimum LRECL must include one byte for the ASA print control character. If you use variable length record format for the REPORT file, then you must add four bytes to the minimum record length to hold the descriptor word. This means that if your REPORT file contains variable length records with a data length of 132 bytes, then you must define the minimum LRECL as 137 bytes.

You can also request an ACTIVITY file as described in “Using the Inventory Management ACTIVITY File” on page 266. The ACTIVITY file is optional except when the VERIFY EXEC parameter is used to request that DFSMSrmm performs a trial run of vital record processing.

Using the Vital Records Retention Report

Use the Vital Records Retention Report to check the vital record specifications that match to data sets and to see which versions of the data sets are being retained. The report file lists the required location for each data set and volume. Use the EDGRPTD movement report to identify the destination selected for each volume after VRSEL processing is completed and DSTORE and RPTEXT have been run.

Figure 134 shows a sample of the report produced by vital record processing:

```
REMOVABLE MEDIA MANAGER                          VITAL RECORDS RETENTION REPORT                                  PAGE          1
        (C) IBM CORPORATION 1993 1998            ----- ------- --------- ------                       TIME 11:21:02 DATE   1998/085

JOB MASK  DATA SET OR VOLUME MASK                      OWNER    TYPE RETN   C X   DELETE   DLY COUNT STNUM LOCATION RLSE
_____________________________________________________________________________________________________________________
          STSGMA.AND.**                                STSGMA   DSN  BYDAYC N N   1999/365   0     3     3 HOME     XI SI
          WHILEC                                       STSGMA   AND  CYCLES Y N   1999/365     99999

JOB NAME  DATA SET NAME      2ndVRS   2ndNAME  FSEQ DSEQ VOLUME VSEQ OWNER    CURRENT  REQUIRED PRTY  RETDATE   RETNAME
_____________________________________________________________________________________________________________________
          STSGMA.AND.G0002V00                      1    0 AND002    1 STSGMA   SHELF    SHELF    5000 CYCL/00003  *
NUMBER OF DATA SETS RETAINED (GROUP STORE) =                                                          1     0

JOB MASK  DATA SET OR VOLUME MASK                      OWNER    TYPE RETN   C X   DELETE   DLY COUNT STNUM LOCATION RLSE
_____________________________________________________________________________________________________________________
          STSGMA.ORR.**                                STSGMA   DSN  BYDAYC N N   1999/365   0     3     3 HOME     SI
          WHILEC                                       STSGMA   NEXT CYCLES Y N   1999/365     99999 99999 HOME

JOB NAME  DATA SET NAME      2ndVRS   2ndNAME  FSEQ DSEQ VOLUME VSEQ OWNER    CURRENT  REQUIRED PRTY  RETDATE   RETNAME
_____________________________________________________________________________________________________________________
          STSGMA.ORR.G0009V00                      1    0 ORR009    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0008V00                      1    0 ORR008    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0007V00                      1    0 ORR007    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0006V00                      1    0 ORR006    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0005V00                      1    0 ORR005    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0004V00                      1    0 ORR004    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.G0002V00                      1    0 ORR002    1 STSGMA   SHELF    SHELF    5000 WHILECATLG WHILEC
NUMBER OF DATA SETS RETAINED (GROUP STORE) =                                                          7     0

          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0009V00
                                                   1    0 ORR009    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0008V00
                                                   1    0 ORR008    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0007V00
                                                   1    0 ORR007    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0006V00
                                                   1    0 ORR006    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0005V00
                                                   1    0 ORR005    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0004V00
                                                   1    0 ORR004    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.ORR.AAAAAAAA.BBBBBBBB.G0002V00
                                                   1    0 ORR002    1 STSGMA   SHELF    SHELF    5000 WHILECATLG WHILEC
NUMBER OF DATA SETS RETAINED (GROUP STORE) =                                                          7     0
```

Figure 134. Sample Vital Records Retention Report (Part 1 of 2)

```
JOB MASK  DATA SET OR VOLUME MASK                       OWNER    TYPE RETN   C X   DELETE   DLY COUNT STNUM LOCATION RLSE
_________ STSGMA.MVO.**                                 STSGMA   DSN  BYDAYC N N   1999/365   0     3     3 HOME     XI

JOB NAME  DATA SET NAME      2ndVRS   2ndNAME  FSEQ DSEQ VOLUME VSEQ OWNER    CURRENT  REQUIRED PRTY  RETDATE   RETNAME
_________ STSGMA.MVO.G0009V00
                             WHILEC               1    0 ORR009    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0008V00
                             WHILEC               1    0 ORR008    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0007V00
                             WHILEC               1    0 ORR007    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0006V00
                             WHILEC               1    0 ORR006    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0005V00
                             WHILEC               1    0 ORR005    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0004V00
                             WHILEC               1    0 ORR004    1 STSGMA   SHELF    SHELF    5000 CYCL/00003 *
          STSGMA.MVO.G0002V00
                             WHILEC   WHILEC      1    0 ORR002    1 STSGMA   SHELF    SHELF    5000 WHILECATLG
NUMBER OF DATA SETS RETAINED (GROUP STORE) =                                                        7     0
```

Figure 134. Sample Vital Records Retention Report (Part 2 of 2)

The data columns in the vital records retention report provide the following information:

JOB MASK
The job name mask defined for the vital record specification.

DATA SET OR VOLUME MASK
The data set name mask or generic volume serial number defined for the vital record specification. In addition to the data set name mask or the volume serial number, this field can contain descriptive text about a vital record specification chain.

OWNER
Owner ID of the vital record specification owner.

TYPE
Type of vital record specification: one of AND, DSN, GDG, NEXT, PGDG, or VOL.

- AND designates a NAME vital record specification which is pointed to by a vital record specification with the ANDVRS operand.
- DSN for data set vital record specification.
- GDG designates a data set vital record specification with the GDG operand specified.
- NEXT designates a NAME vital record specification which is pointed to by a vital record specification with the NEXTVRS operand.
- PGDG designates a data set vital record specification with a pseudo-generation data set name mask.
- VOL for volume vital record specification.

RETN
Type of retention for data set vital record specifications and name vital record specifications:

BYDAYC
Retention type is BYDAYSCYCLE.

CYCLES
Retention type is CYCLES.

DAYS
Retention type is DAYS since creation.

LRDAYS
Retention type is LASTREFERENCEDAYS.

XDAYS
Retention type is EXTRADAYS.

C Y if the WHILECATALOG option applies. N if the WHILECATALOG option does not apply.

X Y if the UNTILEXPIRED option applies. N if the UNTILEXPIRED option does not apply.

DELETE
The date DFSMSrmm deletes the vital record specification.

DLY
The number of days that DFSMSrmm delays the latest copy of a data set or volume before sending it to the named location

COUNT
Total number of retention days or cycles for a data set, total number of retention days for a single volume, total number of volumes for generic volume. The number of days, cycles, or volumes is listed for each vital record specification in the chain that contains retention information. The report lists the total number of data sets retained in the current group at the end of each group of retained data sets.

STNUM
Lists the vital record specification store number value. The store number value is the number of days to retain a data set or volume, the number of data set cycles to retain, or the number of volumes to retain. STNUM is blank for AND vital record specifications. The report lists the total number of data sets in the current group that are requested to be retained outside of their home location.

LOCATION
The location in which the data set or volume should be retained. LOCATION is blank for AND vital record specifications.

RLSE
Lists the vital record specification release options in the data set vital record specification. RLSE can be IX SI, IX, or SI. IX is EXPIRYDATEIGNORE and SI is SCRATCHIMMEDIATE.

JOB NAME
The job that created the data set.

DATA SET NAME OR VOLUME MASK
Data set name. If a data set name exceeds 30 characters in length, and if a data set matches to both a primary and secondary vital record specification, DFSMSrmm splits the output line at this field so that all data set information can be presented.

2ndVRS
Lists the management value vital record specification or management class vital record specification when a data set matches to both a primary and secondary vital record specification. If the management class vital record specification or management value vital record specification is currently retaining the data set, DFSMSrmm puts the name of the vital record specification that is retaining the data set in the 2nd NAME field.

2ndNAME
Lists the name of the first vital record specification in the secondary vital record

specification chain that retains the data set. This field is always filled when a data set is retained by a secondary vital record specification. When vital record specifications are chained using AND, DFSMSrmm puts the name of the first vital record specification in this field. This field is blank when a data set is retained by a primary vital record specification.

FSEQ
Physical file sequence number.

DSEQ
Data set sequence number on the named volume.

VOLUME
Volume serial number.

VSEQ
Volume sequence number.

OWNER
Owner ID of the volume and data set owner.

CURRENT
Current location of the volume.

REQUIRED
Destination of volume based on the matching vital record specification. When multiple data sets exist on a volume, the destination for the volume is calculated using the priority of each of the required locations identified for the volume. The volume's destination is calculated based on the location priorities described in Table 48 on page 270. If there are multiple data sets on a volume or the volume is retained using multiple vital record specifications, the required location listed in the report might be different from the destination to which DFSMSrmm attempts to move the volume.

When the RETDATE is CATRETPD, this field contains the volume's current location.

PRTY
Defined or defaulted relative priority of the location.

RETDATE
Lists information for individual data sets and volumes. This field contains the retention date calculated by vital record processing. The meaning of the retention date depends on the retention type of the vital record specification. See *z/OS DFSMSrmm Guide and Reference* for information about how DFSMSrmm calculates the retention date.

BYDAYSCYCLE
For the BYDAYSCYCLE retention type, RETDATE is displayed as a special date format CYCL/*ccccc*. *ccccc* is the COUNT value for cycles used in the vital record specification.

CYCLES
For the CYCLES retention type, RETDATE is displayed as a special cycles date format, CYCL/*ccccc*, where *ccccc* is the COUNT value for cycles used in the vital record specification.

DAYS
For the DAYS retention type, RETDATE is displayed as the date calculated by vital record selection processing. This is the COUNT value added to the data set creation date or the volume assigned date.

EXTRADAYS
For the EXTRADAYS retention type, RETDATE is a date calculated by inventory management vital record processing. The RETDATE is the COUNT value in the vital record specification chain added to the date when the subchain started to retain the data set.

LASTREFERENCEDAYS
For the LASTREFERENCEDAYS retention type, RETDATE is displayed as the date calculated by the vital record selection processing. This is the COUNT value added to the date the data set or volume was last referenced.

UNTILEXPIRED
For the UNTILEXPIRED retention type, DFSMSrmm calculates the RETDATE based on the presence of a secondary vital record specification. When a secondary vital record specification retains a data set, the UNTILEXPIRED retention is based on the retention type in the secondary vital record specification. The retention type can be any of the date formats specified for CYCLES, DAYS, LASTRERENCEDAYS, WHILECATALOG, BYDAYSCYCLE, and EXTRADAYS. If the secondary vital record specification contains WHILECATALOG, the retention date is WHILECATLG as long as the data set is cataloged.

WHILECATALOG
Retention date for WHILECATALOG can be the special catalog date format, WHILECATLG or CATRETPD. When the RETDATE is WHILECATLG, the data set is retained by a vital record specification with the WHILECATALOG retention type and the data set is cataloged. CATRETPD is used when the data set is not cataloged and is created within the period defined by the parmlib OPTION CATRETPD operand. DFSMSrmm retains the data set for the catalog retention period if the data set has never been cataloged. DFSMSrmm does not retain the data set if DFSMSrmm detected that the data set was cataloged and then uncataloged during the catalog retention period. DFSMSrmm sets the REQUIRED field to the volume's current location and does not include the data set in the cycle count.

RETNAME
RETNAME displays the name of the current vital record specification in the primary vital record specification chain that retains the data set as follows:

- The first vital record specification in the subchain for ANDVRS groups
- An * if the retaining vital record specification is a data set name vital record specification in a primary vital record specification
- A blank for when a secondary vital record specification retains a data set

NUMBER OF DATA SETS RETAINED (GROUP STORE)
Lists two numbers. The first is the number of data sets or volumes retained by the vital record specification. The second is the number of data sets or volumes retained in a storage location.

Using the Inventory Management ACTIVITY File

DFSMSrmm provides the VERIFY function to perform a trial run of vital record processing and synchronize catalog processing so you can see the results of processing on a production run.

The ACTIVITY file is optional except during VERIFY processing. During VERIFY processing, the ACTIVITY file is required so that you can analyze processing results before they are actually performed. The ACTIVITY file is a pre-allocated DASD data

set, like the REPORT file. The ACTIVITY file is a variable blocked file with the record length set to the largest record created by DFSMSrmm. The block size is determined by the system.The ACTIVITY file is not intended to be a report, but to contain detailed information about changes made to data sets during DFSMSrmm processing. The DFSMSrmm supplied sample EDGJHKPA shows the JCL to allocate the ACTIVITY file.

DFSMSrmm writes an activity record for data set changes only when a change is identified in the ACTD_CHANGE section of the record. During processing if an ACTIVITY file is allocated, DFSMSrmm writes information about changes in the data set information, such as matching vital record specification, vital record status, retention date and catalog status to the ACTIVITY file. If VERIFY processing is being run, the changes are not actually made.

You can view the ACTIVITY file on-line. To print the ACTIVITY file, use a product like DFSORT or DFSORT ICETOOL to selectively format and print fields. DFSMSrmm provides a sample job EDGJACTP in SAMPLIB to print the ACTIVITY report. See *z/OS DFSMSrmm Reporting* for information about the reports you can produce with the sample job.

How Vital Record Processing Works

This section describes how vital record processing works.

1. You control how vital record processing works by using the EDGRMMxx parmlib OPTION command options CATRETPD, MOVEBY, RETAINBY, VRSJOBNAME, VRSCHANGE, VRSMIN, and VRSEL as described in “Defining System Options: OPTION” on page 122.
2. You must run vital record processing when you add or change a vital record specification for DFSMSrmm to apply the policy defined by the vital record specification. You should reclaim any volumes that are pending release or ready to return to scratch to avoid data loss. Use the RMM CHANGEVOLUME subcommand to change the status of these volumes to reclaim them
3. As part of vital record processing, DFSMSrmm checks that data set name masks and job name masks used in vital record specifications are specified according to DFSMSrmm naming conventions. *z/OS DFSMSrmm Guide and Reference* provides information on defining vital record specifications. DFSMSrmm compares the data set, job name, and volume information recorded in the control data set with information in the vital record specifications to determine which data sets and volumes to retain and the processing required. This includes any volumes with special JCL specified expiration dates used by your installation. See “Managing Volumes with Special Dates” on page 70.
4. DFSMSrmm deletes any vital record specifications that have reached their automatic deletion date from the control data set. When a vital record specification is deleted, no data set or volume information is changed. DFSMSrmm uses only the remaining vital record specifications to apply policies. If the data set or volume matches to another remaining vital record specification, DFSMSrmm applies those policies.
5. DFSMSrmm retains stacked volumes based on how the contained volumes are retained. The stacked volume is retained by a vital record specification if any contained volume is retained on a volume basis or data set basis. DFSMSrmm sets the stacked volume’s retention date to the highest retention date of all contained volumes. DFSMSrmm sets the required location of the stacked volume using location priority.
6. During vital record processing, DFSMSrmm records information about the matching vital record specification name and retention date that DFSMSrmm

sets for the data set or volume. If the data set or volume does not match to any vital record specifications, and is no longer retained by a vital record specification, the data sets are eligible for expiration processing.

7. DFSMSrmm saves movement and retention information in each volume record. DFSMSrmm also saves retention information in each data set record.
   - When a data set is retained by a vital record specification, DFSMSrmm sets the data set retention date to the date calculated during vital record processing.
   - When a data set is no longer retained by a vital record specification, DFSMSrmm sets the data set retention date to the date vital record processing started.
   - When a volume is pending release or scratch, or is no longer retained by a vital record specification, DFSMSrmm does not change the retention date that was already set.
   - DFSMSrmm uses the highest data set retention date on the volume to set the volume retention date.
8. See “Confirming Global Volume Movement” on page 276 for information about the global move confirmation processing that takes place during vital record processing.
9. Any volume no longer retained by a vital record specification is updated to indicate that it is not retained by a vital record specification and the retention date is set to the date that inventory management is run.

How DFSMSrmm Processes Vital Record Specification Chains

DFSMSrmm validates vital record specification chains by checking for the existence of the next link in a vital record specification chain. If the next link in the vital record specification chain is missing, DFSMSrmm issues message EDG2230I.

When the EDGRMMxx parmlib member OPTION VRSEL(NEW) operand is used, you can define policies using individual vital record specifications and vital record specification groups or subchains. During inventory management DFSMSrmm processes vital record specifications based on the parmlib VRSEL operand value you define. When a data set matches to a vital record specification, DFSMSrmm uses the retention information to retain the data set. Once the retention criteria has been met, the next vital record specification in the chain is used, and so on, until the end of the chain is reached. Each time you run vital record processing, DFSMSrmm processes from the start of the chain in case any of the earlier retention criteria apply again.

How DFSMSrmm Processes Primary and Secondary Vital Record Specifications

You can define both a primary and secondary vital record specification to retain a data set. DFSMSrmm matches the data set to the vital record specification based on data set name, jobname, management class, vital record specification management value, the ABEND and OPEN reserved names, or the '**' data set name mask. DFSMSrmm matches the data set to the secondary vital record specification based on management class or vital record specification management value if the primary match is on data set name, but not '**'.

When you use the parmlib member EDGRMMxx OPTION VRSEL(NEW) operand, DFSMSrmm uses the following criteria to retain the data set:

- Retained by the primary data set name vital record specification

  Location is taken from the primary data set name vital record specification. Retention date is calculated based on the values set in the current subchain of

the primary vital record specification. Release actions are determined by values set in the primary vital record specification.

- Retained by the primary data set name vital record specification including the UNTILEXPIRED retention type in the current subchain

  Location is taken from the primary data set name vital record specification. Retention date is calculated based on the values set in both the primary vital record specification and the secondary vital record specification. The retention date is the earliest date of the two current vital record specifications. Release actions are determined by values set in the primary vital record specification.
- Retained by the secondary vital record specification and not the primary vital record specification

  Location is taken from the secondary vital record specification. Retention date is the calculated based on the value set in the secondary vital record specification. Release actions are determined by values set in the secondary vital record specification.
- Not retained by any vital record specification

  The data set is not retained as a vital record. Release actions are determined by values set the last time the data set was retained as a vital record.

Combining Retention Types

When you use the parmlib OPTION VRSEL(NEW) operand, you can define vital record specifications so that DFSMSrmm retains the data set or volume by combining the retention information from two vital record specifications. When the EDGRMMxx parmlib OPTION VRSEL(NEW) operand is used, DFSMSrmm processes both primary and secondary vital record specifications to retain a data set. DFSMSrmm can combine retention information from the two vital record specifications and apply the combined retention to a data set. Use the UNTILEXPIRED retention type in the primary vital record specifications to combine its retention with the retention in the secondary vital record specification. When UNTILEXPIRED is specified in a primary vital record specification, DFSMSrmm looks at the secondary vital record specification to determine if UNTILEXPIRED is true or not. If DFSMSrmm finds no secondary vital record specification that matches a data set or if UNTILEXPIRED is specified in the secondary vital record specification, then DFSMSrmm uses the volume expiration date to determine if UNTILEXPIRED is true or not.

How DFSMSrmm Selects Retention and Movement Policies

DFSMSrmm retains data sets and volumes based on policies you define in vital record specifications by matching data sets and volumes to vital record specifications. DFSMSrmm matches data sets with vital record specifications based on the data set name and job name specified in the vital record specification.

You can define policies for specific data sets and volumes. You can also define system-wide policies for all data sets not covered by a specific policy.

The data set name masks ** and primary vital record specification *.** match to all data sets not covered by a more specific vital record specification. DFSMSrmm matches a vital record specification with the data set name mask *.** to a data set before matching to a vital record specification with a vital record specification management value. DFSMSrmm uses the vital record specification with the data set name mask ** to cover any data sets that do not match to any other vital record specifications. You can use these data set name masks to define a system-wide retention policy.

When you specify the parmlib OPTION VRSEL(NEW), DFSMSrmm matches a data set to a secondary vital record specification when the data set first matches to a vital record specification with a data set name mask *.**.

You can select how DFSMSrmm uses data set name and job name in matching with the parmlib OPTION VRSJOBNAME operand described in “Defining System Options: OPTION” on page 122. *z/OS DFSMSrmm Guide and Reference* provides information on defining vital record specifications and how to retain and move data sets and volumes.

Considerations for Retaining Data Sets and Volumes

Any volumes that are currently open or left open are listed in message EDG2404W. If you do not want to retain those volumes that are left open from processing errors or abends, you can use the RMM DELETEVOLUME *volser* RELEASE command to release those volumes.

You can also define vital record specifications with the reserved data set name mask OPEN to manage volumes left open. You can use the reserved data set name mask ABEND in a vital record specification to specify policies for data sets closed as a result of an abnormal end in a task. See *z/OS DFSMSrmm Guide and Reference* for information on defining vital record specifications.

Data sets and volumes that have reached or passed their expiration date and that are not to be retained are subject to normal expiration and release processing. You can control when DFSMSrmm releases volumes using the parmlib OPTION VRSEL(NEW) operand. After specifying the VRSEL(NEW) operand, you can define vital record specifications that ignore the expiration date so that volumes are released before their expiration date. See “How Expiration Processing Works” on page 274 for more information.

Moving Volumes

During inventory management, DFSMSrmm identifies the destination for a volume. DFSMSrmm uses the location priority value to resolve movement conflicts when a volume is destined for more than one location. Priority values as shown in Table 48 are purely relative and do not have any further significance. If more than one destination is identified, and the locations are not the same, the DFSMSrmm default priorities are based on the following:

- If none of the locations are storage locations, DFSMSrmm selects the most automated location based on the location priority.
- If one or more storage locations is specified for a single volume, DFSMSrmm stores the volume in the location based on the DFSMSrmm default location priority, the priority set in the LOCDEF command for the location, or the priority specified in a vital record specification. The lower priority numbers take precedence. For example, a volume would move to a location with a priority value 100 before moving to a location with a priority value of 200. You can set a priority value with the PRIORITY operand on the LOCDEF parmlib command to define the relative importance of locations.

  You can define PRIORITY on RMM ADDVRS subcommands to override default or assigned priorities at the data set level. When you do not set a priority value, DFSMSrmm uses the priority shown in Table 48.

Table 48. DFSMSrmm Movement Priority Default Values

Priority Number	Location Name or Location Type
100	REMOTE DFSMSrmm built-in storage location name
200	DISTANT DFSMSrmm built-in storage location name

Table 48. DFSMSrmm Movement Priority Default Values (continued)

Priority Number	Location Name or Location Type
300	LOCAL DFSMSrmm built-in storage location
2000	Installation defined storage locations
4800	AUTO automated tape libraries
4900	MANUAL manual tape libraries
5000	SHELF location name

For stacked volumes, DFSMSrmm determines the required location using the required location of each of the volumes in the same container that is retained by a vital record specification. Conflicts in locations are resolved using movement priority.

Volumes requiring movement are identified for storage location management processing. Storage location management processing sets the destination for the volume and allocates shelf locations, based on the destination specified in the vital record specification. See “How Storage Location Management Processing Works” on page 272 for more information.

You can request that DFSMSrmm retain a volume in its existing location instead of specifying a storage location or the home location. You define the location in a vital record specification using the CURRENT reserved location name. When you run vital record processing, DFSMSrmm keeps the volume in the current location rather than scheduling the volume for a move.

Inventory Management Trial Run

You can run a trial run of inventory management vital record processing before DFSMSrmm makes the changes. The trial run lets you see how the vital record specifications you defined would be processed in a production run except that DFSMSrmm does not make any changes to the control data set.

1. Allocate the ACTIVITY file that DFSMSrmm uses to record data set changes that would result during inventory management vital record processing.
2. Submit an inventory management job using JCL as shown in Figure 133 on page 261 to request a trial run of vital record processing. Perform step 3, 4, and 5 until you are satisfied that the correct policies are in place.
3. Analyze the ACTIVITY file to see what changes would have occurred based on the vital record specifications you defined.
4. Change vital record specifications by deleting and adding vital record specifications as needed to correct the policies you want in place.
5. Check the EDGRMMxx member OPTION VRSCHANGE operand value. Make sure VRSCHANGE(VERIFY) is specified so that DFSMSrmm issues message EDG2308I if any changes are made since the last run of inventory management.
6. Submit an inventory management job requesting a production run of vital record processing after you have completed making changes to the vital record specifications.

Running Storage Location Management Processing

Request storage location management processing when you are using vital record specifications to identify data sets and volumes to be moved between locations or using RMM TSO CHANGEVOLUME subcommands to move volumes between system-managed libraries and between storage locations. Manual moves using the

RMM CHANGEVOLUME subcommand could be used to support dynamic shelf-management. Vital record processing sets the required location where a volume should be stored. Storage location management sets the destination for the volume and optionally assigns the exact shelf location to be used for the volume while it is in the storage location.

JCL for Storage Location Management Processing

To request storage location management processing, specify the DSTORE parameter. You can submit a job with JCL similar to Figure 135:

```
//HSKP     EXEC PGM=EDGHSKP,
//      PARM='DSTORE'
//MESSAGE  DD DISP=SHR,DSN=HSKP.MESSAGES
```

Figure 135. Example of JCL for Storage Location Management Processing

How Storage Location Management Processing Works

Storage location management processing assigns volume destinations and sets required volume destinations based on the results of other inventory management functions. Storage location management must be run after vital record processing because the volume destinations are determined by vital record processing. See “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support is Enabled” on page 89 and “DFSMSrmm Support for Stacked Volumes When Stacked Volume Support Is Not Enabled” on page 93 for information about the processing sequence you must use when a VTS is in use. See “Confirming Global Volume Movement” on page 276 for information about the global move confirmation processing that takes place during vital record processing.

Storage location management processing assigns a shelf location, known as the bin number, to volumes moving to and among shelf-managed storage locations and sets a destination storage location. If the volume destination is a system-managed tape library, DFSMSrmm does not assign a bin number.

When you have enabled stacked volume support, storage location management is performed for stacked volumes, not for contained volumes. For contained volumes, the location of the stacked volume identifies the contained volume location. DFSMSrmm sets the required location for the stacked volume based on the required location defined for all volumes contained in the stacked volume. At the completion of export processing, the stacked volume has a required location. The required location is set during export based on the required location and priority of each exported volume. At the completion of export processing, the required location is used to set a destination if the location is not a shelf-managed storage location. If the destination location is shelf-managed, DFSMSrmm sets the destination during storage location management and assigns a bin number.

When you do not enable stacked volume support, DFSMSrmm does not consider the stacked volume when performing storage location management.

DFSMSrmm marks volumes not residing in a system-managed library as being ’intransit’ at this time. Volumes in system-managed libraries are marked as being ’intransit’ only after you eject them.

We recommend that after successful storage location processing, you schedule a job or job step to eject all volumes to be moved using the bulk output station. To automatically eject physical volumes, add the job step shown in Figure 136 on page 273

page 273 to the job that runs EDGHSKP vital record processing and storage location management processing.

```
// EXEC PGM=IKJEFT01
//SYSTSPRT DD SYSOUT=*
//SYSTSIN  DD *
 RMM SEARCHVOLUME VOLUME(*) OWNER(*) LIMIT(*) -
   LOCATION(atlname) DESTINATION(storename) -
   INTRANSIT(N) CLIST('RMM CHANGEVOLUME ',' EJECT(BULK)')
 EXEC EXEC.RMM.CLIST
/*
```

Figure 136. Automatically Ejecting Volumes from System-managed Libraries

The job step shown in Figure 136 runs the batch TMP and uses DFSMSrmm TSO subcommands to produce a list of volumes to be ejected and then uses the list to initiate the ejects. To eject stacked volumes, you can use the same DFSMSrmm TSO subcommands that you used for physical volumes to generate a list to be ejected, but you must use the list to enter the requests at the Library Manager console.

You can override automatic vital record specification location selection by using the RMM CHANGEVOLUME subcommand. See “Using Manual Move Control” on page 113 for more information.

To select a suitable bin number for a volume moving to a storage location, DFSMSrmm uses the volume media name and the LOCDEF media names. If the media name is specifically defined on LOCDEF, DFSMSrmm looks for a bin number which is empty and uses the same media name. If the specific media name is not found, DFSMSrmm checks if '*' is defined on the LOCDEF command. If it is, then DFSMSrmm looks for a bin with a media name of '*'. If neither the specific media name nor '*' is found on the LOCDEF command, then the volume cannot be sent to that location, and DFSMSrmm issues message EDG2412E.

To determine if a volume move is required, DFSMSrmm uses vital record processing information. If a move to a shelf-managed storage location is required, DFSMSrmm selects an empty bin in the target location and assigns it to the volume based on media name and LOCDEF information.

If there are no empty bin numbers available in a storage location, DFSMSrmm issues message EDG2403E. Inventory management continues and DFSMSrmm does not change the status of the volumes destined for a storage location which has no empty bin numbers. The volumes are moved in subsequent inventory management runs after more empty bin numbers are added, or when existing bin numbers are freed by other volumes being moved out of the storage location. After you have corrected the problem, request storage location management processing again.

If you have implemented volume movement by set, DFSMSrmm sets a common required location for all the volumes in the set that are retained by vital record specifications based on the priority of each volume’s required location. See “Defining System Options: OPTION” on page 122 for information about implementing volume movement by set using the DFSMSrmm EDGRMMxx parmlib OPTION command MOVEBY(SET) operand.

Running Expiration Processing

During expiration processing, DFSMSrmm:

- Identifies volumes not required for vital records that are ready to expire by checking the expiration date.
- Determines the type of release action, if any, needed for the volumes that have reached their expiration date.
- Manages the release actions for each volume before returning it to the scratch pool or removing it from the library.
- Uncatalogs all data sets for volumes returning to scratch status if you have specified UNCATALOG(Y or S) in parmlib member EDGRMMxx.
- Removes the catalog entry and uncatalogs all parts of the data set across all volumes in the set for a multivolume data set which are recorded in the DFSMSrmm control data set.
- Optionally, updates RACF tape security profiles for volumes returning to scratch status.
- Ensures all volumes in a set are not expired if any one volume does not expire when the EDGRMMxx parmlib option RETAINBY(SET) is in use.

JCL for Expiration Processing

To request expiration processing, specify the EXPROC parameter. You can submit a job with JCL similar to Figure 137:

```
//HSKP     EXEC PGM=EDGHSKP,
//     PARM='EXPROC'
//MESSAGE  DD DISP=SHR,DSN=HSKP.MESSAGES
```

Figure 137. Example of JCL for Expiration Processing

How Expiration Processing Works

DFSMSrmm checks the expiration date for volumes not retained by a vital record specification. If the expiration date has been reached, DFSMSrmm changes the volume status to ‘pending release’. DFSMSrmm checks for any actions that should be taken before the volume can be released. DFSMSrmm defers most release actions for later processing. However, DFSMSrmm processes the ‘notify owner’ release action immediately if an electronic address is provided for the owner and the DFSMSrmm system option NOTIFY is in use.

When a data set is no longer retained by a vital record specification, DFSMSrmm considers the volume on which the data set resides for release processing. The volume is released only if no data set on the volume is retained by a vital record specification. If you use the parmlib VRSEL(NEW) option and the RMM ADDVRS RELEASE(EXPIRYDATEIGNORE) operand, DFSMSrmm ignores the volume expiration date and uses information in a vital record specification to control retention.

When a volume reaches its expiration date, and is not being retained by a vital record specification, it is not immediately returned to scratch or its owner. Two runs of expiration processing are needed to return a volume. The first run of expiration processing sets the volume status to pending release. Expiration processing must be run a second time to complete the return. DFSMSrmm does not change the volume status during the first run of expiration processing. DFSMSrmm marks the volume as pending release. No other information is changed in case the volume is

reclaimed before it is returned to scratch status. Requiring two runs of expiration processing provides time to make changes to the volume status before the volume is released. If you do not need to run expiration processing in two runs, you can use the parmlib VRSEL(NEW) option and the RMM ADDVRS RELEASE(SCRATCHIMMEDIATE) operand to return the volumes to scratch status in only one run.

See “Confirming Global Volume Movement” on page 276 for information about the global move confirmation processing that takes place during vital record processing.

If you have implemented volume retention by set, DFSMSrmm retains all volumes in a volume set if any volume in the set is retained. DFSMSrmm sets the retention date for all the volumes in the set to the highest retention date for the volumes in the set. See “Defining System Options: OPTION” on page 122 for information about implementing volume retention by set using the DFSMSrmm EDGRMMxx parmlib OPTION command RETAINBY(SET) operand.

Returning Volumes to Scratch Status

DFSMSrmm returns volumes to scratch that are already in ‘pending release’ status and require no other action than returning to scratch. These volumes are available to satisfy scratch mount processing or RMM TSO GETVOLUME subcommand requests.

When DFSMSrmm returns a volume to scratch status, DFSMSrmm clears the following information from the control data set:

- Volume description.
- Jobname.
- Accounting information.
- Access list.
- Volume owner.
- Owner access.
- Software product details. DFSMSrmm removes the volume from the product’s list of volumes.

DFSMSrmm updates the volume information to indicate that the volume is no longer retained by a vital record specification. When DFSMSrmm finds that a volume has been released manually using the RMM DELETEVOLUME subcommand but is still retained by a vital record specification, DFSMSrmm sets the retention date to the current date in addition to updating the volume information to indicate that the volume is no longer retained by a vital record specification.

During inventory management expiration processing, DFSMSrmm calls the EDGUX200 installation exit. The exit is called every time a volume is identified as ready to return to scratch. See “Using the DFSMSrmm EDGUX200 Installation Exit” on page 220 for information on the EDGUX200 installation exit processing.

In addition, DFSMSrmm requests that all data sets recorded in the control data set for the volume are uncataloged. DFSMSrmm performs RACF processing as described in Table 29 on page 165.

Tracking Volumes with Permanent Errors

DFSMSrmm keeps track of permanent I/O errors for a volume. During each run of expiration processing, DFSMSrmm sets the release actions for volumes that are not pending release. During the run volumes that are marked with the return to scratch

release action, that have permanent I/O errors will be marked for replacement. DFSMSrmm only identifies those volumes with the ‘return to scratch’ release action, not those with the ‘return to owner’ action.

Use the RMM SEARCHVOLUME subcommand to obtain information about volumes that might need replacement. You can use the extract data set or the DFSMSrmm ISPF dialog to check for volumes with temporary errors. See “JCL for Creating an Extract Data Set” on page 280 for information about using the extract data set to identify volumes with temporary errors.

Managing Open Data Sets

DFSMSrmm produces a report in the MESSAGE file as shown in Figure 138 that lists tape data sets that might be open as well as messages describing expiration processing.

```
EDG2404W VOLUME 111020 FOR JOB STSGGWC1 IS OPEN - VOLUME HAS EXPIRATION DATE 16/03/1993
EDG2404W VOLUME 111023 FOR JOB STSGGWC1 IS OPEN - VOLUME HAS EXPIRATION DATE 16/03/1993
EDG2229I NUMBER OF VRS RECORDS READ IS 14
EDG2420I TOTAL VOLUMES READ                          =             1970
EDG2421I TOTAL VOLUMES UPDATED                       =              330
EDG2422I TOTAL VOLUMES, THIS RUN, KEPT FOR VRS       =               50
EDG2423I TOTAL VOLUMES, THIS RUN, ASSIGNED TO STORES =               85
EDG2424I TOTAL VOLUMES, THIS RUN, SET PENDING RELEASE =              126
EDG2425I TOTAL VOLUMES RETURNED TO SCRATCH           =               55
EDG2429I MAIN INVENTORY MANAGEMENT UPDATES HAVE COMPLETED SUCCESSFULLY
EDG2307I INVENTORY MANAGEMENT TASK VRSEL    COMPLETED SUCCESSFULLY
EDG2307I INVENTORY MANAGEMENT TASK DSTORE   COMPLETED SUCCESSFULLY
EDG2307I INVENTORY MANAGEMENT TASK EXPROC   COMPLETED SUCCESSFULLY
EDG2307I INVENTORY MANAGEMENT TASK RPTEXT   COMPLETED SUCCESSFULLY
EDG6401I MASTER FILE BACKUP SUCCESSFUL
```

Figure 138. Expiration Processing Report

These might be valid cases, or jobs that are currently active. However, some data sets on the list might be produced by a job that failed so the data set was never closed. Review this list and make the necessary corrections. The expiration date in the message, shows when the volume will be automatically released. During vital record processing, DFSMSrmm matches open data sets to vital record specifications using the OPEN reserved data set name mask or to vital record specifications defined with data set name masks.

Confirming Global Volume Movement

Vital record processing determines the volume movements required and storage location management processing assigns the volume destinations. You must ensure that volume movements are completed and confirmed to DFSMSrmm.

You use the RMM subcommands and DFSMSrmm ISPF dialog to confirm that volume movements have taken place. You use the RMM CHANGEVOLUME * CONFIRMMOVE subcommand to change the status of a volume move from PENDING to CONFIRMED. You can perform confirmation for a single volume or for multiple volumes. Performing confirmation for multiple volumes is called global confirmation. In DFSMSrmm, confirmation means to issue a command to notify DFSMSrmm that a volume has moved to a location or that a release action defined for a volume has been completed. If you perform confirmation for a single volume, DFSMSrmm processes the confirmation immediately. If you issue a request for a global confirmation, DFSMSrmm processes the global confirmation during inventory management processing.

Global move confirmation is performed as part of DFSMSrmm inventory management. DFSMSrmm performs move confirmation for a volume, prior to making any other updates to a volume, as part of the following inventory management functions:

- Vital record processing
- Storage location management processing
- Expiration processing

If a volume move is outstanding, and it has been globally confirmed, DFSMSrmm performs confirmation of the move for that volume. DFSMSrmm confirms moves in progress prior to starting any new moves that might be set by the current inventory management run. If each of the inventory management functions is in a separate job step, then global move confirmation is performed once for each step. If the inventory management functions are run in a single job step, DFSMSrmm performs global move confirmation once.

The timing of the inventory management runs is very important. Here are some things to consider:

- If you requested global move confirmation and want to change it, you can undo the request prior to the next run of inventory management. You can use the RMM CHANGEVOLUME subcommand to undo global confirmation of volume moves. After the next run of inventory management, DFSMSrmm will have confirmed the volume moves making undoing the confirmation of the moves difficult.
- When you request an extract data set to be used for generating movement or inventory reports, consider the timing of inventory management functions. An extract data set produced after a run of vital record processing and storage location management processing, contains the information of new volume movement for movement reports. An extract data set produced after a global confirm move and a run of any of the listed inventory management functions, contains information about volumes after moves have been confirmed.
- To make scratch volumes available after a move and when you use global move confirmation, make sure you run expiration processing to complete the global move confirmation and return the moved volumes to scratch status.

Confirming Global Release Actions

If the RMM CHANGEVOLUME subcommand with * CONFIRMRELEASE operands is issued to confirm global release actions, for any volume with the action outstanding, DFSMSrmm marks the corresponding action complete. Global release action confirmation takes place during expiration processing just prior to when DFSMSrmm performs a check for outstanding global confirmation or if the volume expiration date has been reached. If the ‘return to owner’ action is confirmed, the volume is deleted from the DFSMSrmm control data set. If the erase or initialize release actions are confirmed, DFSMSrmm deletes the data set information for those volumes with the actions outstanding. If erase is confirmed, DFSMSrmm sets the initialize action as outstanding so that the correct volume labels can be written to the erased volume.

If the RMM DELETEVOLUME subcommand with the RELEASE operand was issued, DFSMSrmm changes the volume status to ‘pending release’ during subcommand processing. Use expiration processing to complete the release process. These volumes are returned to scratch during the first EDGHSKP run, if no other release actions are required.

Backing Up the Control Data Set

You can use EDGHSKP to back up both the control data set and the journal by specifying the BACKUP DD statement and the JRNLBKUP DD statement while the DFSMSrmm subsystem is active. You can also back up the control data set using the EDGBKUP utility described in “Chapter 16. Maintaining the Control Data Set” on page 287. One difference between using the EDGHSKP utility and the EDGBKUP utility is that when using the EDGHSKP utility to back up the control data set, DFSMSrmm clears the journal data set. You can specify BACKUP(DSS) without using concurrent copy. If you specify BACKUP(DSS) and you use concurrent copy, DFSMSrmm clears the journal only if you also back up the journal.

If the subsystem is not active, you must use the EDGBKUP utility to back up the control data set and journal. When you use EDGBKUP, the journal data set is not cleared. For more information on EDGBKUP, see “Chapter 16. Maintaining the Control Data Set” on page 287.

We recommend that you schedule regular backups for both the control data set and journal. You should plan to keep multiple backup copies, so that, should a backup fail, you still have a previous, successful backup from which to recover. Remember that the journal backup taken at the same time as the control data set backup is to be used with the previous control data set backup. Use the current journal with the most recent control data set backup to forward recover to the point of failure.

When backup is performed using the DFSMSdss DUMP command, plan to keep backup copies for both the control data set and the journal. For any backup being restored, a journal backup is also required for forward recovery. For the latest control data set backup, both the latest journal backup and the current journal must be used for forward recovery.

You can automate the backup of the control data set and the clearing of the journal as described in “Automating Control Data Set Backup and Journal Clearing” on page 290. Clearing out the journal data set regularly prevents the journal from becoming full, and thus reduces the risk of losing the updates to the control data set.

JCL for Backing Up the Control Data Set

To create a backup copy using EDGHSKP, specify the BACKUP parameter. You can submit a job with JCL as shown in Figure 139:

```
/*
//EDGHSKP  EXEC PGM=EDGHSKP,PARM='BACKUP(DSS)'
//MESSAGE  DD DISP=SHR,DSN=RMM.MESSAGE
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.CDS(+1),
//         LABEL=(,SL)
//JRNLBKUP DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.JRNL(+1),
//         DCB=(RECFM=VB,BLKSIZE=8460,LRECL=8456),
//         LABEL=(2,SL),VOL=REF=*.BACKUP
//DSSOPT   DD *
    CONCURRENT OPTIMIZE(1) VALIDATE
/*
```

Figure 139. Example of JCL for Backing Up the Control Data Set

Specify the JRNLBKUP DD statement only if you want to back up the journal. See "Customizing the DSSOPT DD Statement" for information about changing the DSSOPT DD statement.

Note: The names of the control data set and journal are obtained from the running DFSMSrmm subsystem. Do not specify the data set names in the JCL. If you do, the job fails.

Specify BACKUP(DSS) when you want to use DFSMSdss to perform the back up. You do not need to use concurrent copy to specify BACKUP(DSS). Using DFSMSdss concurrent copy permits the update of the control data set during backup processing so that all tape activities can continue during backup processing. To use DFSMSdss concurrent copy, you must have a concurrent copy environment set up. If you specify BACKUP(DSS) without concurrent copy, you can still direct the output to tape. All other updates to the control data set will wait until the control data set backup completes.

Customizing the DSSOPT DD Statement

You can use the DSSOPT DD statement to specify customized operands for the DUMP and RESTORE commands used by DFSMSrmm. You might customize the operands based on the media used for the backup and the resource you have available.

Figure 140 shows the DFSMSdss DUMP and RESTORE commands issued by DFSMSrmm.

```
DUMP DS(INCLUDE(cds_name)) OUTDD(BACKUP) SHARE -
   COMPRESS CONCURRENT VALIDATE OPTIMIZE(1)

RESTORE DS(INCLUDE(**)) INDD(BACKUP) -
    REPLACE
```

Figure 140. DFSMSdss Commands Issued by DFSMSrmm

You can change the second line of the DUMP and RESTORE commands in the examples shown in Figure 140. If you decide to change the commands, specify all the operands you want to be processed because DFSMSrmm uses your input to replace its own.

Use the JCL shown in Figure 141 to ensure that DFSMSdss does not compress the data. The tape hardware will be used to compress the records.

```
//EDGBKUP  EXEC PGM=EDGBKUP,PARM='BACKUP(DSS)'
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.CDS(+1),
//         LABEL=(,SL)
//JRNLBKUP DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.JRNL(+1),
//         LABEL=(2,SL),VOL=REF=*.BACKUP
//DSSOPT   DD *
    CONCURRENT OPTIMIZE(4) VALIDATE
/*
```

Figure 141. Changing DFSMSdss Commands for Backing up to Tape

The DUMP command operands you can specify in the DSSOPT DD statement are controlled and validated by DFSMSdss, not by DFSMSrmm. If you specify an

unsupported command operand, DFSMSdss fails the dump operation. Refer to *z/OS DFSMSdss Storage Administration Reference* for the supported command operands.

The DSSOPT DD statement can be specified for both dump and restore operations. DFSMSrmm reads all the records and uses them to replace its default command operands beginning at the second line. You can include comments in the DSSOPT records but they must be comments acceptable to DFSMSdss.

How Backup Processing Works

DFSMSrmm produces a backup copy of the control data set and journal using the access method services REPRO command or DFSMSdss DUMP command. DFSMSrmm backs up the control data set and then the journal. DFSMSrmm resets the journal data set and discards journal records if the back up completes successfully. When using DFSMSdss concurrent copy, the successful back up includes the control data set and the journal.

If a job that opens or closes a tape data set tries to update the control data set during AMS REPRO backup processing, DFSMSrmm waits for up to five minutes. If backup is still in progress, DFSMSrmm issues a write-to-operator message EDG4010D that prompts the operator to retry or cancel each job. If the operator specifies retry, DFSMSrmm retries the job five more times at minute intervals before again issuing a write-to-operator if backup processing has not been completed.

Backup using DFSMSdss enables output directly to tape. Using DFSMSdss concurrent copy allows simultaneous updates to the DFSMSrmm control data set so that other tape activity need not be interrupted.It is not necessary to use DFSMSdss concurrent copy when you specify BACKUP(DSS).

Creating an Extract Data Set

As part of inventory management, you can request an extract data set that contains information from the control data set. Use the extract data set as input to EDGRPTD, the DFSMSrmm reporting utility and the EDGRRPTE exec to create reports. See *z/OS DFSMSrmm Reporting* for information about using EDGRPTD and EDGRRPTE.

JCL for Creating an Extract Data Set

To create an extract data set, specify the RPTEXT parameter. You can submit a job with JCL as shown in Figure 142:

```
//HSKP     EXEC PGM=EDGHSKP,
//      PARM='RPTEXT,DATEFORM(E)'
//MESSAGE  DD DISP=SHR,DSN=HSKP.MESSAGES
//REPTEXT  DD DISP=SHR,DSN=MASTER.EXTRACT
```

Figure 142. JCL for Creating an Extract Data Set

Use the DATEFORM parameter to specify the format for date fields in the report extract data set. The DATEFORM parameter can take any of the following values:

Value	Language	Format	Example
A	American	mm/dd/yyyy	12/15/1994
E	European	dd/mm/yyyy	15/12/1994

Value	Language	Format	Example
I	ISO	yyyy/mm/dd	1994/12/15
J	Julian	yyyy/ddd	1994/349
D	Default	Installation's default in EDGRMMxx	Initially set to Julian

DFSMSrmm provides the format of the records in the extract data set in mapping macros. See *z/OS DFSMSrmm Reporting* for layouts of the macros. You can use DFSORT to sort the extract data set records to create many types of reports.

For example, you could select the extract records that show volumes with temporary read errors. Sort the resulting list by descending number of errors. Use this list to identify the damaged volumes that should be replaced. Then, you could use the RMM CHANGEVOLUME subcommand with the RELEASEACTION(REPLACE) operand to update DFSMSrmm with the required action.

You can also create reports by using the DFSMSrmm SEARCH facilities provided with the DFSMSrmm TSO subcommands and DFSMSrmm ISPF dialog.

How Report Extract Processing Works

DFSMSrmm reads sequentially through its control data set, and creates a record in the extract data set for each shelf location, volume, data set, software product, owner and vital record specification records. DFSMSrmm can convert information like the date information into a format you specify. The extract data set is a point-in-time copy of the control data set contents. Use the RMM TSO SEARCH and LIST subcommands to obtain the most current information.

Return Codes for EDGHSKP

EDGHSKP issues one of the return codes shown in Table 49.

Table 49. EDGHSKP Return Codes

Return Code	Explanation
0	All requested functions completed successfully.
4	DFSMSrmm encountered a minor error during processing. It issues a warning message and processing continues.
8	DFSMSrmm has stopped at least one requested function. Processing continues with the next requested function.
12	A severe error occurred during processing of one of the requested functions. DFSMSrmm stops the utility.
16	A severe error occurred during a required communication with the DFSMSrmm subsystem. DFSMSrmm stops the utility.

Chapter 14. Creating Reports with DFSMSrmm

Note

- Information about creating inventory and movement reports with DFSMSrmm has been moved to *z/OS DFSMSrmm Reporting*.
- You will find these topics:
  - Creating Inventory and Movement Reports using the DFSMSrmm EDGRPTD utility.
  - Creating reports using DFSMSrmm-supplied samples.
  - Creating security and audit reports using the DFSMSrmm EDGAUD utility.

© Copyright IBM Corp. 1992, 2001

Chapter 15. Creating Reports and Commands with DFSORT's ICETOOL

Note

- Information about creating reports and commands with DFSORT's ICETOOL has been moved to *z/OS DFSMSrmm Reporting*.
- You will find these topics:
  - Using DFSMSrmm-supplied samples.
  - Creating DFSMSrmm SMF audit record reports.
  - Producing commands and reports from the DFSMSrmm extract data set.
  - Using DFSORT with the DFSMSrmm ACTIVITY file.

© Copyright IBM Corp. 1992, 2001

Chapter 16. Maintaining the Control Data Set

DFSMSrmm Samples Provided in SAMPLIB

- EDGJBKUP Sample JCL for Using the Backup Program
- EDGJUTIL Sample JCL for Initializing the Control Data Set

Use the DFSMSrmm utilities EDGHSKP or EDGBKUP for backing up and restoring the control data set. Use EDGHSKP as described in “Backing Up the Control Data Set” on page 278 when DFSMSrmm is active and EDGBKUP when DFSMSrmm is stopped or quiesced. Use EDGBKUP to:

- Back up the control data set to a non-VSAM data set or a VSAM cluster
- Back up the journal
- Restore the control data set by returning a backup of the control data set and, optionally, forward recover it
- Forward recover a control data set by applying journal updates to a copy of the control data set
- Reorganize the control data set
- Move the control data set and journal to different device types

Use EDGUTIL to:

- Create the control data set control record in an empty VSAM data set
- Update an existing control data set control record
- Verify control data set information to diagnose errors in the control data set
- Check that control data set information about a volume’s status and the library in which it resides are consistent with the TCDB information, and optionally the Library Manager database information
- Detect consistency errors in control data set information created during conversion activities and fix the errors detected
- Enable selected functions
- Synchronize the TCDB and Library Manager information from information in the DFSMSrmm control data set

Backing Up and Restoring the Control Data Set: EDGBKUP

You can use EDGBKUP independently of DFSMSrmm to back up, restore, and reorganize the DFSMSrmm control data set and to back up the journal. When you use EDGBKUP to back up the control data set, DFSMSrmm does not clear the journal data set.

See “Step 19: Starting DFSMSrmm” on page 45 for information about stopping or quiescing DFSMSrmm to allow processing for restoring or reorganizing the control data set.

You can use EDGBKUP with DFSMSdss DUMP, or RESTORE commands, or the access method services REPRO command. When you use DFSMSdss concurrent copy, DFSMSrmm allows updates to the DFSMSrmm control data set.

EDGBKUP links to IDCAMS or ADRDSSU to perform either a restore or backup of the control data set. EDGBKUP links to IDCAMS to perform a back up of the

© Copyright IBM Corp. 1992, 2001

journal data set.You can see the commands and the messages produced in the SYSPRINT data set. The DFSMSrmm journal data sets and backup copies that EDGBKUP produces are in a format that only DFSMSrmm understands. You must not attempt to selectively copy, edit, or sort these data sets.

You can also back up the control data set and reset the journal using EDGHSKP, if you request backup as part of inventory management processing. Note that if you clear the journal before backups are taken, you lose the recorded changes since the last backup. Without these latest changes, a forward recovery can only recover the control data set up to that last backup before the journal was cleared. For more information about using EDGHSKP, see “Backing Up the Control Data Set” on page 278.

This section describes the EXEC parameters for EDGBKUP and provides JCL examples to back up the control data set and journal, restore the control data set, and reorganize the control data set.

JCL for EDGBKUP

Figure 143 shows the JCL for EDGBKUP:

```
//EDGBKUP  EXEC PGM=EDGBKUP,PARM='BACKUP(DSS)'
//SYSPRINT DD SYSOUT=*
//MASTER   DD DISP=SHR,DSN=RMM.CDS
//JOURNAL  DD DISP=SHR,DSN=RMM.JOURNAL
//BACKUP   DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.CDS(+1),
//         LABEL=(,SL)
//JRNLBKUP DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.JRNL(+1),
//         LABEL=(2,SL),VOL=REF=*.BACKUP,LRECL=32756,
//         BLKSIZE=32760,RECFM=VB
```

Figure 143. JCL Example for EDGBKUP

EXEC Parameters for EDGBKUP

Figure 144 shows the EXEC parameters for EDGBKUP:

Figure 144. EDGBKUP EXEC Parameters

BACKUP(DSS/NREORG/REORG)

Specify BACKUP(NREORG) when you do not want the control data set reorganized during backup processing. NREORG is the default. DFSMSrmm uses IDCAMS to back up the control data set and the journal data set and to restore the control data set from the backup.

Specify BACKUP(REORG) when you want the control data set reorganized during backup processing. DFSMSrmm uses IDCAMS to back up the control data set and the journal data set.

Specify BACKUP(DSS) when you want to use DFSMSdss to back up the control data set. DFSMSrmm uses DFSMSdss to back up the control data set and IDCAMS to back up the journal. To allow updates to the control data set

during backup processing, you must have the DFSMSdss concurrent copy environment set up. You must have the hardware and software required to establish a concurrent copy session. If you specify BACKUP(DSS) without establishing a concurrent copy session, backup processing continues. DFSMSrmm does not, however, allow updates to the control data set until the control data set backup completes. If DFSMSrmm is active and you specify BACKUP(DSS), DFSMSrmm allows the use of tape for the output of the backup.

You should ensure that all systems, including those used for business recovery purposes, are on the level of code supporting DFSMSdss concurrent copy. Backups taken using DFSMSdss cannot be restored using prior levels of EDGBKUP. However, they can be restored using a combination of DFSMSdss for restore, and the EDGBKUP utility for forward recovery.

When you specify that backup uses DFSMSdss and you use concurrent copy the DFSMSrmm journal is only reset if you also back up the journal data set. The journal and the journal backup are required to forward recover to the latest point in time.

RESTORE
Specifies to restore the control data set from a backup copy and optionally forward recover from the journal data set. EDGBKUP checks the DD statements that you specify to determine what actions are required.

Backing Up the DFSMSrmm Control Data Set and Journal

When DFSMSrmm is active, you do not need to specify the MASTER and JOURNAL DD statements. EDGBKUP obtains the name of the control data set and the journal from the DFSMSrmm subsystem. When the DFSMSrmm subsystem is stopped, quiesced, or when you want to back up a control data set that is not in use by DFSMSrmm, specify the MASTER DD statement and the JOURNAL DD statement. Backing up the journal is optional, and only performed if you specify the JRNLBKUP DD statement and the control data set is backed up successfully. If you do not back up the journal before it is cleared, forward recovery from previous control data set backups is limited.

Note: EDGBKUP does not reset the journal after backing up the control data set. Use EDGHSKP if you want the journal reset after backing up the control data set.

DFSMSrmm checks that any previous update of the control data set has completed successfully before backing up the DFSMSrmm control data set. If the previous update of the control data set failed, DFSMSrmm does not back up the control data set. It issues an information message and sets a return code of 12.

To store backup copies of the control data set in a storage location for disaster recovery, you can place the backups on tape and define vital record specifications to move the backups off-site. When BACKUP(DSS) is used, you can back up directly to tape. When you use BACKUP(NREORG) or BACKUP(REORG), use a DASD data set for the initial backup copy. Then copy the backup copy to a tape data set in a subsequent job step or job. For disaster recovery, you can restore directly from the tape data set with the DFSMSrmm subsystem stopped or quiesced as long as you use the EDGBKUP utility. For on-site recovery, use a DASD backup for faster recovery.

Automating Control Data Set Backup and Journal Clearing

You can use DFSMSrmm to automate the backup of the control data set and the clearing of the journal. Although you can continue to run regular backups during inventory management, automating control data set backup and clearing the journal, helps to ensure that the journal does not fill up. A full journal can impact tape usage on your system.

To automate control data set backup and the clearing of the journal you can:

- Specify a value for JOURNALFULL operand on the OPTION command in parmlib as described in “Defining System Options: OPTION” on page 122. If you do not specify a value, DFSMSrmm uses a value of 75%.
- Specify a procedure name for the BACKUPPROC operand of the OPTION command in parmlib as described in “Defining System Options: OPTION” on page 122. DFSMSrmm starts this procedure when the journal threshold is reached. If you do not specify a procedure name, you cannot automate backup using DFSMSrmm. However, you could still use the EDG2107E message as a trigger for your site automation processes.
- Create the procedure in the system procedure library. See “Automating Backup” on page 341 for an example of a procedure that runs backup as part of inventory management. Alternatively, you might want to use the procedure to submit a batch job to perform the backup or to inform your job scheduler to submit the job. DFSMSrmm will not start the procedure if backup is already in progress.
- Include a backup at the start of your inventory management schedule to avoid the filling of the journal during inventory management. If the journal does fill up during inventory management, DFSMSrmm fails any backup started by journal threshold processing because inventory management is in progress.
- Use only a single system to trigger backup using the journal threshold. When you have multiple systems and the threshold is reached, each system could start the backup procedure at the same time. Avoid this situation either by defining the backup procedure on only one system, or by specifying a different threshold on each system. You can also disable threshold processing on a system by specifying a zero value.

Restoring the Control Data Set With Forward Recovery

Figure 145 shows JCL for restoring the DFSMSrmm control data set and forward recovering to a new volume. You can restore the control data set directly from tape using the EDGBKUP utility when DFSMSrmm is stopped or quiesced. You do not need to use the EDGRESET utility or the MODIFY command to reset DFSMSrmm. EDGBKUP uses either the DSS RESTORE command or AMS REPRO for the restore based on the contents of the control data set backup.

```
//EDGBKUP  EXEC PGM=EDGBKUP,PARM='RESTORE'
//SYSPRINT DD   SYSOUT=*
//MASTER   DD   DISP=SHR,DSN=RMM.CDS
//*
//BACKUP   DD   DISP=SHR,DSN=BACKUP.CDS(0)
//*
//JOURNAL  DD   DISP=SHR,DSN=BACKUP.JRNL(0)
//         DD   DISP=SHR,DSN=RMM.JOURNAL
```

Figure 145. Restoring the Control Data Set

The MASTER DD statement is mandatory when restoring from an AMS backup and for forward recovery of an existing control data set. It is optional when restoring from a DFSMSdss backup. This enables you to restore and rename a control data set and perform forward recovery. DFSMSrmm dynamically allocates the MASTER file to the restored data set prior to starting forward recovery. If the MASTER DD statement is specified the data set name must match the data set name that DFSMSdss restores.

You can restore the DFSMSrmm control data set and forward recover the restored control data set with the journal. Use the JOURNAL DD statement to concatenate multiple journal data sets. Figure 146 shows the concatenation when you are using BACKUP(AMS). If you forward recover using multiple backup journal data sets that were created using EDGHSKP BACKUP(AMS), ensure the journal data sets are concatenated in the correct order in which changes were originally made, as shown in Figure 146.

```
//BACKUP   DD       DISP=SHR,DSN=BACKUP.CDS(-2)
//JOURNAL  DD       DISP=SHR,DSN=BACKUP.JOURNAL(-1)
//         DD       DISP=SHR,DSN=BACKUP.JOURNAL(0)
//         DD       DISP=SHR,DSN=RMM.JOURNAL
```

Figure 146. Concatenating Journal Data Sets for BACKUP(AMS)

Figure 147 shows the concatenation when you are using BACKUP(DSS).

```
//BACKUP   DD       DISP=SHR,DSN=BACKUP.CDS(-2)
//JOURNAL  DD       DISP=SHR,DSN=BACKUP.JOURNAL(-2)
//         DD       DISP=SHR,DSN=BACKUP.JOURNAL(-1)
//         DD       DISP=SHR,DSN=BACKUP.JOURNAL(0)
//         DD       DISP=SHR,DSN=RMM.JOURNAL
```

Figure 147. Concatenating Journal Data Sets for BACKUP(DSS)

When backup is taken using BACKUP(DSS), for any backup being restored a journal backup is also required for forward recovery. For the latest control data set backup, both the latest journal backup and the active journal must be used for forward recovery. In a remote recovery site, the journal backup is all that is required for successful forward recovery of the restored control data set.

To restore the control data set without forward recovery, do not specify a JOURNAL DD statement. If DFSMSrmm encounters an error during restore processing, DFSMSrmm completes the restore and sets a return code of 8 when:

- DFSMSrmm finds that the previous update of the control data set failed and the error was not corrected.
- DFSMSrmm cannot match the control data set and the journal. Journal copies used as input to forward recovery are out of sequence with other journal copies.
- DFSMSrmm can match the journal and the control data set, but the last set of journal records is incomplete. DFSMSrmm issues a message to indicate that forward recovery is completed to the point of the last complete set of journal records.
- DFSMSrmm detects discrepancies in the journal records used to perform a forward recovery. We recommend using EDGHSKP with the CATSYNCH parameter to synchronize catalogs after restoring the control data set.

Restoring the Control Data Set Without Forward Recovery

Figure 148 shows JCL to forward recover the control data set using DFSMSdss without forward recovery.

```
//*******************************************************************
//HSMATH0R JOB MSGCLASS=R,MSGLEVEL=(1,1)
//*******************************************************************
//*                                                                 *
//*  THIS JOB RESTORES THE RMM CDS AND RENAMES SYS1.RMM.CDS TO      *
//*  USER.RMM.CDS.                                                  *
//*  SPECIFY RENAMEU(SYS2) IN ORDER TO CHANGE THE HLQ FOR ALL       *
//*  DATASETS RESTORED WITH THIS EXECUTION TO 'SYS2'                *
//*                                                                 *
//*  IN ADDITION, NULLSTORCLAS AND BYPASACS(*) ARE SPECIFIED TO     *
//*  AVOID SMS ALLOCATION ERRORS DURING DISASTER RECOVERY OR WHEN   *
//*  RESTORING TO A FOREIGN SYSTEM.  WITH THE USE OF OUTDYNAM THE   *
//*  CDS WILL BE RESTORED TO SHRPK3.                                *
//*                                                                 *
//*******************************************************************
//*******************************************************************
//STEP02 EXEC PGM=ADRDSSU,REGION=8M
//*******************************************************************
//SYSPRINT DD SYSOUT=*
//SYSUDUMP DD SYSOUT=V,OUTLIM=3000
//DTAPE1 DD DISP=(OLD,KEEP),DSN='DSS.BACKUP.OF.RMM.CDS',
//         UNIT=SYSDA,VOL=SER=TAPE01
//SYSIN    DD *
  RESTORE  -
           DATASET(INC(**)) -
           INDDNAME (DTAPE1) -
           OUTDYNAM(SHRPK3) -
           NULLSTORCLAS    -
           BYPASSACS(**)
           RENAMEU(SYS1.RMM.CDS,USER.RMM.CDS)
/*
```

Figure 148. JCL Example for Forward Recovering the Control Data Set

Forward Recovering the Control Data Set

Figure 149 shows JCL to forward recover the control data set using EDGBKUP.

```
//RSTR     EXEC PGM=EDGBKUP,PARM='RESTORE'
//SYSPRINT DD       utility message data set
//MASTER   DD       control data set
//JOURNAL  DD       journal data set
```

Figure 149. JCL Example for Forward Recovering the Control Data Set

When the BACKUP DD statement is not provided, DFSMSrmm does not restore the control data set. DFSMSrmm assumes that the data set identified by the MASTER DD statement identifies the correct control data set and EDGBKUP uses data from the journal to forward recover the control data set.

You can use the JOURNAL DD statement to concatenate multiple journal data sets. You can use a restored or non-restored control data set, if automatic forward recovery failed, or if you have already restored the control data set but have not used journal data for forward recovery. The DFSMSrmm subsystem must be stopped or quiesced during forward recovery of the active control data set. See Figure 146 on page 291 for information about concatenating journal data for recovery.

Reorganizing the Control Data Set

Figure 150 shows JCL to reorganize the control data set and back up the journal:

```
//RSTR     EXEC PGM=EDGBKUP,PARM='BACKUP(REORG)'
//SYSPRINT DD   utility message data set
//BACKUP   DD   backup data set
//MASTER   DD   control data set
//JRNLBKUP DD   journal backup data set
//JOURNAL  DD   journal data set
```

Figure 150. JCL Example for Reorganizing the CDS with Journal Backup

Figure 151 shows JCL to reorganize the control data set without backing up the journal:

```
//RSTR     EXEC PGM=EDGBKUP,PARM='BACKUP(REORG)'
//SYSPRINT DD   utility message data set
//BACKUP   DD   backup data set
//MASTER   DD   control data set
```

Figure 151. JCL Example for Reorganizing the CDS without Journal Backup

DFSMSrmm reorganizes the control data set by first backing up the control data set and optionally the journal. Then DFSMSrmm restores the control data set from the backup data set. The DFSMSrmm subsystem must be stopped or quiesced during control data set reorganize processing.

If you specify the JRNLBKUP DD and the JOURNAL DD statement, DFSMSrmm backs up the journal before attempting to restore the control data set.

BACKUP(DSS) cannot be used to reorganize the control data set. If BACKUP(DSS) is used to take regular backups for recovery purposes, care should be taken when using the EDGBKUP utility with the BACKUP(REORG) parameter. Although DFSMSrmm can determine which utility to use for recovery from any backup taken using an DFSMSrmm utility, any backup taken during BACKUP(REORG) might impact the cycles maintained of regular backup copies depending on the data set names used.

Return Codes for EDGBKUP

EDGBKUP issues one of the return codes shown in Table 50.

Table 50. EDGBKUP Return Codes

Return Code	Explanation
0	All requested functions completed successfully.
4	DFSMSrmm encountered a minor error during processing. It issues an information message and continues processing.
8	DFSMSrmm encountered errors during the forward recovery process. DFSMSrmm has updated the control record in the recovered control data set to show that recovery was not successful.
12	DFSMSrmm encountered a severe error during processing of one of the requested functions. DFSMSrmm stops the utility. DFSMSrmm has updated the control record in the recovered control data set to show that recovery was not successful.

Table 50. EDGBKUP Return Codes (continued)

Return Code	Explanation
16	DFSMSrmm encountered a severe error during a required communication with the DFSMSrmm subsystem. DFSMSrmm stops the utility.

For either a return code of 8 or 12, you should decide whether the restored control data set is acceptable and take corrective actions. You can try to recover again using the correct control data set and journal data sets. If you do not have any other backups or journals from which to restore, you will have to accept the restored control data set.

DFSMSrmm sets values in the control data set control record to indicate that the recovery did not complete satisfactorily. Until these values are reset, DFSMSrmm always prompts the operator at DFSMSrmm startup time to determine if the control data set can be used or not. To clear the values, run EDGUTIL VERIFY(ALL) to validate the recovered control data set. If the VERIFY(ALL) completes successfully, DFSMSrmm resets the control data set control record and accepts the control data set for use without the operator being prompted at future startup times.

If EDGUTIL finds errors in the restored control data set, you must correct them and run EDGUTIL again. After identifying errors in the control data set, you can correct them by using RMM TSO subcommands to update the information in the control data set. You will have to start DFSMSrmm and use the restored control data set while you issue TSO subcommands.

Recovering from Control Data Set Update Failures

Information about a volume in the DFSMSrmm control data set is stored in several records. A change in a volume's status can require the updating of several records. Since an update of multiple records takes a finite time, it is possible that external events, such as a power outage, could interrupt the updating process, leaving some records reflecting the volume's old status and some its new. The control data set is then considered corrupt as it might be impossible to subsequently change the volume's status. This situation is referred to as a *multi-record update failure*.

DFSMSrmm detects a multi-record update failure at DFSMSrmm address-space start-up when the control data set is not shared between systems. When a control data set is shared between multiple systems, the multi-record update failure can be detected at any time. A hardware failure on any of the systems could be detected by another system at the next I/O to the control data set. In this case, a SYSTEM RESET of the failing system releases the control data set reserve, and the other systems sharing that control data set, find they had experienced a multi-record update failure.

Recovery Processing

When a multi-record update failure is first detected, DFSMSrmm attempts automatic recovery processing which requires no operator intervention. If a journal data set matching the corrupt control data set is found, DFSMSrmm issues message EDG2111I to notify the operator that automatic recovery processing is starting. DFSMSrmm issues message EDG2115I if automatic recovery is not possible and manual recovery is required. Manual recovery might be necessary when:

- The journal data set is not defined in the initialization parameters

- The journal and control data sets do not match
- The journal data set has been disabled in response to message EDG2103D
- The journal data set update has been ignored in response to message EDG2103D

Manual recovery requires operator intervention. See *z/OS DFSMSrmm Guide and Reference* for operator procedures for responding to messages DFSMSrmm issues during recovery processing.

We recommend using EDGHSKP with the CATSYNCH parameter to synchronize catalogs after recovery.

Handling of DFSMSrmm Subsystem Requests

The first request for I/O to the control data set, following a multi-record update failure, detects the situation and recovery processing begins. Other attempts to access the control data set are queued behind the current request until either manual recovery is required or automatic recovery is successful.

After recovery is completed, the following requests are retried:
- Any tape processing activity
- DFSMShsm tape volume release activity

Automatic recovery

Once automatic recovery is successful the first request continues as normal, and the queued requests are performed.

Manual recovery

When manual recovery is required, each subsystem request that results in I/O to the control data set fails as though it is an I/O error on the control data set. For requests that can be retried, a WTOR EDG4001D or EDG8008D is issued.

Manual recovery requires operator intervention. See *z/OS DFSMSrmm Guide and Reference* for operator procedures for information about stopping, quiescing, and restarting the DFSMSrmm subsystem. After manual recovery completes, the operator can reply 'RETRY' or 'CANCEL' to the WTORs. The following requests fail and must be rerun or reissued after manual recovery:
- Inventory management in progress
- DFSMSrmm utilities EDGINERS and EDGUTIL
- RMM TSO subcommands

Moving the Control Data Set and Journal to a Different Device

If you need to move the control data set or journal to a different device, you can use one of several methods. We recommend using DFSMSrmm utilities to move them. For other DFSMSrmm data sets, such as the extract data set, use the existing storage management techniques you are familiar with to move them.

Here are examples for moving the control data set and journal data set using both DFSMSrmm utilities and other storage management techniques.

Moving the Control Data Set and Journal Using DFSMSrmm Utilities

To move your control data set and journal to a different device:

1. Allocate a new control data set and journal. Allocation of a new control data set is optional if you are planning to use the BACKUP(DSS) option of EDGHSKP.

2. With RMM active, run EDGHSKP,PARM='BACKUP' or EDGHSKP,PARM='BACKUP(DSS)' to back up both the control data set and the journal as shown in Figure 152. Use the BACKUP(DSS) option on a concurrent copy capable device to enable DFSMSrmm to continue to process requests while the backup is taken.

```
// EXEC PGM=EDGHSKP,PARM='BACKUP'
//MESSAGE  DD DISP=SHR,DSN=messages
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),DSN=cds backup(+1),UNIT=SYSDA
//JRNLBKUP DD DISP=(,CATLG),DSN= journal backup(+1),UNIT=SYSDA
```

Figure 152. JCL Example for Moving the Control Data Set and Journal

   This will clear the current journal data set. Some records might be written to the journal if any updates are made to the control data set before the DFSMSrmm procedure is stopped. This is not a problem as the restore operation will use them in forward recovery.

3. Stop or quiesce the DFSMSrmm procedure to prevent any further updates to the control data set during recovery.
4. Restore the backup of the control data set to the new control data set allocated in step 1 on page 295 as shown in Figure 153.

```
// EXEC PGM=EDGBKUP,PARM='RESTORE'
//SYSPRINT DD SYSOUT= *
//BACKUP   DD DISP=SHR,DSN=cds backup(0)
//MASTER   DD DISP=SHR,DSN=new control data set
//JOURNAL  DD DISP=SHR,DSN=old journal
```

Figure 153. JCL Example for Restoring the Control Data Set Backup

   This puts the latest DFSMSrmm information into the new control data set and uses the old journal to forward recover the control data set backup to the point when the you stopped the DFSMSrmm procedure.

   If the BACKUP(DSS) option is used, you can use the DSSOPT DD statement as described in Figure 154 to specify the new control data set data set name.

```
//EDGBKUP  EXEC PGM=EDGBKUP,PARM='BACKUP(DSS)'
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.CDS(+1),
//         LABEL=(,SL)
//JRNLBKUP DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.JRNL(+1),
//         LABEL=(2,SL),VOL=REF=*.BACKUP
//DSSOPT   DD *
    CONCURRENT OPTIMIZE(4) VALIDATE
/*
```

Figure 154. JCL Example for Restoring the Control Data Set Backup Using the DSSOPT DD Statement

5. Implement the new data sets using one of these techniques:
   - Use IDCAMS ALTER command to rename the new control data set and new journal, after renaming the old data sets, or
   - Create a new EDGRMMxx parmlib member with the new names, or
   - Update the current parmlib member to include the names of the new control data set and journal.
6. If DFSMSrmm was stopped, start the DFSMSrmm procedure, using the current, updated, or the new parmlib member. If DFSMSrmm was quiesced, use the MODIFY command to specify the parmlib member suffix to be used.

   If you are keeping multiple control data set and journal backups for error recovery situations, you should now perform step 2 on page 296 again. If you do not do this, you will require the old journal data set for forward recovery. Taking a backup of the new data sets now, reduces the requirement to keep the old journal for recovery. As your backup copies are created in the future, your requirement for the old journal will be eliminated.

Moving the Control Data Set Using DFSMSrmm Utilities

To move your control data set to a different device:

1. Allocate a new control data set. Allocation of a new control data set is optional if you are planning to use the BACKUP(DSS) option of EDGHSKP.
2. With DFSMSrmm active, run EDGHSKP,PARM='BACKUP' or EDGHSKP,PARM='BACKUP(DSS)' to backup both the control data set and journal as shown in Figure 155. Use the BACKUP(DSS) option on a concurrent copy capable device to enable DFSMSrmm to continue to process requests while the backup is taken.

```
// EXEC PGM=EDGHSKP,PARM='BACKUP'
//MESSAGE  DD DISP=SHR,DSN=messages
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),DSN=cds backup(+1),UNIT=SYSDA
//JRNLBKUP DD DISP=(,CATLG),DSN= journal backup(+1),UNIT=SYSDA
```

Figure 155. JCL Example for Backing Up the Control Data Set and Journal

   This clears the current journal data set. Some records might be written to the journal if any updates are made to the control data set before the DFSMSrmm procedure is stopped. This is not a problem as the restore operation uses the records in forward recovery.
3. Stop or quiesce the DFSMSrmm procedure, to prevent any further updates to the control data set during recovery.
4. Restore the backup of the control data set to the new control data set allocated in step 1 as shown in Figure 156. If the BACKUP(DSS) option is used, you can use the DSSOPT DD statement as described in Figure 154 on page 296 to specify the new control data set data set name.

```
// EXEC PGM=EDGBKUP,PARM='RESTORE'
//SYSPRINT DD SYSOUT= *
//BACKUP   DD DISP=SHR,DSN=cds backup(0)
//MASTER   DD DISP=SHR,DSN=new control data set
//JOURNAL  DD DISP=SHR,DSN=old journal
```

Figure 156. JCL Example for Restoring the Back Ups

This step puts the latest DFSMSrmm information into the new control data set, and uses the old journal data set to forward recover the control data set backup to the point when the you stopped the DFSMSrmm procedure.

5. Implement the control data set using one of these techniques:
   - Use IDCAMS ALTER command to rename the new control data set, having first renamed the old data set, or
   - Create a new EDGRMMxx parmlib member, or
   - Update the current parmlib member to include the name of the new control data set.
6. If DFSMSrmm was stopped, start the DFSMSrmm procedure, using the current, updated, or the new parmlib member. If DFSMSrmm was quiesced, use the MODIFY command to specify the parmlib member suffix to be used.

Moving the Journal Using DFSMSrmm Utilities

The journal cannot, strictly speaking, be moved. You move it by allocating a new journal data set and later deleting the old one.

To move your journal to a different device:

1. Allocate a new journal data set.
2. Stop or quiesce the DFSMSrmm procedure to prevent any further updates to the control data set and journal.
3. With DFSMSrmm stopped or quiesced, run EDGBKUP,PARM='BACKUP' to backup both the control data set and journal as shown in Figure 157.

```
// EXEC PGM=EDGBKUP,PARM='BACKUP'
//SYSPRINT DD SYSOUT=*
//MASTER   DD DISP=SHR,DSN=cds name
//JOURNAL  DD DISP=SHR,DSN=journal name
//BACKUP   DD DISP=(,CATLG),DSN=cds backup(+1),UNIT=SYSDA
//JRNLBKUP DD DISP=(,CATLG),DSN= journal backup(+1),UNIT=SYSDA
```

Figure 157. JCL Example for Backing Up the Control Data Set and Journal

This provides you with a valid point in time backup of the control data set and the old journal data set. After this step, if you need to recover the control data set, you can use this control data set backup, and the new journal data set.

4. Implement the journal using one of these techniques:
   - Use IDCAMS ALTER command to rename the new journal, having first renamed the old data set, or
   - Create a new EDGRMMxx parmlib member, or
   - Update the current parmlib member to include the name of the new journal.
5. If DFSMSrmm was stopped, start the DFSMSrmm procedure, using the current, updated, or the new parmlib member. If DFSMSrmm was quiesced, use the MODIFY command to specify the parmlib member suffix to be used. Doing so, uses the unmoved control data set and the newly allocated journal.

Moving the Control Data Set Using Non-DFSMSrmm Utilities

Use the following procedure for moving the DFSMSrmm control data set using non-DFSMSrmm utilities such as AMS REPRO and EXPORT/IMPORT, or DFSMSdss ADRDSSU.

1. Allocate a new control data set only if you are planning to use AMS REPRO.

2. Stop the DFSMSrmm procedure, to prevent any further updates to the control data set and journal.
3. With DFSMSrmm stopped or quiesced, copy the old control data set to the new control data set using one of the following utilities:
   - AMS REPRO
   - AMS EXPORT followed by IMPORT
   - DFSMSdss ADRDSSU utility
4. Implement the data sets using one of these techniques:
   - Use IDCAMS ALTER command to rename the new control data set, having first renamed the old data set, or
   - Create a new EDGRMMxx parmlib member, or
   - Update the current parmlib member to include the name of the new control data set.
5. Start the DFSMSrmm procedure, using either the current updated parmlib member, or using the new parmlib member. This will use the moved control data set and the unmoved journal.

Creating and Verifying the Contents of the Control Data Set: EDGUTIL

Use the EDGUTIL utility to:

- Create the DFSMSrmm control data set and the control data set control record.
- Verify the contents of the control data set. See “Verifying the Contents of the Control Data Set” on page 305 for information about using the verify function and techniques for correcting errors in the control data set. In a multi-system environment, always run EDGUTIL VERIFY on the system with the highest level of software available. This ensures that EDGUTIL uses the latest control data set record format information to verify the contents of the control data set.
- Mend the control data set by verifying and fixing the control data set upon completion of conversion activities. Run the mend function against a VSAM copy of the control data set as the first step in fixing a production control data set.

  Note: The mend function should only be used with guidance from DFSMSrmm service to determine the underlying cause of any errors in the control data set. See “Mending the Control Data Set” on page 306 for restrictions you should be aware of when using the mend function.
- Perform an audit or a synchronization of the DFSMSrmm control data set, TCDB, and the Library Manager database.

JCL for EDGUTIL

This section provides JCL for creating the DFSMSrmm control data set, verifying the contents of the control data set, updating the control data set, and mending the control data set.

JCL for Creating the Control Data Set

The JCL shown in Figure 158 on page 300 can be used to create a control data set:

```
//EDGUTIL EXEC PGM=EDGUTIL,PARM='CREATE'
//SYSPRINT DD SYSOUT=*
//MASTER   DD DSN=RMM.CONTROL.DSET,DISP=SHR
//SYSIN    DD *
CONTROL
/*
```

Figure 158. Creating the Control Data Set

JCL for Updating the Control Data Set

Use the sample JCL in Figure 159 to update the control data set:

```
//UTIL     EXEC     PGM=EDGUTIL,PARM='UPDATE'
//SYSPRINT DD       SYSOUT=*
//MASTER   DD       DISP=SHR,DSN=RMM.CONTROL.DSET
//SYSIN    DD       *
CONTROL  RACKFREE(1234)
/*
```

Figure 159. Updating the Control Data Set

JCL for Verifying the Contents of the Control Data Set

Use the sample JCL in Figure 160 to verify the contents of the control data set:

```
//UTIL     EXEC     PGM=EDGUTIL,PARM='VERIFY(ALL)'
//SYSPRINT DD       utility message data set
//MASTER   DD       DSN=RMM.CONTROL.DSET,DISP=SHR
//SYSIN    DD       DUMMY
```

Figure 160. Verifying the Contents of the Control Data Set

JCL for Mending the Control Data Set

Use the sample JCL in Figure 161 to mend the control data set:

```
//UTIL      EXEC PGM=EDGUTIL,PARM='MEND'
//SYSPRINT  DD   SYSOUT=*
//MASTER    DD   DSN=RMM.CONTROL.DSET,DISP=SHR
//SYSIN     DD   DUMMY
/*
```

Figure 161. Mending the Control Data Set

EXEC Parameters for EDGUTIL

Figure 162 on page 301 shows the EXEC parameters for EDGUTIL:



Figure 162. EDGUTIL EXEC Parameters

CREATE
Use CREATE to create a new control data set control record.

MEND
Use MEND to detect and fix errors in your control data set. These errors might have been created during conversion activities or as a result of system failures. The mend function should only be used with guidance from IBM service to update the control data set enable stacked volumes support.

MEND processing checks to see if you have enabled stacked volume support with the EDGUTIL UPDATE option STACKEDVOLUME(YES). DFSMSrmm uses existing container information to create stacked volumes from the existing volume 'In container' values. DFSMSrmm marks the control data ready for stacked volume support if processing is successful.

During MEND processing, DFSMSrmm creates stacked volumes in the DFSMSrmm control data set that are marked as media type HPCT and recording format 128TRACKS. DFSMSrmm obtains the media name from pool definitions defined using the DFSMSrmm parmlib member VLPOOL command. To ensure that EDGUTIL can use the VLPOOL information RMM must have been started at least once with a parmlib member containing the correct VLPOOL commands before running EDGUTIL. DFSMSrmm marks the stacked volumes as 'Created during MEND' and obtains location information from the last volume in sequence found to be in the container.

After MEND processing is completed, you might need to add or change some volume information. Use the RMM CHANGEVOLUME subcommand to set or change any information.

Do not enable stacked volume support until all systems using the control data set are on a supporting release level.

MEND must be run on an unused control data set or with DFSMSrmm inactive.

MEND(SMSTAPE)
Use MEND(SMSTAPE) to mend the DFSMSrmm control data set using information from the TCDB and the Library Manager database. You can run MEND(SMSTAPE) even when DFSMSrmm is active to update DFSMSrmm control data set from the TCDB and the Library Manager database. Before

running MEND(SMSTAPE), you should first use the VERIFY option to find information that is not the same in the DFSMSrmm control data set, TCDB, and the Library Manager database. Between running VERIFY and MEND, you can update the control data set using DFSMSrmm TSO subcommands to correct DFSMSrmm information.

UPDATE
Use UPDATE to:

- Update an existing control data set control record
- Mark the DFSMSrmm control data set as synchronized or not synchronized with the user catalogs so the control data set is synchronized at a later time.
- Enable stacked volume support

VERIFY(ALL,DSN,OWNER,PP,RACK,SMSTAPE,STORE,VOLUME,VRS,VOLCAT)
Use VERIFY to verify the information in the control data set and identify errors. You can verify all the information in the control data set at once or select specific values to verify individual pieces of information. If stacked volume support is enabled, DFSMSrmm checks the consistency of stacked volumes and the volumes in the stacked volumes.

To correct inconsistencies found during VERIFY processing, DFSMSrmm TSO subcommands to correct the inconsistencies.. Use MEND(SMSTAPE) to drive changes to the TCDB and Library Manager database from the DFSMSrmm control data set or use access method services commands to correct errors in the TCDB.

The values you can specify on VERIFY are:

ALL
DFSMSrmm verifies all information at once, except for VOLCAT, which does consistency checking against the TCDB. ALL is the default.

DSN
DFSMSrmm validates data set information and compares data set information to volume information.

OWNER
DFSMSrmm validates owner information and compares owner information to volume information.

PP
DFSMSrmm validates product information and compares software product information to volume and library shelf location information.

RACK
DFSMSrmm validates rack number information and compares library shelf location information to volume information.

SMSTAPE
DFSMSrmm performs extra processing with the TCDB and Library Manager database when SMSTAPE is specified. DFSMSrmm scans both the DFSMSrmm control data set and the TCDB sequentially to find DFSMSrmm volumes not in the TCDB and TCDB volumes not in the DFSMSrmm control data set. DFSMSrmm also checks any volume found to be system-managed, either by definition to DFSMSrmm or retrieved from the TCDB, against the Library Manager database for an IBM ATL or 3495-M10 tape library dataserver.

STORE
DFSMSrmm validates bin number information and compares storage location shelf information to volume information.

VOLCAT
DFSMSrmm compares volume status and library name information in its control data set with the same information in the TCDB. If the information is different, DFSMSrmm issues an information message, but sets a minimum return code of 0.

VOLUME
DFSMSrmm compares volume information to information about data sets, software products, owners, and shelf locations in the library and storage locations.

VRS
For vital record specification checking, DFSMSrmm validates the next vital record specification information to see if a name vital record specification exists. If DFSMSrmm does not find a next vital record specification, it issues an information message, but sets a minimum return code of 0.

Creating or Updating the Control Data Set Control Record

Create the control data set control record during the first run of EDGUTIL during DFSMSrmm implementation or conversion to DFSMSrmm. The control data set control record contains information about the number of shelf locations in the library and storage locations. To create or update the control record, the user of EDGUTIL must have UPDATE or higher RACF access to the DFSMSrmm control data set.

Once you have created a control record, defined shelf locations to your installation, and are managing these shelves with DFSMSrmm, use the RMM ADDRACK subcommand to add shelf locations to DFSMSrmm. Do not use EDGUTIL to change the number of shelf locations.

You should only need to update the control record to correct rack or bin counts. DFSMSrmm lets you update the control data set and the control record only if inventory management and backup, restore and reorganize are not in progress.

The SYSIN command in Figure 163 is required to create or update the control data set control record:



Figure 163. EDGUTIL SYSIN Commands

CATSYNCH(NO/YES)
Specifies whether the DFSMSrmm control data set and system catalogs are

synchronized or not. When the DFSMSrmm control data set is not synchronized with the system catalogs, DFSMSrmm always retrieves catalog information to determine the catalog status of a data set.

When you indicate that catalogs are fully shared with the EDGRMMxx parmlib OPTION CATSYSID(*) as described in “Defining System Options: OPTION” on page 122, DFSMSrmm automatically marks the DFSMSrmm control data set as synchronized when you run the EDGKHSP utility with the CATSYNCH parameter as described in “EXEC Parameters for EDGHSKP” on page 253. You must use CATSYNCH(YES) to indicate to DFSMSrmm that catalogs are synchronized when you use DFSMSrmm with unshared catalogs. Do not specify CATSYNCH(YES) if you have not run the EDGHSKP utility with the CATSYNCH parameter on each system to synchronize the DFSMSrmm control data set with the user catalogs.

CATSYNCH(YES) sets the last synchronization date and time to the current date and time. CATSYNCH(NO) clears the last synchronization date and time. Specify CATSYNCH(NO) to force resynchronization of the DFSMSrmm control data set and user catalogs the next time inventory management is run. DFSMSrmm cannot track catalog updates when the DFSMSrmm subsystem is stopped and issues messages when the updates cannot be made.

CDSID(*nnnnnn***)**
Specifies one to eight alphanumeric characters that identify the control data set by name. There is no default.

At DFSMSrmm startup time, DFSMSrmm matches this CDSID value with the CDSID operand in parmlib member EDGRMMxx. The CDSID value in EDGUTIL will set or change the control data set ID. EDGUTIL does not validate the CDSID in the control data set control record; it simply sets the new value into the control record.

If you do not specify an ID for the control data set, you can set it the first time DFSMSrmm is started with this control data set by setting the CDSID operand in EDGRMMxx.

Do not change the CDSID value once you have set it, as changing it can affect inventory management. You can change the value only when no data sets exist that were created on the system or when the WHILECATALOG option for vital record specifications is not in use.

CONTROL
Specifies to update or create the control record.

DBINFREE(*nnnnnn***)**
Specifies the number of empty bin numbers in the DISTANT storage location in a range from 0 to 999999.

DBINNO(*nnnnnn***)**
Specifies the number of bin numbers in the DISTANT storage location in a range from 0 to 999999.

LBINFREE(*nnnnnn***)**
Specifies the number of empty bin numbers in the LOCAL storage location in a range from 0 to 999999.

LBINNO(*nnnnnn***)**
Specifies the number of bin numbers in the LOCAL storage location in a range from 0 to 999999.

RACKFREE(*nnnnnn*)
Specifies the number of empty rack numbers in the library for location SHELF and for system-managed libraries in a range from 0 to 2147483647.

RACKNO(*nnnnnn*)
Specifies the number of rack numbers in the library for location SHELF and for system-managed libraries in a range from 0 to 2147483647.

RBINFREE(*nnnnnn*)
Specifies the number of empty bin numbers in the REMOTE storage location in a range from 0 to 999999.

RBINNO(*nnnnnn*)
Specifies the number of bin numbers in the REMOTE storage location in a range from 0 to 999999.

STACKEDVOLUME(*YES*)
Enables DFSMSrmm stacked volume support. Prior to enabling stacked volume support, ensure all systems using the control data set are at the same release level.

When stacked volumes have been defined to DFSMSrmm but you have not enabled stacked volume support, DFSMSrmm manages the movement of the volumes that are in containers using the individual volume location. Volume movement is limited to non-shelf-managed storage locations. When you enable stacked volume support, DFSMSrmm uses the stacked volume records to manage the movement of the volumes contained in the stacked volumes. See “Setting up DFSMSrmm Stacked Volume Support” on page 307.

Note: you cannot remove stacked volume support after it is enabled.

Verifying the Contents of the Control Data Set

Specify VERIFY on the EXEC parameter of EDGUTIL to verify the contents of the control data set. You can verify all the information in the control data set at once, or select specific values to verify individual pieces of information.

For example, if you specify the STORE value as shown in Figure 164, DFSMSrmm reads all the storage location shelf information in the control data set. DFSMSrmm then reads volume information for only those volumes in the storage locations and verifies that the volumes include the correct location information.

```
//UTIL     EXEC PGM=EDGUTIL,PARM='VERIFY(STORE)'
//SYSPRINT DD SYSOUT=*
//MASTER   DD DISP=SHR,DSN=RMM.CONTROL.DSET
```

Figure 164. Example of JCL for VERIFY(STORE)

You can correct errors found in the control data set using one of the following methods:

- Restore the control data set to a level where the errors are not present.See “Restoring the Control Data Set With Forward Recovery” on page 290 for additional information.
- Correct information in the control data set by using the RMM TSO ADD, CHANGE, DELETE, and LIST subcommands. See*z/OS DFSMSrmm Guide and Reference* for additional information.

- Mend the control data set by specifying MEND on the EXEC parameter of EDGUTIL. See“Mending the Control Data Set” for additional information.
- Synchronize the DFSMSrmm control data set with information from the TCDB and the Library Manager database by specifying MEND(SMSTAPE) on the EDGUTIL EXEC parameter. See“Synchronizing the Contents of the Control Data Set” on page 307 for additional information.

The DFSMSrmm control data set can be updated during verify processing so DFSMSrmm can report inconsistencies for resources updated during the verify processing. To avoid rerunning verify to clean up these inconsistencies, run EDGUTIL when there is little activity that updates the control data set. DFSMSrmm processes each resource in turn, dependent on the VERIFY parameter, and validates related information. For example:

- For every shelf location for a scratch volume, the associated volume must have the correct shelf location and media name and must be recorded as a scratch volume.
- For every data set, the corresponding volume must be defined and the next and previous data set names in sequence must also be correctly defined.
- For every defined owner, the corresponding volumes are checked for correct information.

DFSMSrmm writes a message to the SYSPRINT data set for every error it encounters.

Verifying the Control Data Set and Tape Configuration Database

You can use EDGUTIL VERIFY(VOLCAT) to check the consistency of information in the control data set and the tape configuration database (TCDB). EDGUTIL checks volume status and the library where the volume resides. You can use EDGUTIL VERIFY(SMSTAPE) to perform more detailed checking including the Library Manager database. You can use MEND(SMSTAPE) to update the TCDB and Library Manager database with information from the DFSMSrmm control data set.

Figure 165 shows JCL for verifying the control data set and tape configuration database:

```
//UTIL     EXEC     PGM=EDGUTIL,PARM='VERIFY(VOLCAT)'
//SYSPRINT DD       utility message data set
//MASTER   DD       control data set
```

Figure 165. Sample JCL for Verifying the Control Data Set and the TCDB

Mending the Control Data Set

Use EDGUTIL verify as described in “Verifying the Contents of the Control Data Set” on page 305 to find most control data set errors. Use EDGUTIL MEND with guidance from IBM service to fix those errors found in the DFSMSrmm control data set. When you use the EDGUTIL MEND function to fix errors, the function updates the DFSMSrmm control data set from information from the TCDB and the Library Manager database so you must run the function against an inactive control data set.

Recommendations:

- Always run the mend function on a VSAM copy of the control data set first. Taking a back up of the control data set is essential because the control data set is unusable if mend processing fails for any reason.

- You cannot run the mend function when DFSMSrmm is running on the same system and is using a control data set with the same name as the control data set that the mend function is expected to correct.

Synchronizing the Contents of the Control Data Set

Use the EDGUTIL MEND(SMSTAPE) function to synchronize the TCDB and the Library Manager database from the DFSMSrmm control data set. You can run the function against an active control data set because the function does not update the control data set. The function only makes changes to the TCDB and Library Manager database.

Setting up DFSMSrmm Stacked Volume Support

To enable stacked volume support:

1. Update all systems sharing a control data set to the level of code containing stacked volume support.
2. Correct any information about stacked volumes that you have defined to DFSMSrmm before running the DFSMSrmm EDGUTIL utility. EDGUTIL processing changes the volume type to stacked but does not set the correct location information for the volume. You can set the correct volume type and location information prior to running EDGUTIL MEND using the RMM CHANGEVOLUME subcommand. Figure 166 shows an example for using the RMM SEARCHVOLUME subcommand to build a CLIST that can be used to change volume information. Specify operands based on the way you have defined volumes to DFSMSrmm. Then run the CLIST produced by the command to make changes to the volumes.

```
RMM SEARCHVOLUME VOLUME(ST*) OWNER(*) LIMIT(*) -
    CLIST('RMM CHANGEVOLUME ','TYPE(STACKED) LOCATION(vts_name) NORACK')
```

Figure 166. Changing Volume Type and Volume Location

3. Run the EDGUTIL utility with UPDATE with the STACKEDVOLUME(YES) operand on the CONTROL statement of the SYSIN file to enable stacked volume support.
4. To check the stacked volume information, you can use EDGUTIL with VERIFY(VOLUME) to check if the container information is correct. Use the RMM LISTCONTROL CNTL subcommand to display the status of support. DFSMSrmm marks the support status as MIXED if there is any container information in the control data set volume records. If the support status shows MIXED, you can run EDGUTIL MEND as described in “Mending the Control Data Set” on page 306 to make the container information consistent. During MEND processing, DFSMSrmm creates the necessary stacked volumes if you have not previously defined them using the DFSMSrmm subcommands.
5. Run EDGHSKP storage location management processing to clean up location and bin number information in volumes that are in a container.

How EDGUTIL Processing Works

If you request the CREATE option, EDGUTIL ensures that DFSMSrmm is not active and opens the control data set for load processing. The information provided on the CONTROL command in SYSIN is used to build a control record which is written to the control data set.

If you request the UPDATE option, EDGUTIL ensures that DFSMSrmm is not active and opens the control data set for update processing. The information provided on the CONTROL command in SYSIN is used to update the control record.

For VERIFY processing, EDGUTIL reads sequentially through the different record types in the control data set. The record types are identified by the VERIFY options you specify. For each record DFSMSrmm validates key fields and cross-checks information with related records in the control data set. If any discrepancies are identified an informational message is issued to the SYSPRINT file.

When you specify VERIFY(ALL), DFSMSrmm resets the error indicator that is set when the control data set recovery processing was not successful. For VERIFY with VOLCAT, DFSMSrmm compares TCDB information with information known to DFSMSrmm. For VERIFY with SMSTAPE, DFSMSrmm also retrieves the Library Manager information for each system-managed volume and compares the information to the TCDB and DFSMSrmm information. Use EDGUTIL MEND(SMSTAPE) to synchronize the TCDB and Library Manager with DFSMSrmm. When you specify MEND, without SMSTAPE, EDGUTIL checks that DFSMSrmm is not active or that the DFSMSrmm control data set is not in use. MEND processing is performed the same way as VERIFY(ALL) and VERIFY(VOLCAT) processing. MEND processing cannot fix all discrepancies but those that can be fixed automatically are corrected by updating the control data set.

During VERIFY, EDGUTIL issues messages to indicate what stage of processing has been reached. These messages also go in the SYSPRINT file. An example of the SYSPRINT message file can be seen in Figure 167.

```
EDG6433I STARTING VERIFICATION OF RACK     RECORDS
EDG6433I STARTING VERIFICATION OF VOLUME   RECORDS
EDG6433I STARTING VERIFICATION OF DATA SET RECORDS
EDG6433I STARTING VERIFICATION OF OWNER    RECORDS
EDG6433I STARTING VERIFICATION OF PRODUCT  RECORDS
EDG6434I NO PRODUCT      RECORDS IN CONTROL DATA SET
EDG6433I STARTING VERIFICATION OF STORE    RECORDS
EDG6434I NO EMPTY BIN    RECORDS IN CONTROL DATA SET
EDG6434I NO INUSE BIN    RECORDS IN CONTROL DATA SET
EDG6433I STARTING VERIFICATION OF VRS      RECORDS
EDG6417I CONTROL DATA SET VERIFY SUCCESSFUL
EDG6901I UTILITY EDGUTIL COMPLETED WITH RETURN CODE 0
```

Figure 167. Sample EDGUTIL SYSPRINT Output

During VERIFY processing and MEND processing, DFSMSrmm issues message EDG6838I or message EDG6839I when the volume that is being processed resides in a manual tape library.

Return Codes for EDGUTIL

EDGUTIL issues one of the return codes shown in Table 51.

Table 51. EDGUTIL Return Codes

Return Code	Explanation
0	All requested functions completed successfully.
4	DFSMSrmm encountered a minor error during processing. It issues a warning message and continues processing.
8	DFSMSrmm has encountered an error opening the control data set.

Table 51. EDGUTIL Return Codes (continued)

Return Code	Explanation
12	DFSMSrmm encountered a severe error during processing of one of the requested functions. DFSMSrmm stops the utility.
16	DFSMSrmm encountered a severe error during a required communication with the DFSMSrmm subsystem. DFSMSrmm stops the utility.

Sharing the DFSMSrmm Control Data Set

When you share a DFSMSrmm control data set where at least one system does not support system-managed tape libraries, you must consider the following:

- Data Facility Removable Media Manager for MVS/DFP Version 3 (DFRMM) Program Offering provides support for non-system-managed tape libraries. When you use DFRMM and DFSMSrmm together, or multiple DFSMSrmm systems, they can share the same control data set. When both DFRMM and DFSMSrmm share the control data set, you can use the DFRMM ISPF dialog and RMM TSO subcommands to display all information that has been recorded in the control data set. There are some restrictions on using the RMM TSO subcommands from DFRMM, and from DFSMSrmm on a non-system-managed tape system, to add and change information in the control data set.
- DFRMM has no knowledge of volume residency in an IBM 3494 Tape Library Dataserver or an IBM 3495 Tape Library Dataserver, other than that which is provided by DFSMSrmm on a DFSMS system using a shared control data set.

Running DFSMSrmm Inventory Management When Sharing the Control Data Set

Use the EDGHSKP utility to run inventory management activities which include: vital record processing, expiration processing, storage location management processing, backing up the control data set and journal, and creating an extract data set. See “Chapter 13. Performing Inventory Management” on page 247 for more information.

When you are using DFRMM or have at least one non-system-managed tape environment, you should perform inventory management using DFSMSrmm in a system-managed tape environment. DFSMSrmm ensures that the TCDB is updated with the correct volume status as volumes are returned to scratch, and that volume movement is automatically confirmed to IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver.

Running EDGINERS When Sharing the Control Data Set

If you are using DFRMM or have at least one non-system-managed tape environment, run EDGINERS processing with DFSMSrmm in a system-managed tape environment so that you can take advantage of the dynamic allocation capability of EDGINERS when running on this level.

Defining Volume Information When Sharing the Control Data Set

When you use DFRMM or have at least one non-system-managed tape environment, issue RMM TSO ADDVOLUME, DELETEVOLUME, and CHANGEVOLUME EJECT subcommands using DFSMSrmm in the system-managed tape environment so the TCDB is automatically updated.

Confirming Volume Movement When Sharing the Control Data Set

We recommend running inventory management on the DFSMSrmm in the system-managed tape environment when DFRMM and DFSMSrmm are sharing a control data set. Use the RMM CHANGEVOLUME subcommand with the following operands:

```
RMM CHANGEVOLUME * CMOVE(from_location,to_location)
```

to confirm that pending volume movement has taken place. You can specify a system-managed library name as the from_location or to_location name when using either DFRMM or DFSMSrmm even if system-managed tape is not in use.

When you run inventory management on the DFSMSrmm system, the volume information in the control data set is updated to confirm that any volumes pending movement have been moved. If you run inventory management on the DFRMM system, your request does not fail but volume information is not updated.

Returning Volumes to Scratch When Sharing the Control Data Set

When volumes that reside in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver are returned to scratch by DFSMSrmm, information needs to be updated in the TCDB.

When you have some systems without system-managed tape active, ensure that inventory management runs on a system with system-managed tape active so that system-managed volumes returning to scratch are updated in the TCDB automatically during inventory management expiration processing.

Chapter 17. Initializing and Erasing Volumes

DFSMSrmm Samples Provided in SAMPLIB

- EDGJINER Sample JCL for Using the EDGINERS Utility
- EDGLABEL Sample Started Procedure for Initializing and Erasing Tapes

Use EDGINERS to initialize and erase volumes. Run EDGINERS regularly as part of your inventory management processing.

See *z/OS DFSMSrmm Guide and Reference* for operator procedures that describe operator tasks like responding to initialization messages, tape mount messages, and using the LABEL procedure to request EDGINERS processing. See “Using the LABEL Procedure” on page 341 for a description of the EDGLABEL procedure provided by DFSMSrmm.

If you are authorized to change the label type, you can relabel tape volumes by specifying the label type in your JCL. This is done at the time of volume use to avoid a separate mount of the volume. When you change the volume label type at the time of use, you do not need to use either EDGINERS or the INIT action. DFSMSrmm allows the tape volume label to be created or overwritten at any time, regardless of the status of the volume, if the user has the required access to a security resource. See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for more information about volume labels.

EDGINERS writes BCD labels on 7-track tape volumes and ASCII (ISO/ANSI format) labels on tape cartridges or 9-track tape volumes. EDGINERS writes 7-track tape labels in even parity (translator on, converter off). You can label tape cartridges, 7-track, or 9-track tape volumes with EDGINERS.

EDGINERS provides support for ISO/ANSI version 3 VOL1 and HDR1 labels and for ISO/ANSI version 4 VOL1 and HDR1 labels.

Before initializing or erasing a volume, DFSMSrmm ensures that the correct volume is mounted by reading the volume label. For DFSMSrmm-defined volumes, it also ensures that the requested action is actually required.

When DFSMSrmm reads an existing volume label, the request might fail because the existing volume requires formatting of the servo tracks. If DFSMSrmm detects that a mounted volume has a servo track formatting error, DFSMSrmm issues message EDG6658I and fails the request to initialize or erase the volume.

Note: The recording technology and media associated with IBM new tape architecture products, for example, 3590, uses servo track. See *IBM 3590 High Performance Tape Subsystem Introduction and Planning Guide, GA32-0330* for details.

DFSMSrmm erases volumes using the hardware security erase feature, where supported. When erasing volumes, DFSMSrmm also reinitializes them so that the correct volume labels are written and the volumes are ready for reuse. If the hardware security erase feature is not available, DFSMSrmm overwrites volumes with a bit pattern of hex FF.

© Copyright IBM Corp. 1992, 2001

Replacing IEHINITT with EDGINERS

You can use EDGINERS to replace the IEHINITT utility. The differences between EDGINERS and IEHINITT are that EDGINERS:

- Reads and validates volume labels.
- Maintains RACF profiles.
- Uses and updates information in the DFSMSrmm control data set.
- Provides a facility to erase tapes.
- Defines volumes you initialize or erase that are not yet defined in the control data set.

  Use the IEHINITT utility to initialize tapes you do not want to be defined to DFSMSrmm. Use the RMM CHANGEVOLUME subcommand to inform DFSMSrmm that the volume has been initialized. If you use tapes that are initialized using a utility other than EDGINERS and do not inform DFSMSrmm, DFSMSrmm can issue message EDG4026I at OPEN time.
- Ends processing when two consecutive errors are detected on the same volume to prevent subsequent volumes from being used incorrectly when a cartridge loader is in use. For example, if an incorrect volume label is read, the volume is demounted and a new mount request issued. Processing is dependent on the operator response to DFSMSrmm message EDG6663D and the WRONGLABEL processing described in “EXEC Parameters for EDGINERS” on page 314.
- Issues a WTOR to the operator when a mount request is issued. A reply to the WTOR is not always required as processing continues as soon as the volume is mounted. The WTOR is issued to allow the operator to skip a volume if the volume cannot be mounted for some reason.
- Bypasses any IOS000I messages for an ’NCA’ error (tape not capable message) when reading the label on a volume that has not been initialized.

For information about preventing or limiting the use of IEHINITT, see “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.

Using EDGINERS

You can use EDGINERS in both automatic and manual processing modes. Automatic processing is driven by initialize and erase actions defined in the control data set. Manual processing is driven by either SYSIN or operator commands. You might set up a job that initializes new volumes using automatic processing to minimize librarian intervention. Use manual processing for initializing volumes when you want to change a known, existing volume serial number to another volume serial number. Ensure that you have enough empty shelf locations to accommodate volumes as they are stored in the removable media library by using the RMM ADDRACK subcommand to define rack numbers to DFSMSrmm.

DFSMSrmm performs EDGINERS automatic processing when you specify any of these EDGINERS EXEC parameters in EDGINERS JCL: COUNT, INITIALIZE, ERASE, MEDIANAME, POOL, or LOCATION. DFSMSrmm ignores SYSIN commands when doing automatic processing.

During automatic processing, each volume to be processed is requested to be mounted, as if it were by any batch job, as no operator reply is required. When the volume is mounted, processing continues. If operators are unable to mount a volume, DFSMSrmm allows them to skip processing of the current requested volume.

As part of expiration processing, DFSMSrmm records the volumes that need to be initialized or erased when they are released or returned to scratch. If you use the EXEC parameters in your JCL to set up automatic processing, DFSMSrmm initializes or erases these volumes without librarian intervention. EDGINERS issues write-to-operator messages and MSGDISP requests to the operator and drive to get a volume mounted and demounted.

You can run EDGINERS automatic processing to initialize volumes you are adding to DFSMSrmm. When you add scratch volumes to DFSMSrmm use the RMM TSO subcommand operand, INIT(Y), on the ADDVOLUME command to ensure volumes are initialized before they are available as scratch. Specify the INITIALIZE Exec parameter in your EDGINERS JCL. DFSMSrmm selects all volumes marked as requiring initialization and performs automatic processing. See “Initializing Scratch Volumes in System-Managed Libraries” on page 84 for information on initialization for volumes in a system-managed library.

Manual processing is performed when you do not specify any EXEC parameters that select automatic processing. Specify commands in the SYSIN file or reply to operator messages to request manual processing. We recommend using manual processing with automatic cartridge loaders and volumes with old labels.

The only required SYSIN command operand is the volume serial number. If the volume serial number is the only SYSIN command operand you specify, DFSMSrmm gets the rest of the information about the volume from the control data set.

If you supply MEDIANAME, POOL, or RACK SYSIN command operands that do not match the existing volume entry, DFSMSrmm issues an error message and stops processing the current volume.

DFSMSrmm can process multiple concurrent invocations of EDGINERS. EDGINERS issues an ENQ using a QNAME of SYSZRMM and an RNAME of EDGINERS.*volser*. *volser* is the volume to be processed.

JCL for EDGINERS

Figure 168 shows sample JCL for automatic processing.

```
//INIT     EXEC PGM=EDGINERS,
//              PARM='MEDIANAME(3480),VERIFY'
//SYSPRINT DD   program message data set
//TAPE     DD   UNIT=(TAPE,,DEFER)
```

Figure 168. JCL for EDGINERS Automatic Processing

Figure 169 shows sample JCL for manual processing.

```
//INIT     EXEC PGM=EDGINERS
//SYSPRINT DD   program message data set
//TAPE     DD   UNIT=(TAPE,,DEFER)
//SYSIN    DD   optional control command input
```

Figure 169. JCL for EDGINERS Manual Processing

The TAPE DD statement is only required if any of the volumes to be processed are not in a system-managed tape library.

Figure 170 shows sample JCL for initializing volumes with ISO/ANSI version 4 tape labels. The EXEC JCL statement can be overridden by control information from SYSIN, operator replies to messages, or information from the DFSMSrmm control data set.

```
//INIT     EXEC PGM=EDGINERS,PARM='..,ALVER4,...'
//SYSPRINT DD   SYSOUT=A
//SYSIN    DD   DUMMY
```

Figure 170. JCL for Initializing Volumes with ISO/ANSI Version 4 VOL1 and HDR1 Labels

EXEC Parameters for EDGINERS

Figure 171 on page 315 describes the EXEC parameters:



WRONGLABEL parameter

STATUS parameter



Pool



MEDIANAME parameter

location

Label parms



Figure 171. EDGINERS EXEC Parameters

ALVER3

Use ALVER3 to initialize tape volumes with ISO/ANSI version 3 VOL1 and HDR1 labels. If you do not specify ALVER3 or ALVER4, DFSMSrmm uses the default label value from the parmlib DEVSUPxx member. Using ALVER3

overrides the use of the system default value defined in DEVSUPxx as the processing default value. The processing default value is only used when an AL tape is labeled and the required label version is not specified for the volume. You can specify the required version for the volume by using the INIT VERSION operand in SYSIN for manual processing or using the RMM ADDVOLUME or RMM CHANGEVOLUME subcommands with the REQUIREDLABELVERSION operand to set the value in the DFSMSrmm control data set.

ALVER4
Use ALVER4 to initialize tape volumes with ISO/ANSI version 4 VOL1 and HDR1 labels. If you do not specify ALVER3 or ALVER4, DFSMSrmm uses the default label value from the parmlib DEVSUPxx member. Using ALVER4 overrides the use of the system default value in DEVSUPxx as the processing default value. The processing default value is only used when an AL tape is labeled and the required label version is not specified for the volume. You can specify the required version for the volume by using the INIT VERSION operand in SYSIN for manual processing or using the RMM ADDVOLUME or RMM CHANGEVOLUME subcommands with the REQUIREDLABELVERSION operand to set the value in the DFSMSrmm control data set.

BATCH(*number_of_batches***)**
Use BATCH to specify the number of batches of volumes to be processed in a single run of EDGINERS in automatic mode. Use the COUNT parameter to specify the batch size. Batch size is the number of volumes that will be initialized or erased before those volumes are verified. After verification is completed for one batch, EDGINERS starts again for the next batch.

If no verification is requested, the number of volumes processed is the BATCH value or its default, multiplied by the value of COUNT or its default. However, DFSMSrmm does not batch the processing of these volumes.

The default for BATCH is BATCH(1). If all volumes in a location or pool with actions pending are to be processed, specify BATCH(0). DFSMSrmm treats BATCH(0) as BATCH(X'FFFFFFFF') the upper limit for the number of batches that DFSMSrmm can process.

COUNT(*count***)**
Use COUNT to specify the number of volumes to be selected for erasure or initialization by DFSMSrmm when automatic processing is being performed. Use COUNT with the BATCH parameter to specify the size of each batch of volumes to be processed. The maximum value you can specify is 99. If automatic processing is in effect but COUNT is omitted then the default value is 10. Specifying COUNT requests automatic processing.

ERASE
Use ERASE to request that DFSMSrmm is to select volumes which have the erase action pending. If automatic processing is in effect but ERASE is not specified then DFSMSrmm will only select volumes with the initialize action pending. Specifying ERASE requests automatic processing.

INITIALIZE
Use INITIALIZE to request that DFSMSrmm is to select volumes that have the initialize action pending. If automatic processing is in effect but neither INITIALIZE nor ERASE are specified then INITIALIZE is the default. You can also specify INITIALISE for INITIALIZE. Specifying INITIALIZE requests automatic processing.

LOCATION(*library_name***)**
Specifies a subset of volumes for automatic processing.

The library name must be one which is defined as a system-managed tape library on the running system or SHELF.

There is no default value.

MEDIANAME(*media_name***)**
Specifies automatic processing. The default value is 3480. MEDIANAME is not used to set a default for the SYSIN INIT and ERASE commands MEDIANAME operand.

You can specify only one of MEDIANAME, POOL, and LOCATION. If none of these operands are specified, all volumes defined as 3480 media name will be selected if they have the required action pending.

The default MEDIANAME is 3480.

POOL(*pool_prefix***)**
Specifies a subset of volumes for automatic processing. Use a value one to five alphanumeric characters long plus an *. The pool must be one that is defined to DFSMSrmm on the running system.

There is no default value.

STATUS
Use STATUS to control the kind of tapes that you want DFSMSrmm to initialize or erase. The default for STATUS is NOTMASTER. Specifying STATUS requests automatic processing.

ALL
EDGINERS processes all volumes that have the INITIALIZE or ERASE action pending.

NOTMASTER
EDGINERS processes all volumes in SCRATCH, USER, INIT, ENTRY or PENDING RELEASE status that have the INITIALIZE or ERASE action pending. EDGINERS does not process any volumes in MASTER status. NOTMASTER is the default.

SCRATCH
EDGINERS processes volumes in SCRATCH, INIT, ENTRY or PENDING RELEASE status that have the INITIALIZE or ERASE action pending. EDGINERS does not process any volumes in MASTER or USER status.

VERIFY|NOVERIFY
Use VERIFY to request that DFSMSrmm ask the operator to remount each volume that has been successfully erased or labeled. The volumes are requested in reverse order, and the volume labels read to ensure no operator errors have occurred, for example, a mismatch between the internal label and the external label.

For automatic processing VERIFY is the default. For manual processing NOVERIFY is the default.

WRONGLABEL
When DFSMSrmm detects that a wrong volume is mounted, it checks to see if the volume is defined to DFSMSrmm.

Use WRONGLABEL to specify the processing DFSMSrmm performs when the wrong volume is mounted. WRONGLABEL can be used when running EDGINERS in both automatic and manual mode.

FAIL
DFSMSrmm does not prompt the operator to accept a mounted volume that does not match the requested volume. The mount request is rejected, the volume demounted, and DFSMSrmm issues message EDG6661E or message EDG6662E.

IGNORE
When the wrong volume is mounted no operator involvement is required and processing proceeds after issuing a message to log the label that was detected. Either message EDG6661E or EDG6662E is issued to log the relabeling. This is an extremely dangerous option and should be used with caution. ANY volume can be relabeled as long as the requested volume has the INIT action or is not defined to DFSMSrmm. Use of this option requires CONTROL access to RACF FACILITY class resource STGADMIN.EDG.INERS.WRONGLABEL.

PROMPT
When an incorrect volume label is detected by EDGINERS for the mounted volume, the operator is always prompted to confirm the processing to be performed. Either message EDG6661E or EDG662E will be issued, followed by message EDG6663D. Processing will continue according to the response to message EDG6663D. This option should be used with caution as ANY volume can be relabeled as long as the requested volume is either known to DFSMSrmm and has the INIT action, or is not known to DFSMSrmm. No additional authorization is required, other than that required for running EDGINERS.

RMMPROMPT
When the volume serial number of the mounted volume does not match the volser of the requested volume and the mounted volume is defined to DFSMSrmm the operator is prompted to confirm processing, via message EDG6663D. If the magnetic volser of the tape is not known to DFSMSrmm, initialization continues as if the tape had no magnetic label. If the volume is known to DFSMSrmm messages EDG6662E and EDG6663D are issued, as for the PROMPT option, otherwise EDG6661E is issued to log the relabeling. The use of this option might be appropriate if the installation has all its volumes known to DFSMSrmm, otherwise caution is required. Use of this option requires UPDATE access to RACF FACILITY class resource STGADMIN.EDG.INERS.WRONGLABEL.

SYSIN Commands for EDGINERS

Use the SYSIN commands for manual processing. You must use separate SYSIN commands for each volume you want initialized or erased. The format of the SYSIN commands and operator replies are shown in Figure 172 on page 319:



Pool



Rack

AL Commands:



Figure 172. EDGINERS SYSIN Commands

ACCESS(*code***)**
Specifies the ISO/ANSI volume accessibility code. Specify *code* as any character in the ISO/ANSI X3.4–1986 character set. You must specify LABEL(AL) if you specify an accessibility code.

You must modify the volume access installation exit routine in MVS/ESA to allow subsequent use of the volume if you specify ACCESS.

The default is blank, allowing unlimited access to the volume.

ERASE
Specify ERASE to security erase a volume and write a new label on it.

You must specify either ERASE or INIT.

INIT
Specify INIT to initialize a volume.

You must specify either INIT or ERASE.

LABEL(NL/SL/AL)
Use LABEL to specify the type of label to be written on the volume:

AL
Specifies an ISO/ANSI Label.

NL
Specifies no label.

SL
Specifies an IBM standard label.

If you do not specify the label type and the volume is already defined in DFSMSrmm, DFSMSrmm uses the label type defined in the DFSMSrmm control data set.

If you do not specify the label type and the volume is not already defined in the control data set, DFSMSrmm uses IBM standard label (SL) as the default.

LABELVERSION(3/4)
Use LABELVERSION to specify the ISO/ANSI volume label version. LABELVERSION applies to AL tapes only. The default label version is the value specified in the parameter field of the EXEC JCL statement. If no label version is specified in the EXEC JCL, DFSMSrmm uses the label information from the parmlib DEVSUPxx member. Using LABELVERSION is the same as issuing the RMM CHANGEVOLUME subcommand with the REQUIREDLABELVERSION operand which updates the DFSMSrmm control data set with the required label version for ISO/ANSI output tapes.

3 Use 3 to initialize tape volumes with ISO/ANSI version 3 VOL1 and HDR1 labels

4 Use 4 to initialize tape volumes with ISO/ANSI version 4 VOL1 and HDR1 labels.

MEDIANAME(*media_name***)**
Specifies the volume's media name.

If the volume is already defined in the DFSMSrmm control data set, DFSMSrmm compares the value you specify to the media name defined in the control data set, and fails the request if they do not match.

If the volume is not defined in the DFSMSrmm control data set, DFSMSrmm uses the value you specify when it adds information about the volume to the control data set. If the volume is not already defined in the control data set and you do not specify a media name, DFSMSrmm uses the media name, 3480.

The default is 3480.

OWNERTEXT(*text***)**
Specifies the owner's name or similar identification. *text* is fourteen characters. Enclose in single quotes if it includes blanks or special characters. The text must be 10 bytes for SL, 14 bytes for AL.

The information is specified as character constants, and can be up to 10 bytes long for EBCDIC and BCDIC volume labels, or up to 14 bytes long for volume labels written in ISCII/ASCII.

POOL(*pool_prefix***)**
Specifies a pool prefix for a pool to which you want to assign the volume. If the volume is not defined to DFSMSrmm, DFSMSrmm selects an available rack number for the volume in the pool you specify. If the volume is already defined in the DFSMSrmm control data set, DFSMSrmm changes the volume's rack number to move the volume.

If you do not supply a pool prefix or a rack number and the volume is already defined in the DFSMSrmm control data set, DFSMSrmm uses the volume's existing rack number. If the volume is not defined in the control data set and

you do not supply a pool prefix or a rack number, DFSMSrmm assigns the volume a rack number matching its volume serial number.

RACK(*rack_number***)**
Specifies a shelf location for the volume. If the volume is already defined in the DFSMSrmm control data set, DFSMSrmm compares the value you specify, and fails the request if it does not match the value in the control data set.

If you do not supply a pool ID or a rack number and the volume is already defined in the control data set, DFSMSrmm uses the volume's existing rack number. If the volume is not defined in the DFSMSrmm control data set and you do not supply a pool ID or a rack number, DFSMSrmm assigns the volume a rack number matching its volume serial number.

VOLUME(*volser***,***new_volser***)**
volser specifies the volume serial number of the volume to be initialized or erased. *Volser* is required. If you are adding volumes with a volume serial number less than six characters, you must supply a rack number or a pool, otherwise DFSMSrmm issues an error message.

If the volume is already defined in the DFSMSrmm control data set, DFSMSrmm ensures that the requested action is pending for the volume. If this action is not pending, DFSMSrmm fails the request.

If the volume mounted is already labeled, DFSMSrmm reads the label to ensures that the volume serial number matches the one you specify. If the volume mounted does not have a recognizable volume label but contains data (no label tapes or nonstandard label tapes), DFSMSrmm issues a WTOR. The operator must reply to this message before DFSMSrmm can initialize or erase the volume.

If the volume is not defined in the DFSMSrmm control data set and you do not specify a new volume serial number, DFSMSrmm adds the volume to the control data set.

new_volser specifies a new volume serial number. Use it if you want to relabel a volume with a new volume serial number. If this new volume is already defined in the DFSMSrmm control data set, DFSMSrmm fails the request.

DFSMSrmm adds information about the new volume to the DFSMSrmm control data set, using information recorded for the volume you are replacing, and then deletes information about the volume you are replacing.

For more information about tape label validation or volume access code, see *z/OS DFSMS: Using Magnetic Tapes*.

Using EDGINERS with System-Managed Tape Libraries

With DFSMS/MVS tape support, you can associate tape drives with specific system-managed tape libraries. As a result, you can mount volumes resident in a system-managed tape library only on the drives associated with that library.

Checking Volumes in System-Managed Tape Libraries

EDGINERS performs the following checking to make sure a volume can be used in a system-managed tape library:

- EDGINERS determines if a volume in a system-managed tape library can be mounted on the current system. If the volume cannot be mounted, possibly because it is defined in a TCDB on another system, DFSMSrmm skips that volume.
- In order to initialize a volume in a system-managed tape library, a volume must be in a private category because the automated tape library dataserver does not support specific mounts of scratch volumes. RMM TSO command and release processing attempts to ensure that the volume is in the correct category so that EDGINERS does not have to check the volume status. Refer to “Setting Status for a Volume in a System-Managed Tape Library” on page 323 for more information about setting the status for a volume.
- You must define a volume in a system-managed tape library to DFSMSrmm before you can initialize or erase it. Any volume not defined to DFSMSrmm will be requested to be mounted on the drive allocated by the TAPE DD statement in the JCL for EDGINERS as long as the drive is not in a system-managed library.

Requesting Volume Mounts for System-Managed Tape Libraries

EDGINERS requests volume mounts only on those drives on which the volumes can be mounted, by testing volume eligibility and using dynamic allocation to obtain a suitable drive for each volume to be processed.

DFSMSrmm uses the pre-allocated drive if it is available. If the pre-allocated drive is not available, EDGINERS dynamically allocates a drive using the first volume obtained from the control data set. Further processing checks that the subsequent volumes are eligible for use on the same drive. If the pre-allocated drive is not in a system-managed tape library, DFSMSrmm uses it for all volumes selected that are not resident in a system-managed tape library.

When dynamic allocation of a tape drive fails, EDGINERS sets return code to 4 and skips processing of the current volume. Messages describing the failure are issued. These might include messages prefixed with IKJ and CBR. In most cases you will see a return and reason code returned from OAM. For example, OAM issues return code 8 and reason code 51 to indicate that the requested volume is in scratch status. This error might be the result of a mismatch between the DFSMSrmm control data set and TCDB volume status. You can correct this by updating the status in the TCDB to match that known by DFSMSrmm. Refer to *z/OS DFSMSdfp Diagnosis Reference* for information about OAM return and reason codes.

Running EDGINERS on Multiple System Complexes

You can run EDGINERS on multiple system complexes to ensure that all required volumes are erased or initialized. To select a subset of volumes to initialize or erase, you can specify POOL and LOCATION with the EDGINERS EXEC parameter.

Running EDGINERS on a 3494 in Manual Mode

DFSMSrmm can determine the status of the vision system and if the library is in manual mode. EDGINERS can automatically handle some errors when an automated tape library is fully functional. For example, when the library is fully functional, DFSMSrmm uses the vision system volume serial number to verify that the correct volume is mounted.

Mounting and Demounting Volumes

EDGINERS provides a way to direct to an automated tape library the WTOR messages and MSGDISP requests to the operator and drive to get a volume mounted and demounted. These messages are issued through the library automation communication services component of OAM. If a mount on an

automated tape library drive fails, DFSMSrmm uses the return and reason codes set by the library automation communication services component to test if a volume should be skipped.

During demount processing, DFSMSrmm ensures that errors detected on volumes mounted in an automated tape library are reflected in the TCDB. For example, DFSMSrmm ensures the TCDB contains information about write-protected, wrong volume, and wrong label type errors. DFSMSrmm skips the volume rather than having the operator correct the error.

Using DFSMSdfp Processing to Label Volumes

For volumes in an automated tape library dataserver, you have the option to use DFSMSdfp OPEN processing as an alternative to using EDGINERS to label scratch volumes.

If the automated tape library dataserver is fully functional (vision system working) and the VOL1 label for a scratch volume does not match the external label, DFSMSdfp rewrites the VOL1 label with the correct volser.

DFSMSrmm defers the initialization of the volumes to DFSMSdfp if you request the initialization prior to entering a scratch volume into the automated tape library dataserver. DFSMSrmm turns off the initialize action.

For example you use the RMM ADDVOLUME subcommand to define scratch volumes to DFSMSrmm as shown in Figure 173. Specify INIT(Y) to request that the volume is initialized prior to first use. If you later enter the volumes into an automated tape library dataserver, during entry processing DFSMSrmm turns off the initialize action to defer the labeling to OPEN processing under DFSMSdfp control.

```
RMM ADDVOLUME A12345 INIT(Y) STATUS(SCRATCH)
```

Figure 173. Defining Scratch Volumes to be Initialized

If you request that the initialize action is set for a scratch volume that is already resident in the automated tape library dataserver, as shown in Figure 174 using the RMM CHANGEVOLUME subcommand, DFSMSrmm does not defer the initialization to DFSMSdfp. You must use EDGINERS to label the tape before it can be used.

```
RMM CHANGEVOLUME A12345 INIT(Y)
```

Figure 174. Changing the Initialization Action for a Volume

Setting Status for a Volume in a System-Managed Tape Library

DFSMSrmm maintains volume status in the TCDB for volumes defined in the DFSMSrmm control data set. The status is updated using the RMM TSO commands or when volumes are released. When DFSMSrmm is running in record-only mode, DFSMSrmm does not ensure that the TCDB is updated so the volume status might not be correct. If the TCDB is not updated, the request to initialize or erase a volume in a system-managed tape library might fail because the volume is in a scratch library category. If DFSMSrmm is still running in record-only mode, use the AMS ALTER VOLUMEENTRY command to change the volume status. If DFSMSrmm is running in any other mode, you can use the RMM TSO commands to correct the volume status.

To set the correct status for the volume, issue two commands. Issue the following command to complete the failed request.

```
RMM CHANGEVOLUME A12345 CONFIRMRELEASE(INIT)
```

Then issue following command to request that the volume be initialized.

```
RMM CHANGEVOLUME A12345 INIT(Y)
```

Controlling Access to EDGINERS

You should control access to EDGINERS because it can overwrite previously labeled tapes regardless of expiration date and security protection. DFSMSrmm helps you prevent unauthorized users from using EDGINERS by using the RACF security resource STGADMIN.EDG.OPERATOR. Only users with access to STGADMIN.EDG.OPERATOR can use EDGINERS.

For more information about using STGADMIN.EDG.OPERATOR, see “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153.

How EDGINERS Processing Works

Each volume label that EDGINERS creates contains:

- A standard volume label with a serial number you specify and a blank security byte. The format of the ISO/ANSI label is constructed for Version 3 of the label standard. For a complete description of IBM standard volume labels and ISO/ANSI Version 3 volume labels, see *z/OS DFSMS: Using Magnetic Tapes*.
- An 80-byte dummy header label. For IBM standard labels, this header consists of the characters HDR1 followed by zeros. For ISO/ANSI labels, this header consists of the characters HDR1 followed by zeros, with the following exceptions:
  - Position 54, which contains an ISCII/ASCII space
  - A 1 in the file section, file sequence, and generation number fields
  - A leading space in the creation and expiration date fields
  - A system code of IBMZLA, followed by 13 spaces, to identify the operating system creating the label
- A tape mark.

The first time a tape labeled by EDGINERS is used for output, the following sequence of events occurs:

1. The tape mark that EDGINERS created is overwritten.
2. The dummy header label that EDGINERS created is filled in with operating system data and device-dependent information.
3. A HDR2 record, containing data set characteristics, is created.
4. User header labels are written if exits to user label routines are provided.
5. A new tape mark is written.
6. Data is placed on the receiving volume.

When relabeling a volume defined to DFSMSrmm, DFSMSrmm uses the information recorded about the old volume as part of the new volume information recorded in the control data set.

The following information is taken from the old volume record: Expiration Date, Density, Use Count, Store Id, Bin Number, Old Bin Number, Loan Location, Previous Location, Last Read and Write dates, Assigned Date and Time, Owner,

Status, Label Type, Release actions, Actions Pending (excluding initialize and erase), Volume access and accessors, Unit name, Rack number, Temporary / Permanent Read / Write error counts.

When a volume that resides in an automated system-managed tape library is rejected at OPEN time because the tape media servo tracks require formatting, DFSMSrmm updates the volume information in the control data set. DFSMSrmm sets the volume INIT action to indicate that the volume must be initialized. If EDGINERS is used to relabel a volume and servo tracks have not been formatted, DFSMSrmm cannot initialize the volume.

If you initialize an ISO/ANSI label with EDGINERS only, the labels do not frame an empty, or null, data set as required for interchange. To produce a label symmetry that meets ISO/ANSI standards, at least a minimal open/close sequence must be performed. For example, a volume previously initialized with EDGINERS results in label symmetry if you use the data set utility IEBGENER before the volume leaves the system for interchange, as shown in Figure 175:

```
//STEP1   EXEC  PGM=IEBGENER
//SYSUT1  DD    DUMMY,DCB=(RECFM=F,BLKSIZE=80,LRECL=80)
//SYSUT2  DD    DSN=DUMMY,UNIT=(tape,,DEFER),LABEL=(,AL),
                DCB=(RECFM=F,BLKSIZE=80,LRECL=80)
//SYSIN   DD    DUMMY
```

Figure 175. Using IEBGENER

Return Codes for EDGINERS

EDGINERS issues one of the return codes shown in Table 52.

Table 52. EDGINERS Return Codes

Return Code	Explanation
0	All requested functions completed successfully.
4	DFSMSrmm encountered a minor error during processing. It issues a warning message and continues processing.
8	DFSMSrmm has stopped at least one requested function. It continues processing the next requested function.
12	DFSMSrmm encountered a severe error during processing of one of the requested functions. DFSMSrmm stops the utility.
16	DFSMSrmm encountered a severe error during a required communication with the DFSMSrmm subsystem. DFSMSrmm stops the utility.

EDGINERS Examples

The following examples illustrate some of the uses of EDGINERS. To use the examples, replace the **tape** specified in the examples with actual device numbers or esoteric unit names, unless your installation has the required device numbers defined to the esoteric name ‘TAPE’. The actual device numbers and esoteric unit names depend on how your installation has defined the devices to your system. See *z/OS DFSMS: Using Magnetic Tapes* for devices supported by this utility.

Example 1: Write IBM Standard Labels on Three Tapes

Figure 176 is a manual processing example. Serial numbers 001234, 001235, and 001236 are placed on three tape volumes. The labels are written in EBCDIC at 800 bits per inch. Each volume labeled is mounted, when it is required, on a single 9-track tape unit. You must specify SYSIN commands for each volume you want to label, as Figure 176 shows.

```
//LABEL1   JOB  ...
//STEP1    EXEC PGM=EDGINERS
//SYSPRINT DD  SYSOUT=A
//TAPE     DD  DCB=DEN=2,UNIT=(tape,1,DEFER)
//SYSIN    DD  *
INIT VOL(001234) LABEL(SL)
INIT VOL(001235) LABEL(SL)
INIT VOL(001236) LABEL(SL)
/*
```

Figure 176. Writing IBM Standard Labels on Three Tapes

Control statement description:

- TAPE DD defines the tape unit used in the labeling operation.
- SYSIN DD defines the control data set, which follows in the input stream.
- INIT specifies that the tapes are to be labeled.

Example 2: Write an ISO/ANSI Label on a Tape

Figure 177 is a manual processing example. Serial number 001001 is placed on one ISO/ANSI tape volume; the label is written at 800 bits per inch. The volume labeled is mounted, when it is required, on a 9-track tape unit. You must specify SYSIN commands for each volume you want to label, as Figure 177 shows.

```
//LABEL2   JOB  ...
//STEP1    EXEC PGM=EDGINERS
//SYSPRINT DD  SYSOUT=A
//TAPE     DD  DCB=DEN=2,UNIT=(tape,1,DEFER)
//SYSIN    DD  *
INIT VOL(001001) LABEL(AL)
/*
```

Figure 177. Writing an ISO/ANSI Label on a Tape

Control statement description:

- TAPE DD defines the tape volume to be used in the labeling operation.
- SYSIN DD defines the control data set, which follows in the input stream.
- INIT specifies the serial number and label type for the volume that is being labeled.

Example 3: Place Two Groups of Serial Numbers on Six Tape Volumes

Figure 178 on page 327 is a manual processing example. Two groups of serial numbers (001234, 001235, 001236, and 001334, 001335, 001336) are placed on six tape volumes. The labels are written in EBCDIC at 800 bits per inch. Each volume labeled is mounted, when it is required, on a single 9-track tape unit. You must specify SYSIN commands for each volume you want to label, as Figure 177 shows.

```
//LABEL3   JOB  ...
//STEP1    EXEC PGM=EDGINERS
//SYSPRINT DD  SYSOUT=A
//TAPE     DD  DCB=DEN=2,UNIT=(tape,1,DEFER)
//SYSIN    DD  *
INIT  VOL(001234) LABEL(SL)
INIT  VOL(001235) LABEL(SL)
INIT  VOL(001236) LABEL(SL)
INIT  VOL(001334) LABEL(SL)
INIT  VOL(001335) LABEL(SL)
INIT  VOL(001336) LABEL(SL)
/*
```

Figure 178. Numbering Tape Volumes

Control statement description:
- TAPE DD defines the tape unit to be used in the labeling operation.
- SYSIN DD defines the control data set, which follows in the input stream.
- INIT specifies that the tapes are to be labeled.

Example 4: Place Serial Numbers on Eight Tape Volumes

Figure 179 is a manual processing example. Serial numbers 001234, 001244, 001254, 001264, 001274, and so on in a sequence, are placed on eight tape volumes. The labels are written in EBCDIC at 800 bits per inch. Each volume labeled is mounted, when it is required, on a single 9-track tape unit. You must specify SYSIN commands for each volume you want to label, as Figure 179 shows.

```
//LABEL4   JOB  ...
//STEP1    EXEC PGM=EDGINERS
//SYSPRINT DD  SYSOUT=A
//TAPE     DD  DCB=DEN=2,UNIT=(tape,1,DEFER)
//SYSIN    DD  *
INIT VOL(001234) LABEL(SL)
INIT VOL(001244) LABEL(SL)
INIT VOL(001254) LABEL(SL)
INIT VOL(001264) LABEL(SL)
INIT VOL(001274) LABEL(SL)
INIT VOL(001284) LABEL(SL)
INIT VOL(001294) LABEL(SL)
INIT VOL(001304) LABEL(SL)
/*
```

Figure 179. Placing Serial Numbers on Eight Tape Volumes

Control statement description:
- TAPE DD defines the tape unit used in the labeling operation.
- SYSIN DD defines the control data set, which follows in the input stream.
- The INIT statements specify the tapes to be labeled.

Example 5: Relabel a Volume

Figure 180 on page 328 is a manual processing example for relabeling a volume. Supply both the current and the new volume serial number in your SYSIN statement. In the example the volume that is currently labeled as CURR01 is relabeled to NEW001.

If volume CURR01 is already defined to DFSMSrmm, DFSMSrmm defines a new volume entry NEW001 to the DFSMSrmm control data set using information from the existing volume entry CURR01 and deletes the existing volume entry. If volume

CURR01 is not defined to DFSMSrmm, DFSMSrmm defines a new volume entry NEW001 in the control data set.

```
//INIT     EXEC PGM=EDGINERS
//SYSPRINT DD SYSOUT=*
//TAPE     DD UNIT=(tape,,DEFER)
//SYSIN    DD *
INIT VOLUME(CURR01,NEW001) LABEL(SL)
```

Figure 180. Relabeling a Volume

Control statement description:

- TAPE DD defined the tape unit to be used in the labeling operation.
- INIT specifies the current and new tape labels.

Example 6: Automatically Initialize or Erase 3480 Volumes

Figure 181 is an automatic processing example. EDGINERS requests that DFSMSrmm scan its control data set for the first ten 3480 volumes waiting to be initialized or erased.

```
//LABEL5   JOB  ...
//STEP1    EXEC PGM=EDGINERS,PARM='INITIALIZE,ERASE,COUNT(10)'
//SYSPRINT DD SYSOUT=*
//TAPE     DD UNIT=(3480,,DEFER)
```

Figure 181. Automatically Initialize or Erase 3480 Volumes

Control statement description:

- TAPE DD defines the tape unit used in the labeling operation.

Example 7: Initialize and Erase Volumes in a System-Managed Library

In Figure 182 an automatic run of EDGINERS is scheduled to find, initialize, and erase up to 99 volumes residing in an automated tape library dataserver called MYATL. All tape cartridges will be labeled as appropriate for the drive type on which they are mounted, and for their current media characteristics.

```
//LABEL6 JOB ....
//STEP1 EXEC PGM=EDGINERS,
//     PARM='COUNT(99),LOCATION(MYATL),INITIALIZE,ERASE'
//SYSPRINT  DD  SYSOUT=A
```

Figure 182. Initialize and Erase Volumes in a System-Managed Library

Control statement description:

- Tape DD and SYSIN DD are not required.
- PARM values request automatic processing with the default of VERIFY of all labeled volumes.

Example 8: Initialize 50 Scratch Enhanced Capacity Cartridges

In Figure 183 on page 329, an automatic run of EDGINERS is used to initialize 50 scratch enhanced capacity cartridges defined to DFSMSrmm in the previous job step, and initialize them for use in a non-system managed tape library. This example assumes that no other volumes in the pool need to be initialized.

```
//LABEL7  JOB ...
//STEP1 EXEC PGM=IKJEFT01
//SYSTPRINT  DD  SYSOUT=A
//SYSTSIN  DD  *
  RMM ADDVOLUME A00100 STATUS(SCRATCH) INIT(Y) -
          COUNT(50) LOCATION(SHELF) MEDIATYPE(ECCST)
/*
//STEP2 EXEC PGM=EDGINERS,
//    PARM='COUNT(50),POOL(A*),INITIALIZE,NOVERIFY'
//SYSPRINT  DD  SYSOUT=A
//TAPE  DD  UNIT=(tape,1,DEFER)
```

Figure 183. Initialize 50 Scratch Enhanced Capacity Cartridges

Control statement description:
- SYSTSIN DD includes commands to define required volumes.
- TAPE DD allocates a drive capable of labeling enhanced capacity cartridges.

Example 9: Erase a Volume

In Figure 184, volume 0A7100 is erased and defined to DFSMSrmm. The volume is successfully erased and the volume label is written as an ISO/ANSI label.

```
//LABEL8 JOB ....
//STEP1 EXEC PGM=EDGINERS
//SYSPRINT  DD  SYSOUT=A
//TAPE  DD  UNIT=(tape,,DEFER)
//SYSIN  DD  *
  ERASE VOL(0A7100) LABEL(AL)
/*
```

Figure 184. Erase a Volume

Control statement description:
- Tape DD allocates a drive suitable for this volume.
- SYSIN DD includes the command requested to erase the volume.

Chapter 18. Customizing DFSMSrmm

This chapter helps you customize DFSMSrmm to best meet your installation's needs.

Changing the Initial Entry Point to the DFSMSrmm Dialog

Normally, when you enter the DFSMSrmm ISPF dialog, the first panel you see is the Primary Option Menu. You can change this initial entry point so tape librarians always see the Librarian Menu when they enter DFSMSrmm or general users see the DFSMSrmm User Menu.

To change the initial entry point, use the RMMISPF exec with one of its optional parameters which changes the panel navigation to go directly to a lower level. Figure 185 shows the operands you can use with the RMMISPF exec:



Figure 185. RMMISPF Exec Syntax Diagram

Each of the operands, except for TRACE, represents a specific user or function menu from which you can request functions. Use the TRACE(option) operand to diagnose problems in any of the REXX execs supplied in the dialog. For more information about using TRACE, see *z/OS DFSMSrmm Diagnosis Guide*.

To start the librarian at the Librarian Menu, add

```
%    R +DFSMSrmm   - Librarian dialog
```

to the ISPF selection panel as shown in Figure 186 on page 332. Although the example shows the ISRUTIL panel, you can use any other selection panel to make the changes.

© Copyright IBM Corp. 1992, 2001

```
%------------------------  UTILITY SELECTION MENU  ---------------------
%OPTION  ===>_ZCMD
%
%    1 +LIBRARY    - Compress or print data set.  Print index listing.
+                     Print, rename, delete, or browse members
%    2 +DATASET    - Allocate, rename, delete, catalog, uncatalog, or
+                     display information of an entire data set
%    3 +MOVE/COPY  - Move, copy, or promote members or data sets
%    4 +DSLIST     - Print or display (to process) list of data set names
+                     Print or display VTOC information
%    5 +RESET      - Reset statistics for members of ISPF library
%    6 +HARDCOPY   - Initiate hardcopy output
%    8 +OUTLIST    - Display, delete, or print held job output
%    9 +COMMANDS   - Create/change an application command table
%   10 +CONVERT    - Convert old format menus/messages to new format
%   11 +FORMAT     - Format definition for formatted data Edit/Browse
%   12 +SUPERC     - Compare data sets (Standard dialog)
%   13 +SUPERCE    - Compare data sets (Extended dialog)
%   14 +SEARCH-FOR - Search data sets for strings of data
%    R +DFSMSrmm   - Librarian dialog
)INIT
  .HELP = ISR30000
)PROC
  &ZSEL = TRANS( TRUNC (&ZCMD,'.')
                1,'PGM(ISRUDA) PARM(ISRUDA1)'
                2,'PGM(ISRUDA) PARM(ISRUDA2)'
                3,'PGM(ISRUMC)'
                4,'PGM(ISRUDL) PARM(ISRUDLP)'
                5,'PGM(ISRURS)'
                6,'PGM(ISRUHC)'
                8,'PGM(ISRUOLP)'
                9,'PANEL(ISPUCMA)'
               10,'PGM(ISRQCM) PARM(ISRQCMP)'
               11,'PGM(ISRFMT)'
               12,'PGM(ISRSSM)'
               13,'PGM(ISRSEPRM) NOCHECK'
               14,'PGM(ISRSFM)'
               R,'CMD(%RMMISPF LIBRARIAN) NEWAPPL(EDG)'
              ' ',' '
                *,'?' )
  &ZTRAIL = .TRAIL
)END
```

Figure 186. Adding DFSMSrmm Librarian Option to ISPF

Adding Local Dialog Extensions

You can add your own local extensions to the DFSMSrmm ISPF dialog. DFSMSrmm has a dummy panel, EDGP@LCL, that provides easy access to local dialog extensions. You can use these extensions without having to modify DFSMSrmm. Use the following steps to add your extensions:

1. Create a selection menu, EDGP@LCL, that includes the extensions you want to add.
2. For each extension, create the required procedures and panels.
3. Make the local menu available to ISPF in a panel library so that it is selected ahead of the menu DFSMSrmm supplies.
4. Start the DFSMSrmm ISPF dialog.
5. Select Option 6 (LOCAL). You should see the modified local selection menu you just created.

You do not have to limit the local extensions to functions that use DFSMSrmm commands and utilities. Add any function that is useful to DFSMSrmm users, such as the tape librarian and storage administrator. For example, you could add:

- Service level reporter charts on tape activities
- A link to ISMF or RACF dialogs
- Lists of DFSMShsm volumes to compare with DFSMSrmm definitions
- A volume loan facility that enforces local standards for location names

When including RMM TSO subcommands, use the REXX procedure language instead of CLIST. RMM TSO subcommands set REXX variables so you do not need to trap and interpret the command output. Refer to the REXX procedures DFSMSrmm supplies for examples of using the subcommands and receiving variables. Do not modify the supplied execs because they can change from one release to the next.

For more information on using the RMM TSO subcommands within REXX and the variables each subcommand issues, see *z/OS DFSMSrmm Guide and Reference*.

Changing the ADD Product Volume Defaults

When you use the DFSMSrmm ISPF dialog to define product volumes to DFSMSrmm, the dialog issues either the RMM TSO CHANGEVOLUME or ADDVOLUME subcommand.

When ADDVOLUME is used, the dialog has some hard-coded default values set for RETPD and RELEASEACTION. You can modify the dialog EXEC EDGRPADV to change the values to ones that suit your installation.

The EDGRPADV dialog default is:

```
command = edgcmd" ADDVOLUME "edg@vol" STATUS(MASTER)" ,
          "NUMBER('"edgraddq(edg@pnum)"') LEVEL("edg@ver")",
          "FEAT("edg@fcd")" ,
          "MEDIANAME('"edgraddq(edg@medn)"')",
          "LOCATION("edg@loc") RETPD(90) RELEASE(RETURN)"
```

If you plan to modify the values that the EDGRPADV EXEC uses we recommend that you install your changes using an SMP/E USERMOD after editing a copy of the EDGRPADV EXEC. The only modifications you should make are to either add new operands to the ADDVOLUME command, or to change the values set for the MASTER, RETPD, and RELEASE operands.

Customizing DFSMSrmm Messages

DFSMSrmm provides messages for report titles and user notification. You can customize them by:

1. Updating the text of a message in the DFSMSrmm message table EDGMTAB.
2. Applying changes to EDGMTAB by creating an SMP/E-installable USERMOD.

Customizing DFSMSrmm Report Titles

You can customize the title text on DFSMSrmm reports. For example, you can add your company's name to the bottom of each report page.

To customize, update the text of a message in the DFSMSrmm message table EDGMTAB. The report utilities get the message text from the message table and

use it when creating the report trailer lines. Table 53 shows the message numbers DFSMSrmm uses for each report utility:

Table 53. Customizing Report Titles

Utility	Message Number	Used For
EDGAUD	5839	security report trailer 1
EDGAUD	5840	security report trailer 2
EDGAUD	5846	audit report trailer 1
EDGAUD	5847	audit report trailer 2
EDGHSKP	2203	EDGHSKP REPORT file header
EDGRPTD	5825	trailer line 1

To customize the message text, edit the message text in the EDGMTAB source, supplied with the product. You could change trailer 1 for EDGRPTD, as shown in the following examples. Figure 187 shows the text before modification:

```
EDGMSGB 5825,TYPE=I,                                          X
      '                                        ',             X
      MOD=NO
```

Figure 187. Before Modifying the Trailer 1 for EDGRPTD

Figure 188 shows the text after modification:

```
EDGMSGB 5825,TYPE=I,                                          X
      'Warwick Corporation',                                  X
      MOD=NO
```

Figure 188. After Modifying the Trailer 1 for EDGRPTD

The report utility centers the text before printing.

Customizing Notification Messages and Notes

With DFSMSrmm you can set up automatic notification to owners by setting a parmlib option and defining owner electronic address to DFSMSrmm. Refer to “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115 for information on setting up automatic notification and controlling message text case.

DFSMSrmm provides a series of messages in the DFSMSrmm message module, EDGMTAB. You can modify them to provide specific information to users:

Messages EDG2405 through EDG2409
Notify users that volumes they own are eligible for release.

Messages EDG2700 through EDG2713
Create a note you send to product owners when new volumes for a product are entered into the library.

When modifying messages, you should:

- Keep message variables in the same order as in the original message.
- Use the same number of substitution characters as shown in the original message text.

- Keep the messages in the same order they are displayed.
- Do not delete any messages from EDGMTAB. If you do not want to use a particular message, leave the message text blank.

Modifying Text for Release Notification

Modify messages 2405-2409 to change the message text to notify users that their volumes are eligible for release.

You can substitute the message text without restriction for all the messages except message 2406. For message 2406, you must specify the secondary currency character X'4A' to represent substitution characters for variables that DFSMSrmm supplies. The secondary currency character shown in Figure 189 is ¢. You must also keep the variables in the order shown in Figure 189. The &NAM variable shown in message 2405 is replaced with the product name and need not be specified.

Figure 189 shows the messages in EDGMTAB before modification:

```
EDGMSGB 2405,TYPE=I,                                          X
      'Subject: &NAM volume expiration',                      X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2406,TYPE=I,                                          X
      'Volume ¢¢¢¢¢ assigned to owner ¢¢¢¢¢¢¢ on ¢¢¢¢¢¢¢¢¢ X
      at ¢¢:¢¢:¢¢',                                           X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2407,TYPE=I,                                          X
      'is now pending release.',                              X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2408,TYPE=I,                                          X
      'If you wish the volume to be retained, please take immeX
      diate action.',                                         X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2409,TYPE=I,                                          X
      'You can use the dialog functions or the RMM CHANGEVOLUMX
      E TSO command.',                                        X
      MOD=NO,MSGID=NO
```

Figure 189. Notify Owner Messages

Figure 190 shows the notification text resulting from Figure 189.

```
Subject: DFSMSrmm volume expiration
Volume LAUREN assigned to owner KRISTINE on 1998/01/01 at 09:45:11
is now pending release.
If you wish the volume to be retained, please take immediate action.
You can use the dialog functions or the RMM CHANGEVOLUME TSO COMMAND.
```

Figure 190. Default Notification Text

Figure 191 on page 336 shows the same messages after modification:

```
EDGMSGB 2405,TYPE=I,                                          X
      'Subject:   Bld 88 Tape Volume Expiration               X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2406,TYPE=I,                                          X
      'Volume ¢¢¢¢¢¢ assigned to owner ¢¢¢¢¢¢¢¢ on ¢¢¢¢¢¢¢¢¢¢ x
      at ¢¢:¢¢:¢¢',                                           x
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2407,TYPE=I,                                          X
      'has now expired.  Please come to the Computer Room Tapex
       Library Window',                                       x
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2408,TYPE=I,                                          X
      'to pick up the tape.  Contact the tape librarian at 555x
      -5796 for any',                                         x
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2409,TYPE=I,                                          X
      'questions.  DO NOT REPLY to this automated system messax
      ge.  Thanks.  ',                                        x
      MOD=NO,MSGID=NO
SPACE 2
```

Figure 191. Modified Messages

Figure 192 shows the text resulting from Figure 191.

```
Subject: Bld 88 Tape Volume Expiration.
Volume LAUREN assigned to owner KRISTINE on 1998/01/01 at 09:45:11
has now expired.  Please come to the Computer Room Tape Library Window
to pick up the tape.  Contact the tape librarian at 555-5796 for any
questions.  DO NOT REPLY to this automated system message.  Thanks.
```

Figure 192. Modified Notification Text

Modifying Text in Notes to Product Owners

DFSMSrmm provides note text for notifying product owners when:

- A new software product volume is added to DFSMSrmm.
- A change is made to add a volume to a product.
- The software level of a product volume is changed.

You can modify the note by modifying messages EDG2700 through EDG2713. Figure 193 on page 337 shows an example of a note produced by modifying EDG2700 through EDG2713.

```
Subject: Volume PP0001 has been added for software product 5647-A01
A volume has been added on 1999/12/27 at 20:19:31 to a DFSMSrmm
software product which you own:

 Product Number = 5694-A01  Level = V01R01M00
 Name           = z/OS  Version 1.1
 Description    = includes rmm

 Volume   Rack     Feature Code   Description
 ------   ------   ------------   ------------------------------
 PP0001   PP1233   5678           z/OS     V1.1 (volume 1 of 1)
```

Figure 193. Notifying Product Owner

Figure 194 on page 338 shows the messages you can modify. The messages must be displayed in sequence to produce the note. Several messages consist of blank lines so you have flexibility in the note you send. You can also line up the columns in your message text as shown in message EDG2710.

```
EDGMSGB 2700,TYPE=I,                                            X
      'Subject: Volume ¢¢¢¢¢ has been added for software prodX
      uct ¢¢¢¢¢¢¢',                                             X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2701,TYPE=I,                                            X
      'A volume has been added on ¢¢¢¢¢¢¢¢¢ at ¢¢:¢¢:¢¢ to a X
      &NAM',                                                    X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2702,TYPE=I,                                            X
      'software product which you own:',                        X
      MOD=NO,MSGID=NO
```

Figure 194. Notify Product Owner Messages (Part 1 of 3)

```
SPACE 2
EDGMSGB 2703,TYPE=I,                                            X
      '                                                         X
                ',                                              X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2704,TYPE=I,                                            X
      ' Product Number = ¢¢¢¢¢¢¢  Level = V¢¢R¢¢M¢¢',          X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2705,TYPE=I,                                            X
      ' Name           = ¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢',     X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2706,TYPE=I,                                            X
      ' Description    = ¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢',     X
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2707,TYPE=I,                                            X
      '                                                         X
                ',                                              X
      MOD=NO,MSGID=NO
```

Figure 194. Notify Product Owner Messages (Part 2 of 3)

```
SPACE 2
EDGMSGB 2708,TYPE=I,                                          X
      ' Volume   Rack     Feature Code   Description',        X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2709,TYPE=I,                                          X
      ' ------   ------   ------------   ----------------------X
      ---------',                                             X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2710,TYPE=I,                                          X
      ' ¢¢¢¢¢   ¢¢¢¢¢  ¢¢¢¢           ¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢¢X
       ¢¢¢¢¢¢¢¢¢',
      MOD=YES,MSGID=NO
SPACE 2
EDGMSGB 2711,TYPE=I,                                          X
      '                                                       X
                ',                                            X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2712,TYPE=I,                                          X
      '                                                       X
                ',                                            X
      MOD=NO,MSGID=NO
SPACE 2
EDGMSGB 2713,TYPE=I,                                          X
      '                                                       X
                ',                                            X
      MOD=NO,MSGID=NO
```

Figure 194. Notify Product Owner Messages (Part 3 of 3)

Managing VM Tape Volumes

DFSMSrmm Samples Provided in SAMPLIB

- EDGCLIBQ Sample Exec to Create Reports for VM Tape Volumes
- EDGJVME Sample JCL for Creating Reports for VM Tape Volumes

DFSMSrmm provides SAMPLIB members to help you manage VM tapes. The sample, EDGJVME, is a batch job that creates a list of volumes flagged for VM use. EDGJVME gets the information from the extract data set. The job sends this list to the relevant VM system.

When you have received the list on the VM system, you can use the sample, EDGCLIBQ. EDGCLIBQ is an exec that produces information about the volumes on the list, including shelf location, owner, and users allowed to access the volumes.

DFSMSrmm provides the LIBQ exec to help you query information about VM volumes. Use the LIBQ exec to get the location where a volume resides. This describes one scenario for using the LIBQ exec.

1. A user requests a volume to be mounted on VM by sending a message to the operator.
2. The operator issues the LIBQ exec, with the volume serial number requested as ‘LIBQ volser’.

3. The LIBQ exec returns the rack number where the volume resides to the operator.
4. The operator decides whether to mount the volume as requested by the user.
5. The operator attaches the drive with the volume mounted, as requested.

If you want to use the LIBQ exec to find a scratch volume, modify the exec to search for scratch volumes in the file it processes. You can tailor the rules you want to use for 'in use' or scratch volumes, or modify the exec and use it as part of your VM tape automation. You might also tailor the process to work with other non-MVS platforms.

Replenishing Scratch Volumes in a System-Managed Library

DFSMSrmm Sample Provided in SAMPLIB

- EDGXPROC Sample to Replenish Scratch Volumes in a System-Managed Library
- EDGSETT Sample that you can use in Tivoli OPC in place of EDGXPROC.

When a tape library dataserver detects a low-on-scratch condition, where more scratch volumes are needed, OAM issues a write-to-operator message (CBR3660A). DFSMSrmm intercepts the message and starts the procedure you define with the SCRATCHPROC value in parmlib. See "Defining System Options: OPTION" on page 122 for more information about specifying SCRATCHPROC. You must run DFSMSrmm with a scratch procedure. You can modify the DFSMSrmm supplied sample, EDGXPROC, to support your location procedures. You can use the scratch procedure to take any action you would like. For example, you can code the procedure to trigger the required inventory management expiration processing job, to run inventory management, or to take no action.

You can use the DFSMSrmm supplied sample procedure, EDGXPROC, which runs DFSMSrmm expiration processing to replenish the automated tape library dataserver's scratch volumes. If you use the DFSMSrmm supplied sample, EDGXPROC, you must define the procedure in the installation procedure library, SYS1.PROCLIB as described in "Step 8: Updating the Procedure Library" on page 30.

You can modify this procedure, for example, to alert the operator if scratch volumes are not replenished. Figure 195 shows the EDGXPROC procedure:

```
//EDGXPROC PROC OPT=EXPROC
//EDGHSKP  EXEC PGM=EDGHSKP,
//         PARM='&OPT.'
//SYSPRINT DD SYSOUT=*
//MESSAGE  DD DSN=MESSAGE.FILE.NAME,DISP=SHR
```

Figure 195. EDGXPROC Procedure

DFSMSrmm keeps track of the time and date the procedure starts and when it last ran expiration processing to ensure that one procedure completes processing before a new procedure begins. You can display this information using the RMM LISTCONTROL subcommand with the CNTL operand.

Automating Backup

DFSMSrmm Sample Provided in SAMPLIB

- EDGBETT Sample that you can use in Tivoli OPC automating backup.

Create a backup procedure in the system procedure library. Figure 196 shows an example of a procedure that runs backup as part of inventory management. Alternatively, you might want to use the procedure to submit a batch job to perform the backup or to inform your job scheduler to submit the job.

Specify your backup procedure name with the BACKUPPROC value in parmlib. See “Defining System Options: OPTION” on page 122 for more information about specifying BACKUPPROC.

```
//CDSBKUP  PROC
//EDGHSKP  EXEC PGM=EDGHSKP,PARM='BACKUP(DSS)'
//MESSAGE  DD DISP=SHR,DSN=RMM.MESSAGE
//SYSPRINT DD SYSOUT=*
//BACKUP   DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.CDS(+1),
//         LABEL=(,SL)
//JRNLBKUP DD DISP=(,CATLG),UNIT=TAPE,DSN=BACKUP.JRNL(+1),
//         LABEL=(2,SL),VOL=REF=*.BACKUP
//         PEND
```

Figure 196. Example BACKUPPROC procedure

Using the LABEL Procedure

You can run the EDGINERS utility as an operator started procedure, so that the operator or librarian can make requests for tape labeling and erasing.

Figure 197 on page 342 shows a copy of the sample procedure you can use in your installation. Rename the procedure to LABEL. Specify additional processing options that suit the needs of your installation.

You must define the LABEL procedure as a RACF started procedure. The LABEL procedure requires UPDATE access to the STGADMIN.EDG.OPERATOR RACF facility class profile. See “Chapter 8. Authorizing DFSMSrmm Users and Ensuring Security” on page 153 for information about STGADMIN.EDG.OPERATOR.

See *z/OS DFSMSrmm Guide and Reference* for information on using the LABEL procedure as part of your operator’s tasks.

```
//LABEL   PROC OPT=NOVERIFY,U=3480,SOUT=DUMMY
//*
//*      RMM procedure for volume labelling and erasing
//*        See DFSMS/MVS Version 1 Release 2
//*            DFSMSrmm Guide and Reference SC26-4931
//*        for details of the LABEL utility.
//*
//*      &OPT are the options for the EDGINERS utility.
//*        See DFSMS/MVS Version 1 Release 2
//*            DFSMSrmm Implementation and Customization Guide SC26-4932
//*        for details of the EDGINERS utility.
//*
//*      &U is the device type or number requested for a tape drive
//*
//*      &SOUT Allows you to specify that the message file is
//*      printed. For example S LABEL,SOUT='SYSOUT=A'
//*
//*      If either VERIFY OR NOVERIFY is the only option specified
//*      in the &OPT parameter, requests are entered via the
//*      system console as WTOR replies.
//*
//INIT     EXEC PGM=EDGINERS,PARM='&OPT'
//SYSPRINT DD  &SOUT
//TAPE     DD  UNIT=(&U,,DEFER)
```

Figure 197. Sample Label Procedure

Processing NL Label Tapes: EDG019VM

The EDG019VM sample exit that DFSMSrmm provides can be used as a replacement for IFG019VM. The exit uses the tape volume mount exit to obtain tape label information from the operator when an NL tape is mounted as a scratch tape on a non-specific NL mount request.

Input

The invocation environment must be identical to that provided at entry to the exit IFG019VM.

Output

The parameter list provided as input is updated. R15 is set on exit with one of the possible values for the return codes:

0	Accept the volume. The parameter list might have been updated.
4	Continue normal processing. The parameter list has not been updated.
8	Reject the volume.

Processing

EDG019VM returns the rack number as the mounted volume for use by open processing.

```
RMMV01D device REPLY WITH RACK NUMBER FOR NL REQUEST – OR REPLY "REJECT"
```

Environment

See *z/OS DFSMS Installation Exits* for information about setting up the exit.

Chapter 19. Using the Problem Determination Aid Facility

Perform this step once for each MVS image. You only need to perform this step if you want an external DASD record of trace data.

The problem determination aid (PDA) facility gathers DFSMSrmm processing information to enable analysis to pinpoint module flow and resource usage related to DFSMSrmm problems. The PDA facility is required for IBM service because it traces module and resource flow. The PDA facility consists of in-storage trace, optional DASD log data sets, EDGRMMxx parmlib member options, and operator commands to control tracing.

DFSMSrmm accumulates problem determination information at specific module points in the form of trace data, and it records this data in main storage. At predetermined intervals, the trace data is scheduled for output to DASD. The DFSMSrmm trace recording function receives the trace data scheduled for output and writes this data to a file on DASD. The PDA facility consists of two separate log data sets. DFSMSrmm recognizes these log data sets by their DD names, EDGPDOX and EDGPDOY. Recording takes place in the data set defined by EDGPDOX. When that data set is filled, the two data set names are swapped, and recording continues on the newly renamed data set.

When this data set is filled, the names are again swapped, and the output switches to the other data set, thus overlaying the previously recorded data. The larger the data sets, the longer the period of time that is represented by the accumulated data.

The preferred implementation of the PDA facility is to establish a protocol that automatically copies the EDGPDOY data set to tape as a generation-data-group data set each time DFSMSrmm issues message EDG9117I. This practice provides a sequential history of trace data over time so that the data is available when needed for resolving problems.

DFSMSrmm trace data can be formatted with the DFSMShsm ARCPRPDO utility. You are authorized to use ARCPRPDO even if you are not licensed to use DFSMShsm. See *z/OS DFSMShsm Diagnosis Guide* for details about ARCPRPDO. *z/OS DFSMSrmm Diagnosis Guide* provides information about using the DFSMSrmm trace data to determine possible sources of errors. See *z/OS MVS System Messages, Vol 1* and *z/OS MVS System Messages, Vol 2* for the messages issued by the DFSMShsm ARCPRPDO utility.

Planning to Use the PDA Facility

Before you can use the PDA facility, you need to:

1. Determine how long you want to keep trace information.
2. Optionally allocate storage on DASD for the PDA log data sets, EDGPDOX and EDGPDOY.
3. Implement the PDA facility based on how long you want to keep trace data.

© Copyright IBM Corp. 1992, 2001

Determining How Long to Keep Trace Information

How many hours, days, or weeks of trace history does your site want to keep? The minimum recommended trace history is four hours; however, a longer trace history gives a greater span both forward and backward in time. Your choice of a trace history interval falls into one of the following categories:

Short-Term Trace History

One to two days is typically considered a short-term trace history interval. Short-term trace histories can be obtained without using generation data groups (GDGs).

Long-Term Trace History

Two or more days is typically considered a long-term trace history interval. Long-term trace histories are best implemented with the use of generation data sets (GDSs) appended sequentially to form a generation data group (GDG).

A long-term trace history is preferred because some DFSMSrmm processing occurs only on a periodic basis. With a longer trace history, you might be able to see more patterns to help you perform problem analysis.

Problem Determination Aid (PDA) Log Data Set Size Requirements

The amount of storage that you allocate for your PDA log data sets depends on the amount of trace data activity at your site and depends on how long you want to keep trace information. If you choose to keep trace information for two days or less, see “Appendix G. Problem Determination Aid Log Data Set Size Work Sheet for Short-Term Trace History” on page 411. If you choose to keep trace information for longer than two days, see “Appendix F. Problem Determination Aid Log Data Set Size Work Sheet for Long-Term Trace History” on page 409.

Controlling the Problem Determination Aid (PDA) Facility

The PDA facility default operating mode is trace enabled at DFSMSrmm startup.

You should continuously enable PDA tracing when DFSMSrmm is active since the processing overhead is minimal. If the EDGPDOX and EDGPDOY DD statements are defined in the DFSMSrmm startup procedure, the EDGPDOX and EDGPDOY data sets are swapped and trace output is logged in the data sets.

You can control PDA tracing by using the following MODIFY command keywords. You can also enable or disable PDA processing by using the parmlib OPTION command PDA operands described in “Defining System Options: OPTION” on page 122.

PDA=ON|OFF
Specify to turn PDA tracing on or off.

PDALOG=ON|OFF|SWAP
Specify to control the LOGGING function during PDA tracing.

This example shows how to use the MODIFY command to enable PDA tracing.

```
F DFRMM,PDA=ON
```

The PDA log data sets are automatically swapped at DFSMSrmm startup. Although there is no way to control swapping at startup, you can use the MODIFY command

PDALOG=SWAP to manually swap the data sets as required. For information on how to manually swap the PDA log data sets, see the *z/OS DFSMSrmm Diagnosis Guide* manual for details.

Allocating the Problem Determination Aid (PDA) Log Data Sets

Figure 198 shows how to allocate and catalog the problem determination log data sets.

```
/*********************************************************************/
/* SAMPLE JOB THAT ALLOCATES AND CATALOGS THE PDA LOG DATA SETS.     */
/*********************************************************************/
//ALLOPDO JOB MSGLEVEL=1
//STEP1   EXEC PGM=IEFBR14
//DD1     DD DSN=?UID..?HOSTID..RMMPDOX,DISP=(,CATLG),
//           UNIT=?TRACEUNIT.,
//           VOL=SER=?TRACEVOL.,SPACE=(CYL,(20))
//DD2     DD DSN=?UID..?HOSTID..RMMPDOY,DISP=(,CATLG),
//           UNIT=?TRACEUNIT.,
//           VOL=SER=?TRACEVOL.,SPACE=(CYL,(20))
```

Figure 198. Sample JCL Job that Allocates and Catalogs the PDA Log Data Sets

Change the User ID (?UID.), MVS system image ID (?HOSTID.), the trace unit (?TRACEUNIT.), and the volume serial number (?TRACEVOL.) parameters to names that are valid for your environment. The LRECL and RECFM fields will be set by DFSMSrmm when the data set is opened and are not required in the JCL. Do not add the RLSE parameter to the DD statement.

The EDGPDOX and EDGPDOY data sets must be allocated to the same volume. The EDGPDOX and EDGPDOY data sets must be cataloged, variable blocked physical sequential and must not be striped. The data sets are required only if you want to keep a permanent history of the trace data on DASD. We recommend an initial data set size of 20 cylinders. You can adjust the size as you gain more experience with the amount of activity that is traced in your installation. If you allocate them as SMS-managed data sets they must be associated with a storage class having the GUARANTEED SPACE attribute. They should not be associated with a storage class that will conflict with the required data set attributes.

You must define a pair of trace output data sets for each MVS image. Do not share the trace data sets with multiple DFSMSrmm systems or with other system components.

Archiving the Problem Determination Aid (PDA) Log Data Sets

DFSMSrmm writes trace data to the data set name defined by the EDGPDOX DD statement. When DFSMSrmm swaps the output data sets, trace data recorded prior to the swap is available in the data set name defined by the EDGPDOY DD statement. If you want to archive trace data, you should copy the EDGPDOY data set at the time DFSMSrmm issues message EDG9117I.

Figure 199 on page 346 defines the generation data group (GDG) name for the archived problem determination output data set. The MVS system image ID (?HOSTID.) must be valid for your environment.

```
/*********************************************************************/
/* SAMPLE JOB THAT DEFINES THE GENERATION DATA GROUP NAME FOR THE     */
/* ARCHIVED PDA LOG DATA SET.                                        */
/*********************************************************************/
/*
//DEFGDG   JOB MSGLEVEL=1
//STEP1    EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
           DEFINE   GDG(NAME('?UID..?HOSTID..RMMTRACE') -
           LIMIT(30) NOSCRATCH NOEMPTY)
/*
```

Figure 199. Sample JCL Job that Defines the GDG Name for the Archived PDA Log Data Set

Copying the Problem Determination Aid (PDA) Log Data Sets to Tape

Figure 200 shows how to copy the inactive trace data set to a scratch tape as a generation data set (GDS). The data set name for the DD statement, SYSUT1, must correspond to the name specified for the EDGPDOY data set. Change the MVS system image ID (?HOSTID.) to an ID that is valid for your environment.

```
/*********************************************************************/
/* SAMPLE JOB THAT COPIES THE INACTIVE PDA LOG DATA SET TO TAPE       */
/*********************************************************************/
/*
//PDOCOPY     JOB MSGLEVEL=1
//STEP1       EXEC PGM=IEBGENER
//SYSPRINT DD SYSOUT=A
//SYSIN    DD DUMMY
//SYSUT1   DD DSN=?UID..?HOSTID..RMMPDOY,DISP=SHR
//SYSUT2   DD DSN=?UID..?HOSTID..RMMTRACE(+1),
//            UNIT=TAPE,
//            DISP=(NEW,CATLG,DELETE),
//            DCB=(?UID..?HOSTID..RMMPDOY)
```

Figure 200. Sample JCL Job that Copies the Inactive PDA Log Data Set to Tape

Printing the Problem Determination Aid (PDA) Log Data Sets

For information about printing the problem determination aid logs, see the *z/OS DFSMShsm Diagnosis Guide* manual for information about the ARCPRPDO utility.

Chapter 20. Setting Up DFSMSrmm Disposition Processing

DFSMSrmm disposition processing is optional and provides support for:

- Providing operators with information to assist them in tasks like moving a tape to a specific location
- Generating sticky labels
- Updating the location where a volume resides.

You can request DFSMSrmm disposition processing by identifying a disposition control data set using the DFSMSrmm parmlib EDGRMMxx OPTION DISPDDNAME operand and coding the same DD name in a job step that creates or references a tape data set. Figure 202 on page 350 shows how you might code the DD name in a job step. DFSMSrmm disposition processing occurs at CLOSE and EOV for each volume. DFSMSrmm does not provide support for asynchronous processing in a separate job step.

If you use the input disposition control file and, optionally, customize via the DFSMSrmm EDGUX100 installation exit, DFSMSrmm disposition processing can be expanded to support:

- Message(s) issued to one or more route codes by defining multiple messages in the disposition control file.
- Suppression of label output you might have set up using the control file. Modify label output using the DFSMSrmm EDGUX100 installation exit.
- Assignment of loan location, storage location, or library location for a volume.

Implementing DFSMSrmm Disposition Control File Processing

To implement DFSMSrmm disposition processing, you:

1. Define disposition control information in a disposition control file as described in “Modifying the Contents of the Disposition Control File” on page 348. You can define separate disposition control files that can be used for individual users, a separate job, or a separate job step. Define the data sets with LRECL 80. The data sets can be sequential files or can be members of a partitioned data set. You can also include data in your JCL stream instead of defining a data set.
2. Add the disposition control file DD name to the batch job step of the tape jobs that process the tape files for which messages or labels or location assignment is required. The DD name is the same name as you specified in DISPDDNAME in parmlib.
3. Define the disposition control file DD name in the DFSMSrmm EDGRMMxx parmlib member using the OPTION command DISPDDNAME operand as described in “Defining System Options: OPTION” on page 122. You can also define a message ID in parmlib using the OPTION command DISPMSGID operand. DFSMSrmm builds a WTO message using the message number from the DISPMSGID parmlib option and the message text defined in the disposition control file.
4. By default, sticky labels are produced using a WTO on route code 13. Add the OUTPUT JCL statement to the DFRMM started procedure as shown in “Step 8: Updating the Procedure Library” on page 30 if you want DFSMSrmm to dynamically allocate a SYSOUT file for each label. If you do not add the OUTPUT JCL statement, sticky labels are produced using a WTO on route code 13. You use the attributes of the OUTPUT statement to define how the label output should be printed.

© Copyright IBM Corp. 1992, 2001

5. Document the procedures you use for printing label output and applying sticky labels to the correct volumes. If you are using DFSMSrmm disposition control for the first time, work with your operations staff to develop, test, and document procedures for responding to DFSMSrmm messages, printing labels, and using the DFSMSrmm EXGUX100 exit to modify output. See *z/OS DFSMSrmm Guide and Reference* for information about procedures for your operators.

Modifying the Contents of the Disposition Control File

You identify the input disposition control file by using DFSMSrmm EDGRMMxx parmlib DISPDDNAME operand. The disposition control file is a fixed format sequential file with a record length of 80 characters. All the parameters including the message text are position dependent. Figure 201 shows the layout for the disposition control file.

```
ddname_1nrlOUT=vvvv,message text
ddname_1nrlmessage text
ddname_2nrlLOC=vvvvvvvv,message text
ddname_3nrlLOC=vvvvvvv,message text
```

Figure 201. Disposition Control File Record Format

ddname
1 to 8 character ddname of an input or output file. This *ddname* must match the ddname you defined for the input or output tape file processed by the current job step. DFSMSrmm only processes the statements that match to the DD name of the file being processed by CLOSE or EOV.

You can code multiple lines for each ddname specified and can include as many different ddnames as is required to cover tape data sets requiring disposition support. As each file is processed by CLOSE or EOV, DFSMSrmm uses only those statements that match the ddname of that file. *ddname* must be coded in position 1 through 8.

n Code any non-blank character in position 9 to cause the message to be issued in a non-roll deletable message to the console.

r Code a character to define the route code to use for the WTO. Use one of the characters shown in Table 54 to use specific route codes. Use any character other than the characters in Table 54 to use the default route code 13.

Table 54. Setting the Message Route Code

If You Code	Then You Are Requesting This Route Code
Any	13 (default value). Any value other than those below results in the default value being used.
A	2
B	3
C	5
*	11
F	2,11
G	3,11
H	5,11

I Indicates if a sticky label is to be produced as part of disposition processing and must be coded in position 11. DFSMSrmm ignores any other value and no label is produced.

Table 55. Coding Sticky Label Text

If You Code	Then You Are Requesting That
L	a label is produced by disposition processing. You can code multiple L's with the same ddname and route code if more message text is required.
M	a label is produced by disposition processing but the message text is passed as user data to the DFSMSrmm EDGUX100 installation exit for further processing.

OUT=*vvvvvvv*

This is an optional keyword starting in position 12. Use OUT to change the location for a volume. When you use OUT to change a volume's location, you do not need to confirm the volume move. When OUT is specified, OUT must be followed by a comma, if you also specified message text. *vvvvvvv* is a 1 to 8 character location name, that is to be used by DFSMSrmm as a location name for the current volume.

LOC=*vvvvvvv*

This is an optional keyword. If you specify LOC, it must be followed by a comma if the optional message text is specified. *vvvvvvv* is a 1 to 8 character location name. DFSMSrmm uses the value as a location name for the current volume. When you use LOC=, you request that DFSMSrmm update the volume's' destination so that the move can be tracked and confirmed later.

LOC and OUT are mutually exclusive. If you specify multiple statements for the same DD name, DFSMSrmm uses the last location name that you specify for the volume.

You can optionally blank pad location names on the right up to the maximum length of a location name.

DFSMSrmm checks the location name you specify against the location names you defined using the DFSMSrmm LOCDEF location information defined to DFSMSrmm at startup time. If the location you specified, is not defined using LOCDEF DFSMSrmm treats the location as if it is a loan location. If the location you specified is identified as a storage location, use OUT= if you do not want to confirm the move. Use LOC= if you want the move confirmed at a later time.

You can use EDGUX100 to control how the location name is used as described in "Changing Location Information with EDGUX100" on page 207. You can override the location type determined from the LOCDEF location information to specify that a location is a loan location. You can control whether a confirm move is required for DFSMSrmm storage locations.

When you specify a location name, DFSMSrmm uses this information just as if you had entered the value on an RMM CHANGEVOLUME subcommand with either LOANLOC or LOCATION. If the location is a bin managed storage location the required location is set to this value and inventory management DSTORE processing will assign a bin number. It is possible that any location assignment can later be overidden by your vital record specification movement policies.

message_text
This is up to 69 characters of message text to be issued as a WTO. It must begin in position 12 or after the comma which separates the message text from the location name. If additional text is required, include another record in the control file specifying the same ddname and route code. Each message is issued as a separate WTO.

If the *l* value is M, the message text is limited to up to 69 characters of text and is treated as user data for label processing. No additional ddname records are supported for the M user data option.

Figure 202 shows sample JCL to

- Issue a WTO on route code 2 and route code 1
- Generate a sticky label
- Set the volume location to a location called FICH
- Confirm that the volume is moved to the location FICH. In Figure 202, when IEBGENER closes the SYSUT2 output file, DFSMSrmm scans the DISPDD file for the SYSUT2 DD statement, if the DISPDD file is defined. Figure 202 shows two entries for SYSUT2 which is the file being closed. The first entry requests that DFSMSrmm issue the message 'SEND THIS TAPE TO THE FICHE PRINTER' on route codes 2 and 11, that a sticky label is generated, and that the volume's move to location FICH is already confirmed. The second entry provides user data that is passed to the DFSMSrmm EDGUX100 installation exit. DFSMSrmm includes the user data in the sticky label it generates as described in "Creating Sticky Labels" on page 204

```
// EXEC PGM=IEBGENER
//SYSUT2 DD DISP=(,KEEP),DSN=MY.FICHE.DATA,UNIT=TAPE,LABEL=(,SL)
//SYSUT1 DD DISP=SHR,DSN=MASTER.FICHE.DATA
//SYSIN  DD DUMMY
//DISPDD DD *
SYSUT2   FLOUT=FICH,SEND THIS TAPE TO THE FICHE PRINTER
SYSUT2    MUSER DATA TO BE SENT TO EDGUX100
/*
```

Figure 202. Sample JCL to Request Disposition Processing

The message DFSMSrmm issues is EDG4054I, but you can use the DISPMSGID parmlib option to change the message number to an installation selected value.

Label Processing

You can request that DFSMSrmm produce labels using a WTO on route code 13 or using the OUTPUT JCL statement to send labels to a spool file or a printer. You control the method DFSMSrmm uses by specifying an OUTPUT JCL statement in the DFSMSrmm started procedure as described in "Step 8: Updating the Procedure Library" on page 30. The name on the OUTPUT JCL statement must exactly match that specified for the DD name of the disposition control file.

If you use the OUTPUT JCL statement method, DFSMSrmm dynamically allocates a sysout file for each label using the DISPDDNAME OUTPUT JCL statement. You use the attributes of the OUTPUT statement to define how the label output is to be printed. For example, you can route the output to another system, specify a special forms type or use any of the OUTPUT statement keywords.

If you do not provide an OUTPUT JCL statement in the DFSMSrmm started procedure, you must configure a console to accept WTO messages on route code 13 so that the labels can be printed.

Labels

The default label is 10 rows with a maximum of 80 characters per row. The default LRECL is set to 80. The maximum number of data characters supported in a label is 2000 characters. DFSMSrmm provides two default label styles for your use. You can modify these label styles using the DFSMSrmm EDGUX100 installation exit. Figure 203 shows the default label for cartridges. The default label consists of eight data rows, two of which are used for spacing. Cartridge labels are identified by media type other than *, and a density of either *, IDRC, or 3480. Figure 204 shows the default label for all other types of volumes. The default label consists of seven data rows, 3 of which are used for spacing the labels.You can use the DFSMSrmm installation exit EDGUX100 to update the default labels as described in “Modifying DFSMSrmm Label Output” on page 205.

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7.
dsname_____________________________________
userdata___________________________________________________________

 jobname_     crdate____
              expdt_____
 dens comp lrecl  blksiz recf

 volser seqn lab       devc
```

Figure 203. Default Label Format for a Tape Cartridge

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7.
dsname_____________________________________
userdata___________________________________________________________
    jobname_                  crdate____

 dens comp lrecl  blksiz recf expdt_____

               volser seqn lab      devc
```

Figure 204. Default Label Format for a Round Tape

The values for the variables shown in Figure 203 and Figure 204 are:

dsname
The data set name of the file being processed. 1 to 44 characters.

userdata
The user data specified via message text in the disposition control file. 0 to 69 characters.

jobname
The current job name. 1 to 8 characters.

crdate
The data set create date. 1 to 10 characters in the date format specified by the DATEFORM parmlib option.

expdate
The data set expiration date. 1 to 10 characters in the date format specified by the DATEFORM parmlib option.

dens
The recording density of the volume. 1 to 4 characters.

comp
Indication of compaction of data on the volume. 4 characters.

lrecl
The logical record length of the data. 1 to 5 characters.

blksiz
The block size of the data. 1 to 6 characters.

recf
The record format. 1 to 4 characters.

volser
The volume serial number. 1 to 6 characters.

seqn
The volume sequence number. 1 to 4 characters.

lab
The volume label type. 1 to 3 characters.

devc
The number of the drive on which the file is processed. 4 characters.

Use the EDGSLAB macro to map the label data area as described in “Sticky Label Data: EDGSLAB” on page 379.

Chapter 21. Running DFSMSrmm with Tivoli OPC

DFSMSrmm provides sample jobs and procedures that you can modify to set up automation software, such as Tivoli OPC, to run DFSMSrmm tasks.

The DFSMSrmm provides sample jobs and the procedures that the samples jobs require in SAMPLIB. Before you use the DFSMSrmm-supplied jobs, we recommend that you customize the jobs for your installation. You must make the job control language (JCL) available to Tivoli OPC for submission. The procedures must be in a procedure library that you use with Tivoli OPC-submitted jobs.

The naming conventions are EDGJxxxx for Tivoli OPC jobs and EDGPxxxx for Tivoli OPC procedures. Each EDGJxxxx job contains JCL SET statements for variables that are required for correct JCL generation. For example, you must set the variable RMMPREF to the data set name prefix for use on all output data sets. You can tailor the jobs so you can use the jobs for normal job submission or for recovery or restart. Each EDGPxxxx procedure can be tailored as well. You might have to customize space requirements for the files that are allocated for use as output files.

The supplied jobs support DFSMSrmm tasks that are performed daily, weekly, and monthly and fall into these categories:

1. Scheduled tasks that are run on a regularly scheduled basis.
2. Event triggered tasks that are run on as-needed basis. See “Event Triggered Tracking” on page 358 for descriptions of DFSMSrmm event triggered tasks.

Considerations When Running DFSMSrmm with Tivoli OPC

Use a Tivoli OPC special resource to:

- Allow some DFSMSrmm jobs to run in parallel.
- Prevent more than one EDGHSKP job from running at the same time.
- Avoid jobs failing because inventory management is already running.
- Prevent the EDGUTIL VERIFY job from running at the same time as other DFSMSrmm inventory management jobs.
- Allow Tivoli OPC to handle the dependencies for jobs that do not always need to run.

The special resource is named in the DFSMSrmm sample Tivoli OPC loader job EDGJLOPC. The special resource is defined when you load the DFSMSrmm application to Tivoli OPC. You can customize the name of the special resource in EDGJLOPC. Be sure to change all occurrences of the special resource name in the application definition, so that Tivoli OPC job scheduling can maintain inventory management serialization properly.

Most of the DFSMSrmm tasks in the job flow are automated. These tasks require manual intervention.

1. Confirmation of moves requires intervention at a Tivoli OPC terminal to mark volume moves completed. You must confirm volume movement before the confirm job can run.
2. During restart or recovery of the DFSMSrmm-supplied Main job, you might have to perform visual checking and some other recovery actions based on the reason for the failure. For example, when recovery completed, the Main job

© Copyright IBM Corp. 1992, 2001

restarts from the beginning. For EDGHSKP, return code 4 is an acceptable completion code. Any higher return code value triggers restart or recovery processing.

DFSMSrmm provides a sample procedure called EDGJLOPC. The sample procedure includes code that supports the inventory management schedule that is recommended in “Scheduling DFSMSrmm Utilities” on page 247.

Setting Up DFSMSrmm to Use Tivoli OPC

To setup Tivoli OPC for management of DFSMSrmm tasks:

1. Customize the batch loader statements in EDGJLOPC as described in “Customizing Tivoli OPC Batch Loader Statements” on page 358.
2. Ensure that the Tivoli OPC workstations that are required by the DFSMSrmm applications are defined to Tivoli OPC as described in “Setting Up Tivoli OPC Workstations” on page 358.
3. Make the customized jobs and procedures available to Tivoli OPC and to your running systems as described in “Descriptions of DFSMSrmm Jobs to Run with Tivoli OPC”.
4. Run EDGJHKPA to define GDG bases and create first generations if needed. DFSMSrmm provides a job called preparation, that is described in “Descriptions of DFSMSrmm Jobs to Run with Tivoli OPC”, that you can use to create the GDGs.
5. Change the DFSMSrmm PARMLIB OPTION command BACKUPPROC and SCRATCHPROC operands to use the new sample procedures for use with Tivoli OPC as described in “Defining System Options: OPTION” on page 122.
6. Run the DFSMSrmm sample EDGJLOPC job as described in “Descriptions of DFSMSrmm Jobs to Run with Tivoli OPC”.
7. Add the event trigger tracking entries to Tivoli OPC using the Tivoli OPC dialog as described in “Event Triggered Tracking” on page 358.
8. Set up Tivoli OPC restart management to handle restart activities. Tivoli OPC restart management uses the DFSMSrmm application programming interface to issue commands based on the Tivoli OPC restart/recovery options that you define. If you do not use Tivoli OPC, you can issue DFSMSrmm TSO subcommands to change information as needed.

   If not all of the data sets on a volume are created successfully, you can use the subcommand shown in Figure 205 to override normal vital record specification management processing.

```
RMM CHANGEDATASET dsname VOLUME(volser) SEQ(number) ABEND
```

Figure 205. Overriding Vital Record Specification Management Processing with the RMM CHANGEDATASET TSO Subcommand

Descriptions of DFSMSrmm Jobs to Run with Tivoli OPC

All of the sample jobs used with Tivoli OPC job management include the required Tivoli OPC control statements about recovery, restart, or modifications to make at submit time. The JCL uses procedures that are shipped with DFSMSrmm. The procedures are provided to avoid duplicate JCL and to simplify job construction.

Preparation

You must first allocate files that are required for the regular processing. EDGHSKP has special requirements for the data sets that are used for

processing. Use EDGJHKPA to define the GDGs and set up the first generation of the files as required. EDGJHKPA uses the procedures EDGPHKPA, EDGPVRSA, EDGPMSGA, EDGPACTA and EDGPRPTA, and REXX procedure EDGRHKPA. Specify parameters in EDGHKPA to customize the GDG names and limits.Customize the file size by altering the SPACE values in the lowest level procedures.

CDS Verify
Run this job when you want to verify the contents of the DFSMSrmm control data set. The EDGJVFY job runs EDGUTIL with PARM=VERIFY on the current DFSMSrmm control data set. The expected completion is return code 0. You must perform manual recovery before dependent jobs can be run when the return code is greater than 0.

CDS Backup
Run this job when you want to back up the DFSMSrmm control data set. The EDGJBKP1 and EDGBKP2 jobs run EDGHSKP with PARM=BACKUP. Backup is performed at the start and at the end of the main inventory management application processing. You can modify the jobs to use DSS or AMS for backup. You make the choice of backup to DASD or tape when running the preparation jobs.

Jobs EDGJBKP1 and EDGJBKP2 run procedure EDGPBKP to perform the backup. Expected completion is return code 4 or less. You must perform manual recovery before dependent jobs can be run when the return code is greater than 4.

Inventory Management
Run this job when you want to perform DFSMSrmm inventory management processing. These jobs run EDGHSKP with VRSEL and EXPROC. These jobs also include running storage location management on a weekly basis to trigger movement decisions for off-site storage. Job EDGJDHKP and job EDGJWHKP run procedures EDGPHSKP, EDGPMSGA, and EDGPVRSA to process and set up the files for the next run. The job copies the message file to SYSOUT for easier information analysis. The expected completion is return code 4 or less. You must perform manual recovery before dependent jobs can be run when the return code is greater than 4. As part of the recovery, run the EDGJVRSV job to run VRSEL with VERIFY and to report on the ACTIVITY file for analysis of VRSMIN and VRSCHANGE conditions. For return code 8, you might have to change vital record specifications or add additional empty bin numbers. Higher return codes or abends need to be researched by the support programmer.

Erasing and Labeling Volumes
Run this job when you want to initialize and erase volumes depending on the release actions set for the volumes. The EDGJINER job runs an automatic EDGINERS job to handle the INIT and ERASE release actions. You can run dependent jobs run regardless of successful completion.

Scratch Processing
Run this job when you want to process volumes that are returning to scratch status. The EDGJSCR job runs EDGHSKP with the EXPROC parameter. This job handles the return to scratch of volumes requiring confirmed actions; whether INIT/ERASE or movement actions. You can run dependent jobs regardless of successful completion.

Scratch Reporting
Run this job when you want to obtain information about volumes in scratch status. The EDGJSCR job produces an up-to-date extract and uses EDGRPTD

with SCRLIST and NEWSCR files to produce the latest scratch list reports. You can run dependent jobs regardless of successful completion.

Ejecting Volumes
Run this job to eject volumes from system-managed tape libraries. This is an optional job that you can use if your installation uses system-managed tape. The job also includes support for VTS export processing. You can run dependent jobs regardless of successful completion. You can customize this job to include similar processing that is required for any non-system-managed volumes that you have in your library.

Producing Reports
Run this job to produce volume movement reports. The EDGJMOVE job is dependent on the inventory management job and optionally the ejecting volume job processing. This job creates an up-to-date extract and uses EDGRPTD to produce the movement reports. You can run dependent jobs regardless of successful completion.

Move Confirmation
Run this job to perform global confirmation of volume movement. The EDGJCMOV job issues a global confirm move. You can run this job after a manual action is taken by the installation to mark the movement complete at the dependent Tivoli OPC workstation. You can run dependent jobs regardless of successful completion.

Daily jobs are always be run on processing days. Weekly and monthly jobs are included in the job flow and Tivoli OPC automatically adjusts dependencies that are based on the rules specified to it. When a job fails, Tivoli OPC automatically prevents dependent jobs from processing if any manual recovery actions have been defined. To alter the dependencies, you can modify the sample Tivoli OPC applications that are described in “Tivoli OPC Applications for DFSMSrmm”.

CDS backup and scratch processing are functions that are always run in the daily cycle. CDS backup and scratch processing can also be added dynamically to the cycle as required. When CDS backup and scratch processing are added dynamically, they run independently. They are added automatically to the schedule when the write-to-operator (WTO) from DFSMSrmm is detected and the BACKUPPROC or SCRATCHPROC is triggered. When a started procedure matches an application defined to Tivoli OPC running on a started task processor, Tivoli OPC modifies the current plan.

Tivoli OPC Applications for DFSMSrmm

The application definition implements the schedule suggested in the “Scheduling DFSMSrmm Utilities” on page 247. In addition, EDGJLOPC includes support for events triggered by alerts such as the CBR3660A, short on scratch message, and the EDG2107E, journal threshold reached message.

The applications defined in the DFSMSrmm sample Tivoli OPC setup job are:

Table 56. Tivoli OPC Applications

Application	Description
GRMMDAY	GRMMDAY is a grouping application used to set a common start time for daily jobs and applications. GRMMDAY is scheduled to run every working day of the year.
GRMMMTH	GRMMMTH is a grouping application used to set a common start time for monthly jobs and applications. GRMMMTH is scheduled to run once each month on the first Friday of the month.
GRMMWK	GRMMWK is a grouping application used to set a common start time for weekly jobs and applications. GRMMWK is scheduled to run every Monday.
RMMBKP	RMMBKP is the first daily application. RMMBKP backs up the control data set and journal data set, and clears the journal. RMMBKP is dependent on the monthly RMMMTH job EDGJVFY.
RMMEXP	RMMEXP runs expiration processing and produces scratch list reports. RMMEXP is dependent on prior daily jobs and the weekly movement processing performed by the RMMMOVES job.
RMMHKPD	RMMHKPD is the main daily inventory management run. RMMHKPD is replaced once a week with a weekly inventory management run that includes movement processing.
RMMMOVES	RMMMOVES includes jobs to: • Eject system-managed volumes that are moving • Produce and print movement reports • Confirm volume moves once volumes have been moved RMMMOVES includes a manual action to complete a task at a Tivoli OPC workstation when volumes have been moved. RMMEXP is dependent on the completion of RMMMOVES.
RMMMTH	RMMMTH performs a monthly verify of the DFSMSrmm control data set. When you run RMMMTH, all other applications are dependent on RMMMTH running successfully.
RMMPOST	RMMPOST backs up the control data set and journal data set, and clears the journal. RMMPOST runs EDGINERS to process any new release actions.
RMMWK	The main inventory management run once each week instead of the daily inventory management application. RMMWK is dependent on RMMBKP.
RMMVRSVER	RMMVRSVER is an application that is set up only for use during recovery of the main inventory management application. RMMVRSVER is dynamically added if the EDGHSKP step fails with return code 8. RMMVRSVER runs VRSEL with VERIFY and produces a report from the ACTIVITY file.

You can use the sample job EDGJLOPC to run the Tivoli OPC batch loader utility to define DFSMSrmm as an application to Tivoli OPC and to have Tivoli OPC manage the regular scheduling of DFSMSrmm functions.

You customize the EDGJLOPC sample by:

- Modifying the supplied JCL to run in your environment
- Tailoring and customizing the sample application definition and schedule to meet your specific needs.

Then run the sample to load the application definition to the active Tivoli OPC control file or to a VSAM file to be used with the Tivoli OPC subsystem.

Customizing Tivoli OPC Batch Loader Statements

The DFSMSrmm sample job EDGJLOPC contains the application definitions for the applications and jobs described in “Tivoli OPC Applications for DFSMSrmm” on page 356. You can alter or add to the definitions before running the Tivoli OPC batch loader to load the definitions to your Tivoli OPC subsystem or to another VSAM file you plan to use as an Tivoli OPC AD database.

Setting Up Tivoli OPC Workstations

You should ensure that you define these workstations to your Tivoli OPC subsystem or alter them to those you want to use with the DFSMSrmm applications.

The sample definitions use the following workstations:

STC1 A computer workstation for running started tasks

CPU1 A computer workstation for running batch jobs

PRT1 A workstation for printing movement reports

TLIB A manual workstation for use by the tape librarian or operator to mark movement of volumes completed.

Event Triggered Tracking

The applications are set up to take advantage of Tivoli OPC event trigger tracking for these conditions:

- Journal threshold is reached - backup is required to clear the journal
- Low on scratch - expiration processing is required to return pending release volumes to scratch status and produce new scratch lists.

To use the applications:

1. Define these tasks to Tivoli OPC under Event Trigger Tracking; EDGSETT triggers RMMEXP, and EDGBETT triggers RMMBKP.
2. Change the DFSMSrmmm parmlib OPTION command BACKUPPROC and SCRATCHPROC operands to name special procedures EDGBETT and EDGSETT. Specifying EDGBETT and EDGSETT enables the event trigger processing.

   The options for each entry in the ETT table are

   - Event type=J
   - Job replace=Y
   - Dependency resolution=N
   - Availability status=N

   EDGBETT and EDGSETT sample procedures are only intended for tracking by Tivoli OPC. They are not intended for use outside of Tivoli OPC job management because they only execute IEFBR14.

Appendix A. DFSMSrmm Installation Verification Procedures

DFSMSrmm Samples Provided in SAMPLIB

- EDGIVPPM Sample Parmlib for Use in the IVP
- EDGIVP1 IVP Job 1 to Initialize Tape Volumes
- EDGIVP2 IVP Job 2 to Use Tape Volumes

This section helps you prepare for and run the DFSMSrmm installation verification procedures (IVP). You can use the IVP to ensure that the DFSMSrmm functional component has been successfully installed by SMP/E and can be activated on your system. The IVP does not test all the functions in DFSMSrmm but validates that the key interfaces are in place.

Preparing to Run the IVP

Before running the IVP, you need to activate some of DFSMSrmm's functions. This section lists and describes the steps you should perform to set up DFSMSrmm for the IVP. Chapter 2. Implementing DFSMSrmm contains all the steps needed to install DFSMSrmm.

If this is first time you are setting up DFSMSrmm, follow all the steps described in this section. If you are running the IVP on a system that has previously been set up for use with DFSMSrmm, you might not need to perform all the steps listed here. Evaluate your installation setup to determine which steps you can omit.

1. Installing DFSMSrmm with SMP/E

   Ensure DFSMS/MVS including DFSMSrmm is SMP/E applied. Refer to *z/OS Program Directory* that you received with the product tape or to *ServerPac: Installing Your Order* for complete installation instructions.

   Once you have used SMP/E to install DFSMSrmm, we recommend that you IPL your system without performing any implementation tasks and have DFSMSrmm take no part in removable media management. The ability to run without DFSMSrmm is especially helpful if you are running another tape management product in production.
2. Updating SYS1.PARMLIB Members

   Refer to "Step 5: Updating SYS1.PARMLIB Members" on page 25 for detailed instructions. As a minimum, you should update IEFSSNxx and IKJTSOxx. Also ensure IFAPRDxx is updated.
3. Updating the Procedure Library

   Refer to "Step 8: Updating the Procedure Library" on page 30 for detailed instructions. Use member EDGDFRMM of SYS1.SAMPLIB as a sample DFSMSrmm procedure.
4. Assigning DFSMSrmm a RACF User ID

   Perform this step if you want to use a specific RACF user ID for DFSMSrmm during the IVP. When running on a system with RACF installed, assign DFSMSrmm a RACF user ID by adding a definition to the RACF started procedures name table, ICHRIN03 or add a profile in the STARTED class as described in "Step 9: Assigning DFSMSrmm a RACF User ID" on page 33. You can assign a RACF user ID that matches the name of the DFSMSrmm procedure that you created in step 3, but any installation-selected RACF user ID is acceptable.

© Copyright IBM Corp. 1992, 2001

If your installation has a default RACF user ID for started procedures, you can use it during the IVP to avoid the need to update ICHRIN03. As data sets are created for use by the DFSMSrmm procedure, add the RACF user ID to the access list for the data sets. Table 6 on page 33 lists the data sets that the DFSMSrmm procedure should be able to access.

If you are using an equivalent security product, review the RACF-related information to determine the changes that might be required to run DFSMSrmm with the equivalent security product.

5. Defining Parmlib Member EDGRMMxx

   Refer to “Step 10: Defining Parmlib Member EDGRMMxx” on page 34 for detailed instructions. Use member EDGIVPPM of SYS1.SAMPLIB as a sample parmlib member.

6. Specifying DFSMSrmm Options

   Refer to “Chapter 7. Using the Parmlib Member EDGRMMxx” on page 115 for information on tailoring the DFSMSrmm sample parmlib member EDGIVPPM to specify DFSMSrmm options for the IVP.

   During the IVP, DFSMSrmm runs in record-only mode. DFSMSrmm records information about tape volumes but does no validation. You can tailor EDGIVPPM to specify that DFSMSrmm run in warning mode or protect mode if you want DFSMSrmm to validate volumes.

   If you are running the IVP on a system with no other tape management system you can select any mode: record-only, warning or protect. If there is a possibility of accidental use of the wrong tape volumes we suggest that you run in protect mode. However, if you run the IVP on a system where others are using tape including the use of scratch tapes, be aware that DFSMSrmm rejects all scratch tapes not defined to it while running in protect mode. See “Defining System Options: OPTION” on page 122 for information about DFSMSrmm modes of operation.

7. Creating the DFSMSrmm Control Data Set

   Refer to “Step 12: Creating the DFSMSrmm Control Data Set” on page 35 for detailed instructions. You can use the sample JCL in member EDGJMFAL in SYS1.SAMPLIB to allocate a control data set. Ensure that the control data set name is the same as that specified in the parmlib member EDGRMMxx that you created earlier. Initialize the control data set by running the EDGUTIL utility. You can use the sample JCL in member EDGJUTIL in SYS1.SAMPLIB. Set the rack and bin count fields to 0.

8. Creating the Journal

   Refer to “Step 13: Creating the Journal” on page 39 for detailed instructions. You can use sample JCL in member EDGJNLAL in SYS1.SAMPLIB to allocate a journal data set.

9. Making the DFSMSrmm ISPF Dialog Available to Users

   Refer to “Step 15: Making the DFSMSrmm ISPF Dialog Available to Users” on page 42 for instructions to make the DFSMSrmm dialog available to users.

10. Making TSO HELP Information Available to Users

    Refer to “Step 16: Making TSO HELP Information Available to Users” on page 44 to make TSO HELP information available for use during the IVP.

11. Restarting MVS with DFSMSrmm Implemented

    You are ready to start the system with DFSMSrmm implemented. Refer to “Step 17: Restarting MVS with DFSMSrmm Implemented” on page 44 for information on conditions that determine if you need to IPL the system to restart MVS with DFSMSrmm implemented. Perform this step so that the

changes you made to IEFSSNxx and other parmlib members when you performed step 2 on page 359 take effect.

12. Starting DFSMSrmm

    Refer to “Step 19: Starting DFSMSrmm” on page 45 for detailed instructions. When you start DFSMSrmm, if it issues message EDG0103D, reply ’RETRY’. If you reply other than ’RETRY’, DFSMSrmm will not record any tape usage activity.

DFSMSrmm is activated and you are ready to run the IVP.

Running the IVP

To run the IVP, perform the following steps:

1. You need three tape volumes that do not have any data on them, and a single tape unit online to your system. Ask your tape librarian to externally label these volumes EDG000, EDG001, and EDG002 for your testing.

   Ensure that the tape volumes you use are suitable for use with DFSMSrmm during the IVP. For example, if you have an existing tape management system, check that the volumes are either not managed by it or are designated for use with DFSMSrmm for testing.

2. Ensure that TSO help information has been correctly installed by entering the following command from a TSO terminal:

   ```
   HELP RMM
   ```

   DFSMSrmm lists help information for the RMM TSO subcommand, including a list of subcommands, function, syntax, and operands.

3. Add some shelf locations to DFSMSrmm by entering the following RMM TSO command from a TSO terminal:

   ```
   RMM ADDRACK RMM000 COUNT(10)
   ```

4. Add some volumes to DFSMSrmm using the DFSMSrmm ISPF dialog. Enter the following command from a TSO terminal:

   ```
   %RMMISPF
   ```

   DFSMSrmm displays the DFSMSrmm ISPF dialog primary option menu as shown in Figure 206 on page 362.

```
  Panel  Help
------------------------------------------------------------------------------
EDG@PRIM              REMOVABLE MEDIA MANAGER (DFSMSrmm)
Option ===>  VOLUME

0  OPTIONS       - Specify dialog options and defaults
1  USER          - General user facilities
2  LIBRARIAN     - Librarian functions
3  ADMINISTRATOR - Administrator functions
4  SUPPORT       - System support facilities
5  COMMANDS      - Full DFSMSrmm structured dialog
6  LOCAL         - Installation defined dialog
X  EXIT          - Exit DFSMSrmm Dialog

Enter selected option or END command.  For more info., enter HELP or PF1.




5647-A01 (C) COPYRIGHT 1993,2000 IBM CORPORATION
```

Figure 206. DFSMSrmm Primary Option Menu

Enter VOLUME on the option line to display the DFSMSrmm Volume Menu as shown in Figure 206. DFSMSrmm displays a panel as shown in Figure 207.

```
  Panel  Help
------------------------------------------------------------------------------
EDGPT000                     DFSMSrmm Volume Menu
Option ===>

0  OPTIONS   - Specify dialog options and defaults
1  DISPLAY   - Display volume information
2  ADD       - Add a new volume
3  CHANGE    - Change volume information
4  RELEASE   - Delete or release a volume
5  SEARCH    - Search for volumes
6  REQUEST   - Request a volume
7  ADDSCR    - Add one or more SCRATCH volumes
8  CONFIRM   - Confirm librarian or operator actions
9  STACKED   - Add one or more stacked volumes


Enter selected option or END command.  For more info., enter HELP or PF1.



5647-A01 (C) COPYRIGHT 1993,2000 IBM CORPORATION
```

Figure 207. DFSMSrmm Volume Menu

Select option 7, ADDSCR, and press ENTER. DFSMSrmm displays the DFSMSrmm Add Scratch Volumes panel as shown in Figure 208 on page 363. Complete the details as shown in the panel and press ENTER:

```
  Panel  Help
------------------------------------------------------------------------------
EDGPT230                DFSMSrmm Add Scratch Volumes
Command ===>

Volume . . . . . .EDG000            Pool  . . . . . .
                                    or
Media name . . . . .                Rack  . . . . . .RMM000
                                    Location name . . .

Count  . . . . . .3         ( Default is 1 )

Description  . . . .
Assigned date  . . .             YYYY/DDD         MVS use . . . . . .
Assigned time  . . .                              VM use  . . . . . .

Media type . . . . .
Label  . . . . . .SL        ( AL, NL or SL )
  Current version           Label version number( for example 3 )
  Required version          Label version number( for example 4 )
Density  . . . . . .        ( 1600, 3480, 6250 or * )
Initialize . . . . .YES        ( Default is YES )

Press ENTER to ADD one or more SCRATCH volumes, or END command to CANCEL.
```

Figure 208. DFSMSrmm Add Scratch Volumes Panel

DFSMSrmm displays the message `3 volumes added` in the top right hand corner of the screen.

Exit the DFSMSrmm ISPF dialog by entering **=X** on the command line.

5. Initialize tape volumes by editing and submitting the JCL in member EDGIVP1 in SYS1.SAMPLIB. Mount the three tape volumes requested by this job in the sequence EDG002, EDG001, and EDG000.

   Ensure that the job completes with a return code of zero and the expected messages in EDGIVP1 are in the job output.

6. Write data to tape volumes by editing and submitting the JCL in member EDGIVP2 in SYS1.SAMPLIB. Mount the three tape volumes requested by this job in the sequence EDG000, EDG001, and EDG002. Use the three volumes initialized in step 5 on page 363.

   Ensure that all steps of the job complete with a return code of zero. Message IEC502E is issued when the job finishes with the second volume, EDG001. Check that the message in the SYSLOG contains the text RACK=RMM001 on the right hand side as follows:

   ```
   IEC502E RK ddd,EDG001,SL,jjjjjjjj,WRITE22 - RACK=RMM001
   ```

7. To display data set information recorded by DFSMSrmm, enter the following RMM TSO subcommands:

   ```
   RMM LISTDATASET 'RMMIVP.TEST1' VOLUME(EDG000) SEQ(1)
   RMM LISTDATASET 'RMMIVP.TEST2' VOLUME(EDG000) SEQ(2)
   RMM LISTDATASET 'RMMIVP.TEST3' VOLUME(EDG001) SEQ(1)
   RMM LISTDATASET 'RMMIVP.TEST4' VOLUME(EDG001) SEQ(2)
   RMM LISTDATASET 'RMMIVP.TEST4' VOLUME(EDG002) SEQ(1)
   ```

   DFSMSrmm displays data set information as shown in Figure 209 on page 364:

```
Data set name = RMMIVP.TEST1
Job name      = EDGIVP2
Volume        = EDG000                Physical file sequence number = 1
Device number = 0E76       Owner       = RMMIVP   Data set sequence = 1
Create date   = 1997/02/02 Create time = 07:41:29 System ID         = E4E4
Block size    = 80         Block count = 10
Logical Record Length = 80         Record Format  = FB
Date last written     = 1994/02/02 Date last read = 1994/02/02
Step name             = WRITE11    DD name        = SEQOUT
Management class      = MGMT01     VRS management value  =
Storage group         = SGT0S1     VRS retention date    = 1994/07/02
Storage class         = SCFAST     Matching VRS type     =
Data class            = DCCLS1     Matching VRS job name =
Matching VRS name =
Security Class    = U         Description   = UNCLASSIFIED
```

Figure 209. Sample Data Set Information

To cleanup after running the IVP or to prepare to rerun the IVP, issue these commands to remove information from the DFSMSrmm control data set.

```
RMM DELETEVOLUME EDG000 FORCE
RMM DELETEVOLUME EDG001 FORCE
RMM DELETEVOLUME EDG002 FORCE
RMM DELETERACK RMM000 COUNT(10)
```

When you have completed running the IVP, you can return the three volumes to your tape library.

Appendix B. DFSMSrmm Mapping Macros

Note

The following mapping macros have been moved to the *z/OS DFSMSrmm Reporting* book.

- Report Extract Data Set Mapping Macros in SYS1.MACLIB.

  You use the extract data set as input to the DFSMSrmm utility EDGRPTD to create reports.

  The extract data set contains information extracted from the DFSMSrmm control data set. The extract data set records contain all major key fields so that you can select fields and sort them for reports. Variable length fields are expanded to maximum length and redundant control information is removed to allow for simple reporting.
- SMF Records Mapping Macros in SYS1.MODGEN.

  DFSMSrmm requires two record types to support audit and security needs. You specify the exact SMF record types in EDGRMMxx, using SMFAUD for auditing and SMFSEC for security records.

The macros identified in this appendix are provided as programming interfaces for customers by DFSMSrmm.

Attention:

Do not use as programming interfaces any DFSMSrmm macros other than those identified in this book.

- Library Control System Interface Macro in SYS1.MODGEN.
  "OAM Interface: EDGLCSUP"
- DFSMSrmm Installation Exit Mapping Macros in SYS1.MODGEN.
  "Installation Exit Mapping Macro: EDGPL100" on page 372
  "Installation Exit Mapping Macro: EDGPL200" on page 377
- DFSMSrmm Sticky Label Mapping Macro in SYS1.MACLIB.
  - "Sticky Label Data: EDGSLAB" on page 379

General-use Programming Interface Mapping Macros

"General-use Programming Interface Mapping Macros" contains General-use Programming Interface and Associated Guidance Information.

OAM Interface: EDGLCSUP

EDGLCSUP maps the Library Control System interface parameter list. See "Managing System-Managed Tape Library Volumes: EDGLCSUX" on page 179 for more information about using the OAM interface.

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name (Dim)**	**Description**
0	(0)	STRUCTURE		LCSUP	, LOCV PARAMETER LIST
0	(0)	DBL WORD	8	LCSUP_HDR(0)	CONTROL BLOCK HEADER
THE FOLLOWING FIELDS ARE VALIDATED BY EDGLCSUX BEFORE PROCESSING					
0	(0)	CHARACTER	8	LCSUP_IDENT	CONTROL BLOCK ID

© Copyright IBM Corp. 1992, 2001

EDGLCSUP

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
8	(8)	ADDRESS	1	LCSUP_VERNO	CONTROL BLOCK VERSION NUMBER
9	(9)	ADDRESS	1	LCSUP_REVNO	CONTROL BLOCK REVISION NUMBER
10	(A)	ADDRESS	2	LCSUP_SUBPOOL	CONTROL BLOCK SUBPOOL NUMBER
12	(C)	ADDRESS	4	LCSUP_LENGTH	CONTROL BLOCK LENGTH
INPUT FIELDS START HERE					
16	(10)	BITSTRING	1	LCSUP_FUNCTION	REQUESTED FUNCTION
		1...		LCSUP_ENT	″X'80'″ CALLER IS CBRUXENT
		.1..		LCSUP_EJC	″X'40'″ CALLER IS CBRUXEJC
		..1.		LCSUP_CUA	″X'20'″ CALLER IS CBRUXCUA
		...1		LCSUP_VNL	″X'10'″ CALLER IS CBRUXVNL
		.... 1...		LCSUP_ACTVNL	″X'08'″ REENTRY FROM CBRUXVNL FOR ACTION
17	(11)	BITSTRING	1		RESERVED
18	(12)	BITSTRING	1	LCSUP_STATUSD	Corresponds to MVSFLGD byte
		1...		LCSUP_MVOREAD	″X'80'″ Owner may read volume
		.1..		LCSUP_MVOUPD	″X'40'″ Owner may update volume
		..1.		LCSUP_MVOALT	″X'20'″ Owner may alter volume
		...1		LCSUP_MVPROTR	″X'10'″ Read-Only protection
		.... 1...		LCSUP_MVPROTU	″X'08'″ Update protection
		.... .1..		LCSUP_MVMVSUSE	″X'04'″ May be used on MVS systems
		.... ..1.		LCSUP_MVVMUSE	″X'02'″ May be used on VM systems
19	(13)	BITSTRING	1	LCSUP_STATUSE	Corresponds to MVSFLGE byte
		1...		LCSUP_MVRETSCR	″X'80'″ Return to scratch pending
		.1..		LCSUP_MVREPREL	″X'40'″ Replace tape on release pending
		..1.		LCSUP_MVREINIT	″X'20'″ Init pending
		...1		LCSUP_MVDEGAUS	″X'10'″ Degaus/security erase pending
		.... 1...		LCSUP_MVROWNER	″X'08'″ Return to owner pending
		.... .1..		LCSUP_MVNOWNER	″X'04'″ Notify owner pending
20	(14)	SIGNED	4	LCSUP_LCSPL	POINTER TO LCS PARAMETER LIST
OUTPUT FIELDS START HERE					
24	(18)	SIGNED	4	LCSUP_LCSRC	RETURN CODE FOR LCS
28	(1C)	SIGNED	4	LCSUP_LCSRS	REASON CODE FOR LCS
OUTPUT FIELDS FOR CBRUXVNL					
32	(20)	CHARACTER	8	LCSUP_LOANLOC	LOAN LOCATION
40	(28)	CHARACTER	8	LCSUP_LOCATION	CURRENT VOLUME LOCATION
48	(30)	BITSTRING	1	LCSUP_LOCTYPE	CURRENT LOCATION TYPE

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
		....		LCSUP_TYPE_SHELF	″X'00'″ X'00' - SHELF LOCATION
		1		LCSUP_TYPE_STORE	″X'01'″ X'01' - STORAGE LOCATION
		.... ..1.		LCSUP_TYPE_MTL	″X'02'″ X'02' - MANUAL LIBRARY
		11		LCSUP_TYPE_ATL	″X'03'″ X'03' - AUTOMATIC LIBRARY
49	(31)	CHARACTER	8	LCSUP_DEST	CURRENT VOLUME DESTINATION
57	(39)	BITSTRING	1	LCSUP_DESTYPE	CURRENT DESTINATION TYPE Values as for LCSUP_LOCTYPE
58	(3A)	CHARACTER	8	LCSUP_HOME	VOLUME HOME LOCATION
66	(42)	BITSTRING	1	LCSUP_HOMETYPE	VOLUME HOME LOCATION TYPE Values as for LCSUP_LOCTYPE
67	(43)	CHARACTER	6	LCSUP_RACK	RACK NUMBER
73	(49)	CHARACTER	6	LCSUP_BIN	BIN NUMBER
79	(4F)	BITSTRING	1	LCSUP_STATUS	VOLUME STATUS (MVFLGA)
		1...		LCSUP_MSTFLG	″X'80'″ ** VOLUME IS MASTER
		.1..		LCSUP_RLSFLG	″X'40'″ ** VOLUME PENDING RELEASE
		..1.		LCSUP_VRFLG	″X'20'″ ** VITAL RECORD - DO NOT RELEASE
		...1		LCSUP_ASSFLG	″X'10'″ ** USER TAPE (ASSIGNED BY LIB)
		.... 1...		LCSUP_LONFLG	″X'08'″ ** TAPE IS ON LOAN
		.... .1..		LCSUP_OPNFLG	″X'04'″ ** TAPE OPENED AND NOT YET CLOSED002
		.... ..1.		LCSUP_SCRFLG	″X'02'″ ** VOLUME IS SCRATCH
		1		LCSUP_OCEFLG	″X'01'″ ** VOLUME RECORDED BY O/C/EOV
80	(50)	BITSTRING	1	LCSUP_STATUSX	VOLUME STATUS (MVFLGAX)
		1...		LCSUP_GVCFLG	″X'80'″ ** SCRATCH VOL CLAIMED VIA GETVOL002
		.1..		LCSUP_XINFLG	″X'40'″ ** SCRATCH VOLUME HAS NEVER ** BEEN INITIALISED
		..1.		LCSUP_INIFLG	″X'20'″ ** SCRATCH VOLUME WITH INIT ** ACTION PENDING
		...1		LCSUP_ENTFLG	″X'10'″ ** SCRATCH VOLUME WAITING TO ** ENTER ATL
		.... 1...		LCSUP_FABEND	″X'08'″ ** ABEND IN PROCESS WHEN A DATA ** SET CLOSED
		.... .1..		LCSUP_FOCEAB	″X'04'″ ** ABEND PROBABLY IN O/C/EOV **
		.... ..1.		LCSUP_ATIFLG	″X'02'″ ** INIT REQUESTED FOR ATL VOL
81	(51)	BITSTRING	1	LCSUP_FLAGS	FLAG BYTE
		1...		LCSUP_TRANSIT	″X'80'″ VOLUME MOVING STATUS
84	(54)	SIGNED	4	LCSUP_TDSI	TAPE DEVICE SELECTION INFO.
88	(58)	CHARACTER	16	LCSUP_INCONTAINER	In container
104	(68)	SIGNED	1	LCSUP_VOLUMETYPE	

EDGLCSUP

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
					Volume type
105	(69)	CHARACTER	55		Reserved
END OUTPUT FIELDS FOR CBRUXVNL					
160	(A0)	DBL WORD	8	LCSUP_END(0)	END OF LCSUP
		.1.1 1...		LCSUP_LEN#	″LCSUP_END-LCSUP_HDR″ LENGTH OF LCSUP
CONSTANTS USED TO INITIALIZE THE LCSUP HEADER SECTION					
		.... ..1.		LCSUP_VER#	″2″ VERSION NUMBER
		....		LCSUP_REV#	″0″ REVISION NUMBER
		....		LCSUP_SP#	″0″ SUBPOOL NUMBER
CONSTANTS FOR LCSUP_VOLUMETYPE					
		....		LCSUP_VOLUMETYPE_PHYSICAL	″0″ PHYSICAL VOLUME
		1		LCSUP_VOLUMETYPE_LOGICAL	″1″ LOGICAL VOLUME
CONSTANTS FOR RETURN CODES IN R15					
		....		LCSUP_RC_OK	″0″ SUCCESSFUL. A REASON CODE IS SET.
		.... .1..		LCSUP_RC_SSNA	″4″ DFSMSRMM SUBSYSTEM NOT AVAILABLE.
		.... 1...		LCSUP_RC_LERR	″8″ LOGICAL ERROR.
		.... 11..		LCSUP_RC_ENV	″12″ ENVIRONMENT ERROR. A REASON CODE IS SET.
CONSTANTS FOR REASON CODES IN R0 WHEN R15 = LCSUP_RC_OK					
		....		LCSUP_RS_OK	″0″ REQUEST SUCCESSFULLY PROCESSED
		1		LCSUP_RS_NOACTION	″1″ NO ACTION PERFORMED BY DFSMSRMM
		.... ..1.		LCSUP_RS_DONT	″2″ DONT NEED RMM EXITS TO BE CALLED
CONSTANTS FOR REASON CODES IN R0 WHEN R15 = LCSUP_RC_ENV					
		1		LCSUP_RS_IDENT	″1″ INCORRECT VALUE IN LCSUP_IDENT
		.... ..1.		LCSUP_RS_VERNO	″2″ INCORRECT VALUE IN LCSUP_VERNO
		11		LCSUP_RS_REVNO	″3″ INCORRECT VALUE IN LCSUP_REVNO
		.... .1..		LCSUP_RS_SUBPOOL	″4″ INCORRECT VALUE IN LCSUP_SUBPOOL
		.... .1.1		LCSUP_RS_LENGTH	″5″ INCORRECT VALUE IN LCSUP_LENGTH
		.... .11.		LCSUP_RS_FUNCTION	″6″ INCORRECT VALUE IN LCSUP_FUNCTION
		.... .111		LCSUP_RS_NSUPV	″7″ EDGLCSUX NOT SUPERVISOR STATE

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
		.... 1...		LCSUP_RS_LCSUP	″8″ EDGLCSUX PARAMETER LIST COULD NOT BE ADDRESSED
		.... 1..1		LCSUP_RS_CBRPL	″9″ CBRUXXPL PARAMETER LIST COULD NOT BE ADDRESSED
		.... 1.1.		LCSUP_RS_ABEND	″10″ EDGLCSUX ABENDED
		CONSTANTS FOR REASON CODES RETURNED IN LCSUP_LCSRS			
		1		LCSUP_RS_PBD	″1″ INCONSISTENT PARAMETER LIST
		.... ..1.		LCSUP_RS_NMV	″2″ VOLUME NOT TO BE USED WITH MVS
		11		LCSUP_RS_DEB	″3″ SPECIFIED DESTINATION NOT CURRENT LIB
		.... .1..		LCSUP_RS_RJP	″4″ UNDEF. VOL. REJECTED BY REJECT PREFIX
		.... .1.1		LCSUP_RS_SCR	″5″ PRIVATE TO SCRATCH CHANGE INVALID
		.... .11.		LCSUP_RS_IVU	″6″ USER ID NOT VALID FOR RMM
		.... .111		LCSUP_RS_RPX	″7″ RET. PERIOD EXCEEDS INSTALLATION MAX.
		.... 1...		LCSUP_RS_NRM	″8″ VOLUME NOT RMM MANAGED
		.... 1..1		LCSUP_RS_RIU	″9″ RACK TO MATCH VOLSER NOT AVAILABLE
		.... 1.1.		LCSUP_RS_NSL	″10″ LABEL TYPE IS NOT SUPPORTED IN A LIB.
		.... 1.11		LCSUP_RS_IRK	″11″ VOLUME RACK INCONSISTENT
		.... 11..		LCSUP_RS_REL	″12″ VOLUME PENDING RELEASE
		.... 11.1		LCSUP_RS_STA	″13″ VOLUME STATUS IS SCRATCH
		.... 111.		LCSUP_RS_INI	″14″ VOLUME INIT ACTION PENDING
		 1111		LCSUP_RS_DUPLV	″15″ PHYSICAL VOLUME DUPLICATES EXISTING LOGICAL VOLUME
		...1		LCSUP_RS_NOTEXP	″16″ LOGICAL VOLUME IS NOT EXPORTED
		...1		LCSUP_RS_DUPPV	″17″ LOGICAL VOLUME DUPLICATES EXISTING PHYSICAL VOLUME

EDGLCSUP Cross Reference

Name	Offset	Hex Tag	Level
LCSUP_ACTVNL	10	8	2
LCSUP_ASSFLG	4F	10	2
LCSUP_ATIFLG	50	2	2
LCSUP_BIN	49	40404040	2
LCSUP_CUA	10	20	2

EDGLCSUP

Name	Offset	Hex Tag	Level
LCSUP_DEST	31	40404040	2
LCSUP_DESTYPE	39	0	2
LCSUP_EJC	10	40	2
LCSUP_END	58		2
LCSUP_ENT	10	80	2
LCSUP_ENTFLG	50	10	2
LCSUP_FABEND	50	8	2
LCSUP_FLAGS	51	0	2
LCSUP_FOCEAB	50	4	2
LCSUP_FUNCTION	10	0	2
LCSUP_GVCFLG	50	80	2
LCSUP_HDR	0		2
LCSUP_HOME	3A	40404040	2
LCSUP_HOMETYPE	42	0	2
LCSUP_IDENT	0	C5C4C7D3	2
LCSUP_INCONTAINER	58	0	2
LCSUP_INIFLG	50	20	2
LCSUP_LCSPL	14	0	2
LCSUP_LCSRC	18	0	2
LCSUP_LCSRS	1C	0	2
LCSUP_LEN#	58	58	2
LCSUP_LENGTH	C		2
LCSUP_LOANLOC	20	40404040	2
LCSUP_LOCATION	28	40404040	2
LCSUP_LOCTYPE	30	0	2
LCSUP_LONFLG	4F	8	2
LCSUP_MSTFLG	4F	80	2
LCSUP_MVDEGAUS	13	10	2
LCSUP_MVMVSUSE	12	4	2
LCSUP_MVNOWNER	13	4	2
LCSUP_MVOALT	12	20	2
LCSUP_MVOREAD	12	80	2
LCSUP_MVOUPD	12	40	2
LCSUP_MVPROTR	12	10	2
LCSUP_MVPROTU	12	8	2
LCSUP_MVREINIT	13	20	2
LCSUP_MVREPREL	13	40	2
LCSUP_MVRETSCR	13	80	2
LCSUP_MVROWNER	13	8	2
LCSUP_MVVMUSE	12	2	2
LCSUP_OCEFLG	4F	1	2
LCSUP_OPNFLG	4F	4	2
LCSUP_RACK	43	40404040	2
LCSUP_RC_ENV	58	C	2
LCSUP_RC_LERR	58	8	2
LCSUP_RC_OK	58	0	2
LCSUP_RC_SSNA	58	4	2
LCSUP_REV#	58	0	2
LCSUP_REVNO	9		2
LCSUP_RLSFLG	4F	40	2
LCSUP_RS_ABEND	58	A	2
LCSUP_RS_CBRPL	58	9	2
LCSUP_RS_DEB	58	3	2
LCSUP_RS_DONT	58	2	2

Name	Offset	Hex Tag	Level
LCSUP_RS_FUNCTION	58	6	2
LCSUP_RS_IDENT	0	C5C4C7D3	2
LCSUP_INCONTAINER	58		2
LCSUP_RS_INI	58	E	2
LCSUP_RS_IRK	58	B	2
LCSUP_RS_IVU	58	6	2
LCSUP_RS_LCSUP	58	8	2
LCSUP_RS_LENGTH	58	5	2
LCSUP_RS_NMV	58	2	2
LCSUP_RS_NOACTION	58	1	2
LCSUP_RS_NRM	58	8	2
LCSUP_RS_NSL	58	A	2
LCSUP_RS_NSUPV	58	7	2
LCSUP_RS_OK	58	0	2
LCSUP_RS_PBD	58	1	2
LCSUP_RS_REL	58	C	2
LCSUP_RS_REVNO	58	3	2
LCSUP_RS_RIU	58	9	2
LCSUP_RS_RJP	58	4	2
LCSUP_RS_RPX	58	7	2
LCSUP_RS_SCR	58	5	2
LCSUP_RS_STA	58	D	2
LCSUP_RS_SUBPOOL	58	4	2
LCSUP_RS_VERNO	58	2	2
LCSUP_SCRFLG	4F	2	2
LCSUP_SP#	58	0	2
LCSUP_STATUS	4F	0	2
LCSUP_STATUSD	12	0	2
LCSUP_STATUSE	13	0	2
LCSUP_STATUSX	50	0	2
LCSUP_SUBPOOL	A		2
LCSUP_TDSI	54	0	2
LCSUP_TRANSIT	51	80	2
LCSUP_TYPE_ATL	30	3	2
LCSUP_TYPE_MTL	30	2	2
LCSUP_TYPE_SHELF	30	0	2
LCSUP_TYPE_STORE	30	1	2
LCSUP_VER#	58	1	2
LCSUP_VERNO	8		2
LCSUP_VNL	10	10	2
LCSUP_VOLUMETYPE		2	
LCSUP_VRFLG	4F	20	2
LCSUP_XINFLG	50	40	2

Product-sensitive Programming Interface Mapping Macros

This section contains product-sensitive programming interface and associated guidance information. The macros in this section map the parameter lists for the DFSMSrmm EDGPL100 installation exit and the EDGPL200 installation exit, and the mapping for the EDGSLAB sticky label data area.

Installation Exit Mapping Macro: EDGPL100

EDGPL100 maps the DFSMSrmm installation exit, EDGUX100, parameter list. See “Using the DFSMSrmm EDGUX100 Installation Exit” on page 195 for information about using the EDGPL100 installation exit.

Offsets Decimal	Hex	Type	Length	Name (Dim)	Description
0	(0)	STRUCTURE		PL100	, EGDUX100 PARAMETER LIST
0	(0)	DBL WORD	8	PL100_HDR(0)	CONTROL BLOCK HEADER
THE FOLLOWING FIELDS CAN BE VALIDATED BY EDGUX100 BEFORE PROCESSING					
0	(0)	CHARACTER	8	PL100_IDENT	CONTROL BLOCK ID
8	(8)	ADDRESS	1	PL100_VERNO	CONTROL BLOCK VERSION NUMBER
9	(9)	ADDRESS	1	PL100_REVNO	CONTROL BLOCK REVISION NUMBER
10	(A)	ADDRESS	2	PL100_SUBPOOL	CONTROL BLOCK SUBPOOL NUMBER
12	(C)	ADDRESS	4	PL100_LENGTH	CONTROL BLOCK LENGTH
INPUT FIELDS START HERE					
16	(10)	BITSTRING	1	PL100_VALID	VALID FUNCTIONS
		1...		PL100_CAN_IGNORE	″X’80’″ CAN REQUEST VOLUME IS IGNORED
		.1..		PL100_CAN_VRS	″X’40’″ CAN REQUEST VRS VALUE SET
		..1.		PL100_CAN_RACKNO	″X’20’″ CAN RETURN RACKNO
		...1		PL100_CAN_IGNORE_FILE2_TON	″X’10’″ CAN REQUEST DS RECORD IGNORE
		.... .1..		PL100_CAN_POOL	″X’04’″ CAN RETURN POOL NAME
		.... ..1.		PL100_ITS_CLOSE	″X’02’″ Exit called at CLOSE/EOV
17	(11)	BITSTRING	1	PL100_INFO	INFORMATION BYTE
		1...		PL100_INFO_IGNORE	″X’80’″ VOLUME IGNORED BY RMM
		.1..		PL100_INFO_NOTRMM	″X’40’″ VOLUME NOT RMM MANAGED
		..1.		PL100_INFO_DISPDD	″X’20’″ DISPDD ENTRY PROCESSED
		...1		PL100_INFO_CMOVE	″X’10’″ CMOVE REQUIRED LATER
		.... 1...		PL100_INFO_USERDATA	″X’08’″ USERDATA PROVIDED
		.... .1..		PL100_INFO_MTL	″X’04’″ ALLOCATED TAPE DRIVE MTL
18	(12)	BITSTRING	2		RESERVED
20	(14)	CHARACTER	6	PL100_REQ_VOLSER	REQUESTED VOLUME SERIAL NUMBER
26	(1A)	CHARACTER	6	PL100_MOUNT_VOLSER	

Offsets Decimal	Hex	Type	Length	Name (Dim)	Description
					MOUNTED VOLUME SERIAL NUMBER
32	(20)	SIGNED	4	PL100_WTOPTR	ADDRESS OF WTO MESSAGE
OUTPUT FIELDS START HERE					
36	(24)	BITSTRING	1	PL100_FUNCTION	
					REQUESTED FUNCTION
		1...		PL100_SET_IGNORE	
					″X'80'″ CAN REQUEST VOLUME IS IGNORED
		...1		PL100_SET_IGNORE_FILE2_TON	
					″X'10'″ DS IGNORE HAS BEEN SET
		.... 1...		PL100_SET_NOLABEL	
					″X'08'″ SUPRESS STICKY LABEL
		.... .1..		PL100_SET_POOL	
					″X'04'″ POOL NAME HAS BEEN SET
		1		PL100_SET_ACLOFF	
					″X'01'″ DO NOT PERFORM AN ACL LOAD
37	(25)	BITSTRING	1	PL100_FUNCTION2	
					REQUESTED FUNCTION
		1...		PL100_SET_CMOVE	
					″X'80'″ CMOVE REQUIRED LATER
		.1..		PL100_SET_NOCMOVE	
					″X'40'″ UPDATE VOLUME LOCATION
		..1.		PL100_SET_IGNORE_SGNAME	
					″X'20'″ use pooling system
38	(26)	BITSTRING	2		RESERVED
40	(28)	SIGNED	4	PL100_JFCBPTR	ADDRESS OF JFCB COPY
44	(2C)	CHARACTER	8	PL100_VRS	NEW VRS MANAGEMENT VALUE
52	(34)	CHARACTER	6	PL100_RACKNO	EXTERNAL VOLSER
		..11 .1..		PL100_POOL	″PL100_RACKNO″ SCRATCH POOL NAME
60	(3C)	SIGNED	4	PL100_LABINFO	ADDRESS OF LABEL INFO BLOCK
START OF VERSION 2 FIELDS					
64	(40)	CHARACTER	69	PL100_LAB_USERDATA	
					USER DATA FOR LABEL PROCESSING
136	(88)	SIGNED	4	PL100_LABPTR	ADDRESS OF PREPARED LABEL
140	(8C)	CHARACTER	8	PL100_LOCATION	
					TARGET LOCATION NAME
148	(94)	BITSTRING	1	PL100_LOCTYPE	TARGET LOCATION TYPE
		....		PL100_LOC_LOAN	
					″X'00'″ LOAN LOCATION TYPE
		1		PL100_LOC_STORE	
					″X'01'″ STORAGE LOCATION TYPE
		.... ..1.		PL100_LOC_LIBRARY	
					″X'02'″ SYSTEM MANAGED LIBRARY TYPE
149	(95)	CHARACTER	3		RESERVED

EDGPL100

Offsets Decimal	Hex	Type	Length	Name (Dim)	Description
152	(98)	CHARACTER	8	PL100_DDNAME	DD NAME
160	(A0)	CHARACTER	8	PL100_DISPDD	DISPDDNAME
168	(A8)	CHARACTER	24		RESERVED
192	(C0)	DBL WORD	8	PL100_END(0)	END OF PL100
		11..		PL100_LEN#	″PL100_END-PL100_HDR″ LENGTH OF PL100
		CONSTANTS USED TO INITIALIZE THE PL100 HEADER SECTION			
		.... ..1.		PL100_VER#	″2″ VERSION NUMBER
		....		PL100_REV#	″0″ REVISION NUMBER
		....		PL100_SP#	″0″ SUBPOOL NUMBER
0	(0)	STRUCTURE		PL100_LABDS	DSECT OF LABEL INFO BLOCK
0	(0)	CHARACTER	44	PL100_DSN	DATA SET NAME
44	(2C)	CHARACTER	1	PL100_LTYP	LABEL TYPE
		.1..		PL100_AL	″X’40’″ AL - ANSI LABEL
		.... 1...		PL100_UL	″X’08’″ UL - USER LABEL
		...1		PL100_BLP	″X’10’″ BLP - BYPASS LABEL PROCESSING
		.... .1..		PL100_NSL	″X’04’″ NSL - NONSTANDARD LABEL
		.... ..1.		PL100_SL	″X’02’″ SL - STANDARD LABEL
		1		PL100_NL	″X’01’″ NL - NO LABEL
		The following 2 date fields are copied from the JFCB and thus contain 'YYDDDD' in which the 'YY' is an offset from 1900 and 'DDDD' contain the Julian day of the year. Example: X'590008' represents January 8, 1989.			
45	(2D)	CHARACTER	3	PL100_CRDT	CREATION DATE YYDDDD
48	(30)	CHARACTER	3	PL100_XPDT	EXPIRATION DATE YYDDDD
51	(33)	CHARACTER	1	PL100_OFLAG	OPEN FLAGS
		1...		PL100_FOUT	″X’80’″ DATASET OPENED FOR OUTPUT
		..1.		PL100_FEOV	″X’20’″ CALL FOR END OF VOLUME
52	(34)	CHARACTER	6	PL100_VOLSER	VOLUME SERIAL NUMBER
58	(3A)	CHARACTER	8	PL100_JOBNAM	JOB NAME
66	(42)	CHARACTER	8	PL100_STPNAM	STEP NAME
74	(4A)	CHARACTER	8	PL100_SYSTEM	SYSID
82	(52)	SIGNED	2	PL100_LRECL	LOGICAL RECORD LENGTH
84	(54)	SIGNED	2	PL100_BLKSI	BLOCKSIZE
86	(56)	CHARACTER	2	PL100_UNIT	UNIT ADDRESS (BINARY)
88	(58)	SIGNED	4	PL100_BLK#	NUMBER OF BLOCKS WRITTEN
92	(5C)	SIGNED	2	PL100_FSCT	DATASET SEQUENCE COUNT
94	(5E)	CHARACTER	1	PL100_RECFM	RECORD FORMAT
		11..		PL100_UND	″X’C0’″ UNDEFINED
		1...		PL100_FIX	″X’80’″ FIXED
		.1..		PL100_VAR	″X’40’″ VARIABLE
		..1.		PL100_RFO	″X’20’″ TRACK OVERFLOW
		...1		PL100_RFB	″X’10’″ BLOCKED
		.... 1...		PL100_RFS	″X’08’″ STANDARD/SPANNED RECORDS
		.... .1..		PL100_ASA	″X’04’″ ASA CONTROL CHARACTERS
		.... ..1.		PL100_MAC	″X’02’″ MACHINE CONTROL CHARACTERS
95	(5F)	CHARACTER	1	PL100_NVOL	VOLUME SEQUENCE NUMBER

Offsets Decimal	Hex	Type	Length	Name (Dim)	Description
96	(60)	CHARACTER	1	PL100_DEN	TAPE DENSITY (FROM JFCB)
The following 2 TDSI fields are copied from the JFCB and apply only to ATL's (AUTOMATIC TAPE LIBRARY). The TDSI (Tape Device Selection Information) is used to communicate device selection information to and among system components providing tape library support (e.g. OAM).					
97	(61)	CHARACTER	1	PL100_TDSI1	TAPE DEVICE SELECTION INFORMATION
		...1		PL100_18TRK	″X'10'″ 18 TRACK RECORDING MODE -
		..1.		PL100_36TRK	″X'20'″ 36 TRACK RECORDING MODE -
		..11		PL100_128TRK	″X'30'″ 128 TRACK RECORDING MODE -
		1		PL100_MED1	″X'01'″ CARTRIDGE SYSTEM
		.... ..1.		PL100_MED2	″X'02'″ ENHANCED CAPACITY CARTRIDGE
		11		PL100_MED3	″X'03'″ HIGH PERFORMANCE CARTRIDGE TAPE
		.... .1..		PL100_MED4	″X'04'″ RESERVED FOR FUTURE USE OF EHPCT
98	(62)	CHARACTER	1	PL100_TDSI2	TDSI BYTE 2
		...1		PL100_NOCMP	″X'10'″ COMPACTION NOT USED
		..1.		PL100_BIDRC	″X'20'″ COMPACTION TYPE=IDRC
		1		PL100_RDCOM	″X'01'″ READ COMPATIBILITY
START OF VERSION 2 FIELDS					
99	(63)	CHARACTER	8	PL100_MEDIANAME	VOLUME MEDIA NAME
107	(6B)	CHARACTER	4	PL100_CRDATE	DATA SET CREATION DATE PACKED DECIMAL YYYYDDDS
111	(6F)	CHARACTER	4	PL100_CRTIME	DATA SET CREATION TIME PACKED DECIMAL HHMMSSTS
115	(73)	CHARACTER	4	PL100_XPDATE	DATA SET EXPIRATION DATE PACKED DECIMAL YYYYDDDS
119	(77)	CHARACTER	6	PL100_PREVOL	PREVIOUS VOLUME IN SEQUENCE
125	(7D)	CHARACTER	8	PL100_CRJOB	CREATING JOB NAME

EDGPL100 Cross Reference

Name	Offset	Hex Tag	Level
PL100	0		1
PL100_ACCODE	A8		2
PL100_ACEROPTR	B0		2
PL100_AL	2C	40	3
PL100_ASA	5E	04	3
PL100_BIDRC	62	20	3
PL100_BLK#	58		2
PL100_BLKSI	54		2
PL100_BLP	2C	10	3
PL100_CAN_IGNORE	10	80	3
PL100_CAN_IGNORE_FILE2_TON	10	10	3
PL100_CAN_POOL	10	04	3
PL100_CAN_RACKNO	10	20	3

EDGPL100

Name	Offset	Hex Tag	Level
PL100_CAN_VRS	10	40	3
PL100_CRDATE	6B		2
PL100_CRDT	2D		2
PL100_CRJOB	7D		2
PL100_CRTIME	6F		2
PL100_DDNAME	98		2
PL100_DEN	60		2
PL100_DISPDD	A0		2
PL100_DSN	0		2
PL100_END	C0		2
PL100_FEOV	33	20	3
PL100_FIX	5E	80	4
PL100_FOUT	33	80	3
PL100_FSCT	5C		2
PL100_FUNCTION	24		2
PL100_FUNCTION2	25		2
PL100_HDR	0		2
PL100_IDENT	0		3
PL100_INFO	11		2
PL100_INFO_CMOVE	11	10	3
PL100_INFO_DISPDD	11	20	3
PL100_INFO_IGNORE	11	80	3
PL100_INFO_MTL	11	04	3
PL100_INFO_NOTRMM	11	40	3
PL100_INFO_USERDATA	11	08	3
PL100_ITS_CLOSE	10	02	3
PL100_JFCBPTR	28		2
PL100_JOBNAM	3A		2
PL100_LAB_USERDATA	40		2
PL100_LABDS	0		1
PL100_LABINFO	3C		2
PL100_LABPTR	88		2
PL100_LENGTH	C		3
PL100_LOCATION	8C		2
PL100_LOCTYPE	94		2
PL100_LRECL	52		2
PL100_LTYP	2C		2
PL100_MAC	5E	02	3
PL100_MEDIANAME	63		2
PL100_MOUNT_VOLSER	1A		2
PL100_NL	2C	01	3
PL100_NOCMP	62	10	3
PL100_NSL	2C	04	3
PL100_NVOL	5F		2
PL100_OFLAG	33		2
PL100_POOL	34		3
PL100_PREVOL	77		2
PL100_RACKNO	34		2
PL100_RDCOM	62	01	3
PL100_RECFM	5E		2
PL100_REQ_VOLSER	14		2
PL100_REVNO	9		3
PL100_RFB	5E	10	3
PL100_RFO	5E	20	3

Name	Offset	Hex Tag	Level
PL100_RFS	5E	08	3
PL100_SET_ACLOFF	24	01	3
PL100_SET_CMOVE	25	80	3
PL100_SET_IGNORE	24	80	3
PL100_SET_IGNORE_FILE2_TON	24	10	3
PL100_SET_IGNORE_SGNAME	25	20	3
PL100_SET_NOCMOVE	25	40	3
PL100_SET_NOLABEL	24	08	3
PL100_SET_POOL	24	04	3
PL100_SL	2C	02	3
PL100_STPNAM	42		2
PL100_SUBPOOL	A		3
PL100_SYSTEM	4A		2
PL100_TDSI1	61		2
PL100_TDSI2	62		2
PL100_UL	2C	08	3
PL100_UND	5E	C0	3
PL100_UNIT	56		2
PL100_VALID	10		2
PL100_VAR	5E	40	4
PL100_VERNO	8		3
PL100_VOLSER	34		2
PL100_VRS	2C		2
PL100_WTOPTR	20		2
PL100_XPDATE	73		2
PL100_XPDT	30		2

Installation Exit Mapping Macro: EDGPL200

EDGPL200 maps the DFSMSrmm installation exit, EDGUX200, parameter list. See “Using the DFSMSrmm EDGUX200 Installation Exit” on page 220 for information about using the EDGPL100 installation exit.

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
0	(0)	STRUCTURE		PL200	, EGDUX200 PARAMETER LIST
0	(0)	DBL WORD	8	PL200_HDR(0)	CONTROL BLOCK HEADER
THE FOLLOWING FIELDS CAN BE VALIDATED BY EDGUX200 BEFORE PROCESSING					
0	(0)	CHARACTER	8	PL200_IDENT	CONTROL BLOCK ID
8	(8)	ADDRESS	1	PL200_VERNO	CONTROL BLOCK VERSION NUMBER
9	(9)	ADDRESS	1	PL200_REVNO	CONTROL BLOCK REVISION NUMBER
10	(A)	ADDRESS	2	PL200_SUBPOOL	CONTROL BLOCK SUBPOOL NUMBER
12	(C)	ADDRESS	4	PL200_LENGTH	CONTROL BLOCK LENGTH
INPUT FIELDS START HERE					
16	(10)	BITSTRING	1	PL200_VALID	VALID FUNCTIONS
		1...		PL200_CAN_SCRTCH	″X’80’″ CAN HANDLE RETURN TO SCRATCH
17	(11)	BITSTRING	3		RESERVED
20	(14)	CHARACTER	6	PL200_VOLSER	RMM DEFINED VOLUME SERIAL NUMBER

EDGPL200

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
26	(1A)	CHARACTER	6	PL200_RACK_NUMBER	RMM DEFINED RACK NUMBER
32	(20)	CHARACTER	8	PL200_MEDIA_NAME	VOLUME MEDIA NAME
40	(28)	CHARACTER	8	PL200_LOCATION	VOLUME LOCATION
48	(30)	BITSTRING	2	PL200_VOLSEQ	VOLUME SEQUENCE NUMBER
50	(32)	CHARACTER	44	PL200_DSNAME	1ST FILE DATA SET NAME
94	(5E)	BITSTRING	1	PL200_VOLUME_FLAGS	STATUS FLAGS FOR VOLUME
		1...		PL200_SMS_VOL	″X'80'″ VOLUME IS SMS MANAGED
OUTPUT FIELDS START HERE					
95	(5F)	BITSTRING	1	PL200_FUNCTION	REQUESTED FUNCTION
		1...		PL200_SET_NOSCRTCH	″X'80'″ DO NOT RETURN TO SCRATCH
		.1..		PL200_SET_IGNORE_DSN	″X'40'″ IGNORE DATA SET INFORMATION
96	(60)	DBL WORD	8	PL200_END(0)	END OF PL200
		.11.		PL200_LEN#	″PL200_END-PL200_HDR″ LENGTH OF PL200
CONSTANTS USED TO INITIALIZE THE PL200 HEADER SECTION					
		1		PL200_VER#	″1″ VERSION NUMBER
		....		PL200_REV#	″0″ REVISION NUMBER
		....		PL200_SP#	″0″ SUBPOOL NUMBER

EDGPL200 Cross Reference

Name	Offset	Hex Tag	Level
PL200_CAN_SCRTCH	10	80	2
PL200_DSNAME	32	40404040	2
PL200_END	60		2
PL200_FUNCTION	5F	0	2
PL200_HDR	0		2
PL200_IDENT	0	C5C4C7D7	2
PL200_LEN#	60	60	2
PL200_LENGTH	C		2
PL200_LOCATION	28	40404040	2
PL200_MEDIA_NAME	20	40404040	2
PL200_RACK_NUMBER	1A	40404040	2
PL200_REV#	60	0	2
PL200_REVNO	9		2
PL200_SET_IGNORE_DSN	5F	40	2
PL200_SET_NOSCRTCH	5F	80	2
PL200_SMS_VOL	5E	80	2
PL200_SP#	60	0	2
PL200_SUBPOOL	A		2
PL200_VALID	10	0	2
PL200_VER#	60	1	2

Name	Offset	Hex Tag	Level
PL200_VERNO	8		2
PL200_VOLSEQ	30	0	2
PL200_VOLSER	14	40404040	2
PL200_VOLUME_FLAGS	5E	0	2

Sticky Label Data: EDGSLAB

EDGSLAB maps the DFSMSrmm sticky label data area. See “Chapter 20. Setting Up DFSMSrmm Disposition Processing” on page 347 for more information about the default sticky labels you can request with DFSMSrmm disposition processing.

Offsets					
Dec	Hex	Type	Len	Name (Dim)	Description
0	(0)	STRUCTURE		SLAB	
0	(0)	DBL WORD	8	SLABENT (0)	** BEGIN OF SLAB **
0	(0)	CHARACTER	8	SLABID	** SLAB EYECATCHER **
8	(8)	BITSTRING	1	SLABSPL	** SLAB SUBPOOL NUMBER **
9	(9)	BITSTRING	3	SLABSIZE	** SLAB TOTAL SIZE **
12	(C)	BITSTRING	1	SLABKEY	** SLAB PROTECTION KEY**
13	(D)	BITSTRING	1	SLABVER	** SLAB VERSION **
14	(E)	BITSTRING	1	SLABLRECL	** SLAB OUTPUT FILE LRECL**
15	(F)	CHARACTER	1	SLABTYPE	** SLAB LABEL TYPE**
		1...		SLABTYPE_CART	** ″X’80’″ SLAB CARTRIDGE LABEL BUILT **
		.1..		SLABTYPE_REEL	** ″X’40’″ SLAB REEL LABEL BUILT **
16	(10)	BITSTRING	1	SLABCOL	** SLAB NUMBER OF COLUMNS**
17	(11)	BITSTRING	1	SLABROW	** SLAB NUMBER OF ROWS**
20	(14)	SIGNED	4	SLABLAB (0)	** SLAB STICKY LABEL **
20	(14)	CHARACTER	2000	SLABMAX	** **
20	(14)	SIGNED	4	SLABCART (0)	** SLAB CARTRIDGE LABEL LAYOUT**
20	(14)	CHARACTER	80	SLABCLN1	** SLAB RECORD 1 **
100	(64)	CHARACTER	80	SLABCLN2	** SLAB RECORD 2 **
180	(B4)	CHARACTER	80	SLABCLN3	** SLAB RECORD 3 **
260	(104)	CHARACTER	80	SLABCLN4	** SLAB RECORD 4 **
340	(154)	CHARACTER	80	SLABCLN5	** SLAB RECORD 5 **
420	(1A4)	CHARACTER	80	SLABCLN6	** SLAB RECORD 6 **
500	(1F4)	CHARACTER	80	SLABCLN7	** SLAB RECORD 7 **
580	(244)	CHARACTER	80	SLABCLN8	** SLAB RECORD 8 **
660	(294)	CHARACTER	80	SLABCLN9	** SLAB RECORD 9 **
740	(2E4)	CHARACTER	80	SLABCLNA	** SLAB RECORD 10 **
20	(14)	CHARACTER	44	SLABCDSN	** SLAB CART. LABEL DSNAME **
100	(64)	CHARACTER	69	SLABUSR	** SLAB CART. USER DATA **
260	(104)	CHARACTER	1		** **
261	(105)	CHARACTER	8	SLABCJBN	** SLAB CART. LABEL JOBNAME **
269	(10D)	CHARACTER	5		** **
274	(112)	CHARACTER	10	SLABCCRD	** SLAB CART. LABEL CREATE DATE **
340	(154)	CHARACTER	14		** **
354	(162)	CHARACTER	10	SLABCEXP	** SLAB CART. LABEL EXPIR. DATE **

EDGSLAB

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
420	(1A4)	CHARACTER	1		** **
421	(1A5)	CHARACTER	4	SLABCDEN	** SLAB CART. LABEL DENSITY **
425	(1A9)	CHARACTER	1		** **
426	(1AA)	CHARACTER	4	SLABCCMP	** SLAB CART. LABEL COMPACTION **
430	(1AE)	CHARACTER	1		** **
431	(1AF)	CHARACTER	5	SLABCLRC	** SLAB CART. LABEL LRECL **
436	(1B4)	CHARACTER	2		** **
438	(1B6)	CHARACTER	5	SLABCBLK	** SLAB CART. LABEL BLKSIZE **
443	(1BB)	CHARACTER	2		** **
445	(1BD)	CHARACTER	4	SLABCRCF	** SLAB CART. LABEL RECFM **
580	(244)	CHARACTER	1		** **
581	(245)	CHARACTER	6	SLABCVSL	** SLAB CART. LABEL VOLSER **
587	(24B)	CHARACTER	1		** **
588	(24C)	CHARACTER	4	SLABCSQN	** SLAB CART. LABEL VOL SEQUENCE **
592	(250)	CHARACTER	1		** **
593	(251)	CHARACTER	3	SLABCLAB	** SLAB CART. LABEL VOL LABL TYPE **
596	(254)	CHARACTER	7		** **
603	(25B)	CHARACTER	4	SLABCDVC	** SLAB CART. LABEL DEVICE NUMBER **
20	(14)	SIGNED	4	SLABTAPE (0)	** SLAB TAPE LABEL LAYOUT **
20	(14)	CHARACTER	80	SLABTLN1	** SLAB RECORD 1 **
100	(64)	CHARACTER	80	SLABCTLN2	** SLAB RECORD 2 **
180	(B4)	CHARACTER	80	SLABTLN3	** SLAB RECORD 3 **
260	(104)	CHARACTER	80	SLABTLN4	** SLAB RECORD 4 **
340	(154)	CHARACTER	80	SLABTLN5	** SLAB RECORD 5 **
420	(1A4)	CHARACTER	80	SLABTLN6	** SLAB RECORD 6 **
500	(1F4)	CHARACTER	80	SLABTLN7	** SLAB RECORD 7 **
580	(244)	CHARACTER	80	SLABTLN8	** SLAB RECORD 8 **
660	(294)	CHARACTER	80	SLABTLN9	** SLAB RECORD 9 **
740	(2E4)	CHARACTER	80	SLABTLNA	** SLAB RECORD 10 **
20	(14)	CHARACTER	44	SLABTDSN	** SLAB TAPE LABEL DSNAME **
100	(64)	CHARACTER	69	SLABTUSR	** SLAB TAPE USER DATA **
180	(B4)	CHARACTER	4		** **
184	(B8)	CHARACTER	8	SLABTJBN	** SLAB TAPE. LABEL JOBNAME **
192	(C0)	CHARACTER	18		** **
210	(D2)	CHARACTER	10	SLABTCRD	** SLAB TAPE LABEL CREATE DATE **
340	(154)	CHARACTER	1		** **
341	(155)	CHARACTER	4	SLABTDEN	** SLAB TAPE DENSITY **
345	(159)	CHARACTER	1		** **
346	(15A)	CHARACTER	4	SLABTCMP	** SLAB TAPE LABEL COMPACTION **
350	(15E)	CHARACTER	1		** **
351	(15F)	CHARACTER	5	SLABTLRC	** SLAB TAPE LABEL LRECL **

Offsets Dec	Hex	Type	Len	Name (Dim)	Description
356	(164)	CHARACTER	2		** **
358	(166)	CHARACTER	5	SLABTBLK	** SLAB TAPE LABEL BLKSIZE **
363	(16B)	CHARACTER	2		** **
365	(16D)	CHARACTER	4	SLABTRCF	** SLAB TAPE LABEL RECFM **
369	(171)	CHARACTER	1		** **
370	(172)	CHARACTER	10	SLABTEXP	** SLAB TAPE LABEL EXPIR. DATE **
500	(1F4)	CHARACTER	15		** **
515	(203)	CHARACTER	6	SLABTVSL	** SLAB TAPE LABEL VOLSER **
521	(209)	CHARACTER	1		** **
522	(20A)	CHARACTER	4	SLABTSQN	** SLAB TAPE LABEL VOL SEQUENCE **
526	(20E)	CHARACTER	1		** **
527	(20F)	CHARACTER	3	SLABTLAB	** SLAB TAPE LABEL VOL LABL TYPE **
530	(212)	CHARACTER	6		** **
536	(218)	CHARACTER	4	SLABTDVC	** SLAB TAPE LABEL DEVICE NUMBER **
2024	(7E8)	DBL WORD	8	SLABEND (0)	**END OF SLAB** ″SLABEND-SLABENT″
				SLABLNG	** LENGTH OF SLAB **
FLAG BYTES					
		1		SLABVER#	″1′″ ** VERSION NUMBER **
		.... .1.1		SLABKEY#	″5″ ** KEY NUMBER**
		111. .11.		SLABSP#	″230″ ** SUBPOOL NUMBER**
		.... 1.1.		SLABROW#	″10″ ** DEFAULT NUMBER OF ROWS**
		.1.1		SLABCOL#	″80″ ** DEFAULT NUMBER OF COLS**
		.1.1		SLABLRECL#	″80″ ** DEFAULT LRECL **

EDGSLAB Cross Reference

Name	Offset	Hex Tag	Level
SLABCART	14		2
SLABCBLK	1B6		2
SLABCCMP	1AA		2
SLABCCRD	112		2
SLABCDEN	1A5		2
SLABCDSN	14		2
SLABCDVC	25B		2
SLABCEXP	162		2
SLABCJBN	105		2
SLABCLAB	251		2
SLABCLNA	2E4		2
SLABCLN1	14		2
SLABCLN2	64		2
SLABCLN3	B4		2
SLABCLN4	104		2
SLABCLN5	154		2
SLABCLN6	1A4		2

EDGSLAB

Name	Offset	Hex Tag	Level
SLABCLN7	1F4		2
SLABCLN8	244		2
SLABCLN9	294		2
SLABCLRC	1AF		2
SLABCOL	10		2
SLABCOL#	7E8	50	2
SLABCRCF	1BD		2
SLABCSQN	24C		2
SLABCUSR	64		2
SLABCVSL	245		2
SLABEND	7E8		2
SLABENT	0		2
SLABID	0		2
SLABKEY	C		2
SLABKEY#	7E8	5	2
SLABLAB	14		2
SLABLNG	7E8	7E8	2
SLABLRECL	E		2
SLABLRECL#	7E8	50	2
SLABMAX	14		2
SLABROW	11		2
SLABROW#	7E8	A	2
SLABSIZE	9		2
SLABSP#	7E8	E6	2
SLABSPL	8		2
SLABTAPE	14		2
SLABTBLK	166		2
SLABTCMP	15A		2
SLABTCRD	D2		2
SLABTDEN	155		2
SLABTDSN	14		2
SLABTDVC	218		2
SLABTEXP	172		2
SLABTJBN	B8		2
SLABTLAB	20F		2
SLABTLNA	2E4		2
SLABTLN1	14		2
SLABTLN2	64		2
SLABTLN3	B4		2
SLABTLN4	104		2
SLABTLN5	154		2
SLABTLN6	1A4		2
SLABTLN7	1F4		2
SLABTLN8	244		2
SLABTLN9	294		2
SLABTLRC	15F		2
SLABTRCF	16D		2
SLABTSQN	20A		2
SLABTUSR	64		2
SLABTVSL	203		2
SLABTYPE	F		2
SLABTYPE_CART	F	80	2
SLABTYPE_REEL	F	40	2
SLABVER	D		2

EDGSLAB

Name	Offset	Hex Tag	Level
SLABVER#	7E8	1	2

EDGSLAB

Appendix C. Using DFSMSrmm Samples

DFSMSrmm provides several samples in SAMPLIB, SMPSTS, and SYS1.SEDGEXE1. Table 57 lists the samples that are available and where they can be found after SMP/E APPLY processing. After SMP/E ACCEPT processing, samples in SAMPLIB move to ASAMPLIB and samples in SMPSTS move to the AEDGSRC1 library.

You can use the Tivoli OPC sample jobs or procedures with other scheduling systems or without Tivoli OPC. In some cases, you must modify the sample jobs.

Table 57. SAMPLIB and SMPSTS Members

Member Name	Shows You How To	Supplied In
CBRUXCUA	Use programming interface to EDGLCSUX	SMPSTS
CBRUXEJC	Use programming interface to EDGLCSUX	SMPSTS
CBRUXENT	Use programming interface to EDGLCSUX	SMPSTS
CBRUXVNL	Use programming interface to EDGLCSUX	SMPSTS
EDG3IIP1	Update IATIIP1 to force DEFER for all tape requests	SAMPLIB
EDG3LVVR	Update IATLVVR to AWAIT MSGDISP for scratch mounts	SAMPLIB
EDG3UX29	Install a JES3 USERMOD	SAMPLIB
EDG3UX62	Update IATUX62 to override JES3 rejection of standard label tapes	SAMPLIB
EDG3UX71	Update IATUX71 to replace and append text to JES3 fetch and mount messages and to provide text for tape drive displays	SAMPLIB
EDGBETT	Sample procedure for Tivoli OPC event trigger tracking of backup	SAMPLIB
EDGCLIBQ	Use reports for VM tape volumes	SAMPLIB
EDGCLMS	Convert volume information into commands	SAMPLIB
EDGDFRMM	Create a procedure in SYS1.PROCLIB	SAMPLIB
EDGIVPPM	Parmlib member for supplied Installation Verification Program (IVP)	SAMPLIB
EDGIVP1	IVP job 1 - initializes tape volumes	SAMPLIB
EDGIVP2	IVP job 2 - uses tape volumes	SAMPLIB
EDGJACTP	Print the ACTIVITY file	SAMPLIB
EDGJAUDM	Create a monthly archive from weekly audit reports	SAMPLIB
EDGJAUDW	Create a weekly archive from daily audit reports	SAMPLIB
EDGJBCAV	Build RMM ADDVOLUME subcommands from a list of barcode scanned volumes	SAMPLIB
EDGBKP1	Sample Tivoli OPC job for running backup	SAMPLIB
EDGBKP2	Sample Tivoli OPC job for running backup	SAMPLIB
EDGJBKUP	Sample JCL for using the backup program	SAMPLIB
EDGCMOV	Sample Tivoli OPC job for confirming volume moves	SAMPLIB
EDGJCOMB	Audit tape library using a list of barcode scanned volumes	SAMPLIB
EDGJCVB	Create a report of volumes in a storage location	SAMPLIB
EDGJDHKP	Sample Tivoli OPC job for running daily inventory management	SAMPLIB
EDGJDSN	Create a report of data sets sorted by data set name	SAMPLIB
EDGJEJC	Sample Tivoli OPC job for ejecting volumes from system-managed libraries	SAMPLIB
EDGJEXP	Sample Tivoli OPC job for running expiration processing	SAMPLIB
EDGJHKPA	Sample JCL for allocating the data sets required for inventory management	SAMPLIB
EDGJHSKP	Sample JCL for using the utility program EDGHSKP	SAMPLIB

© Copyright IBM Corp. 1992, 2001

Table 57. SAMPLIB and SMPSTS Members (continued)

Member Name	Shows You How To	Supplied In
EDGJIMPC	Sample JCL to create an import list from CLIST output	SAMPLIB
EDGJINER	Sample JCL for using the utility program EDGINERS	SAMPLIB
EDGJLOPC	Sample JCL for running the OPC batch loader utility to define DFSMSrmm as an application to OPC	SAMPLIB
EDGJMFAL	Sample JCL for allocating the control data set	SAMPLIB
EDGJMOVE	Sample Tivoli OPC job for creating movement reports	SAMPLIB
EDGJNLAL	Sample JCL for allocating the journal	SAMPLIB
EDGJNSCR	Create a report of volumes recently returned to scratch status	SAMPLIB
EDGJRACK	Create a report based on rack number prefixes	SAMPLIB
EDGJRECL	Create a report containing information about lost volumes	SAMPLIB
EDGJRECV	Build RMM subcommands to add volumes to DFSMSrmm	SAMPLIB
EDGJROWN	Create a report about owners sorted by name and department number	SAMPLIB
EDGJRPT	Sample JCL to create reports using the extended report extract file	SAMPLIB
EDGJRVOL	Create a report about volumes; by volume serial number, by rack number, by security level, by owner, and by expiration date	SAMPLIB
EDGJSCRL	Sample Tivoli OPC job for creating scratch listings	SAMPLIB
EDGJSMF	Create a report of SMF records	SAMPLIB
EDGJSMFP	Create a list of types of SMF record found	SAMPLIB
EDGJUTIL	Sample JCL for initializing the control data set	SAMPLIB
EDGJVFY	Sample Tivoli OPC job for verifying control data set contents	SAMPLIB
EDGJVLT	Create a report about volumes currently in storage locations sorted by volume serial number	SAMPLIB
EDGJVLTM	Create a report about volumes moving to storage locations	SAMPLIB
EDGJVME	Sample JCL for creating reports for VM tape volumes	SAMPLIB
EDGJVOL	Create a report about volumes sorted by volume serial number	SAMPLIB
EDGJVRSV	Sample Tivoli OPC job for running vital record processing trial run	SAMPLIB
EDGJWHKP	Sample Tivoli OPC job for running weekly inventory management	SAMPLIB
EDGLABEL	Started procedure for initializing and erasing tapes	SAMPLIB
EDGPACTA	Sample Tivoli OPC procedure for allocating ACTIVITY report files	SAMPLIB
EDGPACTC	Sample Tivoli OPC procedure sort input	SAMPLIB
EDGPACTD	Sample Tivoli OPC procedure sort input	SAMPLIB
EDGPACTI	Sample Tivoli OPC procedure ICETOOL control statements	SAMPLIB
EDGPACTM	Sample Tivoli OPC procedure sort input	SAMPLIB
EDGPACTP	Sample Tivoli OPC procedure reporting on ACTIVITY file	SAMPLIB
EDGPACTT	Sample Tivoli OPC procedure sort input	SAMPLIB
EDGPACTV	Sample Tivoli OPC procedure sort input	SAMPLIB
EDGPBKUP	Sample Tivoli OPC procedure for control data set backup	SAMPLIB
EDGPCMOV	Sample Tivoli OPC procedure for global volume move confirmation	SAMPLIB
EDGPEJC	Sample Tivoli OPC procedure for ejecting volumes	SAMPLIB
EDGPEXP	Sample Tivoli OPC procedure for running expiration processing	SAMPLIB
EDGPHKP	Sample Tivoli OPC procedure for running inventory management	SAMPLIB

Table 57. SAMPLIB and SMPSTS Members (continued)

Member Name	Shows You How To	Supplied In
EDGPHKPA	Sample Tivoli OPC procedure for allocating inventory management data sets	SAMPLIB
EDGPINER	Sample Tivoli OPC procedure for labeling and erasing tapes	SAMPLIB
EDGPMOVE	Sample Tivoli OPC procedure for creating movement reports	SAMPLIB
EDGPMSGA	Sample Tivoli OPC procedure for allocating the next generation of the MESSAGE file	SAMPLIB
EDGPMSGC	Sample Tivoli OPC procedure for copying the MESSAGE file and creating the next generation of the MESSAGE file	SAMPLIB
EDGPRPTA	Sample Tivoli OPC procedure for allocating the next generation of the report extract file	SAMPLIB
EDGPRPTX	Sample Tivoli OPC procedure for creating the report extract file	SAMPLIB
EDGPSCRL	Sample Tivoli OPC procedure for creating the scratch list report	SAMPLIB
EDGPVFY	Sample Tivoli OPC procedure for verifying the contents of the control data set	SAMPLIB
EDGPVRSA	Sample Tivoli OPC procedure for allocating the next generation of the REPORT file and the ACTIVITY file	SAMPLIB
EDGRHKPA	Sample Tivoli OPC exec for defining GDG bases	SAMPLIB
EDGRCSCR	Rexx Exec to convert pool information to ACS routine input and VLPOOL definitions	EDGEXE1
EDGRRPTE	REXX Exec to create reports using the extended report extract file	EDGEXE1
EDGRRPTM	REXX Exec to create an extended extract file only for multiple data sets and multivolume reporting	EDGEXE1
EDGRRPTR	REXX Exec to create an extended report extract file	EDGEXE1
EDGRVCLN	REXX Exec to report and update existing vital record specifications	EDGEXE1
EDGSETT	Sample Tivoli OPC procedure for OPC event trigger tracking of low-on-scratch volume condition	SAMPLIB
EDGUX100	Use the installation exit EDGUX100	SAMPLIB
EDGUX200	Use the installation exit EDGUX200	SAMPLIB
EDGXMP1	REXX EXEC to list all volumes in a multivolume set	SAMPLIB
EDGXMP2	REXX EXEC to list all data set information for a given volume	SAMPLIB
EDGXPROC	Replenish scratch volumes in a automated tape library dataserver	SAMPLIB
IGXMSGEX	Use programming interface to EDGMSGEX	SMPSTS

Appendix D. DFSMSrmm System and User Completion Codes

System Completion Codes

These are the system completion codes issued during DFSMSrmm processing.

F13

Explanation: At OPEN time for tape data sets, DFSMSrmm fails to update the DFSMSrmm control data set with information about tape usage or the operator mounted a volume that is not acceptable to DFSMSrmm. DFSMSrmm issues an error message describing the reason why the volume cannot be used.

DFSMSrmm issues this code for one of the following reasons:

- An error occurred performing I/O to the DFSMSrmm control data set and the operator replied CANCEL to message EDG4001D.
- The DFSMSrmm journal file is locked and the operator replied CANCEL to message EDG4000D.
- The DFSMSrmm subsystem is not active and the operator replied CANCEL to message EDG4012D.

The current volume was not acceptable to DFSMSrmm and DFSMSrmm could find no other acceptable volume. If DFSMSrmm returns a reason code or user completion code, this is an indication that a DFSMSrmm subsystem routine failed.

Module: EDGOECK, EDGOECM, EDGOEMD

System Action: The current OPEN request fails because no volume is available to satisfy the request.

Operator Response: None.

Programmer Response: When DFSMSrmm issues message EDG4000D or EDG4001D, refer to the suggested actions for the messages. When DFSMSrmm issues message EDG4012D, ensure that the DFRMM procedure is active and specify the correct volume and tape data set information for specific tape mount request.

F14

Explanation: DFSMSrmm fails to update the DFSMSrmm control data set with information about tape usage because the DFSMSrmm subsystem is not active. DFSMSrmm issues an error message to describe the problem. If a reason code or user completion code is provided, this is an indication that the DFSMSrmm subsystem routine failed.

Module: EDGCLEV

System Action: The CLOSE or End-Of-Volume processing fails. Processing depends on the application error recovery processing.

Operator Response: Refer to the action described for the associated error message.

System Programmer Response: Refer to the action described for the associated error message.

F37

Explanation: An error occurred during validation of a tape volume, or during updating of the DFSMSrmm control data set. DFSMSrmm issues an error message describing the error. DFSMSrmm issues F37 at End-Of-Volume, when validating the new volume for a multivolume tape data set or when recording the use of the previous volume.

DFSMSrmm issues F37 for one of these reasons:

- An error occurred performing I/O to the DFSMSrmm control data set and the operator replied CANCEL to message EDG4001D.
- The DFSMSrmm journal file is locked and the operator replied CANCEL to message EDG4000D.
- The DFSMSrmm subsystem is not active and the operator replied CANCEL to message EDG4012D.
- The current volume was not acceptable to DFSMSrmm and DFSMSrmm could find no other acceptable volume.

If a reason code or user completion code is provided, this indicates that the DFSMSrmm subsystem routine failed. DFSMSrmm issues this code because either the DFSMSrmm subsystem is not active and the operator replied CANCEL to message EDG4012D or because the current volume was not acceptable to DFSMSrmm and DFSMSrmm could find no other acceptable volume.

Module: EDGCLEV, EDGOECK, EDGOECM, EDGOEMD

System Action: The current EOV request fails.

Operator Response: None.

Programmer Response: When DFSMSrmm issues message EDG4000D or EDG4001D, refer to the suggested actions described for the messages. When DFSMSrmm issues message EDG4012D, ensure that the DFRMM procedure is active and specify the correct volume and tape data set information for specific tape mount requests. If a tape volume is rejected because it violates DFSMSrmm tape usage rules, correct your JCL and rerun the job.

© Copyright IBM Corp. 1992, 2001

User Completion Codes

These are the user completion codes issued during DFSMSrmm processing.

U0001

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a GET DIRECT request.

Module: EDGMTSO, EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0002

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a GET DIRECT request.

Module: EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0003

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a GET KEY GREATER THAN request.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0004

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a GET KEY GREATER OR EQUAL request.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0005

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a request to gain exclusive use of the control data set.

Module: EDGMTSO, EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: An associated error message is issued with details of the error. Refer to that message for corrective actions.

U0006

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a LOGICAL ADD request.

Module: EDGMTSO, EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0007

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a CHANGE request.

Module: EDGMTSO, EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0008

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a LOGICAL DELETE request.

Module: EDGMTSO, EDGSOCE

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0009

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a SEARCH request.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0010

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a SEARCH NEXT request.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0011

Explanation: An error occurred processing OWNER information in the DFSMSrmm control data set.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0012

Explanation: An error occurred processing PRODUCT information in the DFSMSrmm control data set.

Module: EDGMTSO

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A possible error exists in the logic of the DFSMSrmm control data set. Use the utility EDGUTIL to verify the contents of the DFSMSrmm control data set.

U0013

Explanation: An error occurred performing I/O to the DFSMSrmm control data set during a request to release exclusive use of the control data set.

Module: EDGMTSO

System Action: The current processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: DFSMSrmm issues an error message describing the error. Refer to that message for corrective actions.

U0014

Explanation: A search request specifying a generic name fails.

Module: EDGMTSO

System Action: The current request fails. The reason code is the return code from an internal DFSMSrmm service routine.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0015

Explanation: A volume is being added or changed and information about it should be in the volume catalog. The DFSMSrmm request to retrieve information from the volume catalog has failed.

Module: EDGMTSO

System Action: The current request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0016

Explanation: A volume is being added or changed that has outstanding actions or moves against it. DFSMSrmm was unable to update the control data set with the specified actions.

Module: EDGMTSO

System Action: The current request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0093

Explanation: An error occurred in TPUT handling while parsing parameters.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0100

Explanation: An error occurred establishing a recovery environment for a DFSMSrmm program. At the time of the abend, Register 15 contains the ESTAE macro return code.

Module: EDGINERS, EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0100

Explanation: An error occurred performing RACROUTE RACHECK.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0100

Explanation: During subsystem interface initialization, a system function failed to complete successfully.

Module: EDGSSSI

System Action: Initialization stops. The reason code is the return code from the system function that failed.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U01nn

Explanation: The DFSMSrmm subsystem encounters an error and cannot recover. DFSMSrmm issues an error message to describe the failure. *nn* in the completion code is the code returned from the failing service routine used.

Module: EDGQMGR

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report this error to the system programmer.

System Programmer Response: Determine the cause of the error and correct it if possible. If the error cannot be corrected, report this error to the IBM Support Center.

U0101

Explanation: The DFSMSrmm subsystem inventory management processing encounters an error and cannot continue. A request to perform I/O to the DFSMSrmm control data set has failed. The abend reason code is the return code from the DFSMSrmm I/O request.

Module: EDGMHKP

System Action: The DFSMSrmm inventory management request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Determine the cause of the error and correct it if possible. If the error cannot be corrected, report this error to the IBM Support Center.

U0110

Explanation: An error occurred performing a RACROUTE RACDEF-DELETE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0111

Explanation: An error occurred performing a RACROUTE RACDEF-DELETE when a related delete had already been successful.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0120

Explanation: An error occurred performing a RACROUTE RACDEF-ADDVOL.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0124

Explanation: An error occurred when attaching the DFSMSrmm subtasks. The completion code is accompanied by a reason code, which is the return code from the ATTACH macro.

Module: EDGAMGR

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report this error to the system programmer.

System Programmer Response: If recovery is not possible, report this error to the IBM Support Center.

U0125

Module: EDGAMGR

Explanation: An error occurred while checking the device type of the data set allocated during inventory management. The completion code is accompanied by a reason code, which is the return code from the DEVTYPE macro.

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report the error to the system programmer.

System Programmer Response: If recovery is not possible, report this error to the IBM Support Center.

U0126

Module: EDGAMGR

Explanation: An error occurred when deallocating the data set allocated during inventory management. The completion code is accompanied by a reason code, which is the return code from SVC 99.

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report the error to the system programmer.

System Programmer Response: If recovery is not possible, report this error to the IBM Support Center.

U0130

Explanation: An error occurred performing a RACROUTE RACDEF-DEFINE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0150

Explanation: An error occurred performing a RACROUTE RACXTRT - EXTRACT.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0160

Explanation: An error occurred performing an ICHEINTY DELETE ACCESS LIST.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0170

Explanation: An error occurred performing a RACROUTE RACXTRT - REPLACE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0180

Explanation: A logic error occurred in DFSMSrmm RACF processing.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0200

Explanation: An error occurred performing a RACROUTE RACHECK.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0200

Explanation: The DEVTYPE macro returned an unacceptable return code when checking for the PARMLIB DD.

Module: EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0200

Explanation: During subsystem interface initialization, a system function failed to complete successfully.

Module: EDGSSSI

System Action: Initialization stops. The reason code is the return code from the system function that failed.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U02nn

Explanation: The DFSMSrmm subsystem encounters an error and cannot recover. DFSMSrmm issues an error message to describe the failure. *nn* in the completion code is the code returned from the failing service routine used.

Module: EDGQMGR

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report this error to the system programmer.

System Programmer Response: Determine the cause of the error and correct it if possible. If it is not possible to correct the error, contact the IBM Support Center.

U0220

Explanation: An error occurred performing a RACROUTE RACDEF - ADDVOL.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0230

Explanation: An error occurred performing a RACROUTE RACDEF - DEFINE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0300

Explanation: An error occurred performing a RACROUTE RACHECK.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0300

Explanation: The PARMLIB DD is allocated to a non-DASD device type.

Module: EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Provide a parmlib data set to DFSMSrmm that resides on a DASD device.

U0300

Explanation: During subsystem interface initialization, DFSMSrmm could not issue a message. The DFSMSrmm message processing routine returned an error indication.

Module: EDGSSSI

System Action: Initialization stops. The reason code is the return code from the DFSMSrmm message routine that failed. An error message is issued by the message routine.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U03nn

Explanation: The DFSMSrmm subsystem encounters an error and cannot recover. DFSMSrmm issues an error message to describe the failure. *nn* in the completion code is the code returned from the failing service routine used.

Module: EDGQMGR

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report this error to the system programmer.

System Programmer Response: Determine the cause of the error and correct it if possible. If it is not possible to correct the error, contact the IBM Support Center.

U0301

Explanation: An error occurred while issuing a message to the TSO terminal.

Module: EDGTSO

System Action: Processing ends.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0302

Explanation: The DFSMSrmm subsystem issued an unexpected return code and reason code.

Module: EDGTSO

System Action: Processing ends.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0303

Explanation: An error occurred while using the TSO service routine IKJCT441 to set the variable that contains the command failure reason code.

Module: EDGTSO

System Action: Processing ends.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0304

Explanation: An error occurred while using the TSO service routine IKJCT441 to set the variable that contains the command error information message text.

Module: EDGTSO

System Action: Processing ends.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0305

Explanation: An error occurred determining the validity of an SMS location or DFSMS Storage Group.

Module: EDGTSO

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0306

Explanation: An error occurred determining if the SMS subsystem was active.

Module: EDGTSO

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0307

Explanation: An error occurred during CLIST processing.

Module: EDGTSOCL

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0350

Explanation: An error occurred performing a RACROUTE RACXTRT - EXTRACT.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0360

Explanation: An error occurred performing an ICHEINTY DELETE ACCESS LIST.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0370

Explanation: An error occurred performing a RACROUTE RACXTRT - REPLACE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0380

Explanation: An error occurred performing a RACROUTE DEFINE for a tape data set. DFSMSrmm tried to create the first entry in the TVTOC for a tape volume. TAPEVOL class and TAPEDSN option are in use and neither ADSP nor PROTECT=YES is specified in the JCL.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0400

Explanation: An error occurred performing a RACROUTE RACHECK.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0400

Explanation: An attempt to obtain the Job File Control Block (JFCB) for the PARMLIB DD failed.

Module: EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U04nn

Explanation: The DFSMSrmm subsystem encounters an error and cannot recover. DFSMSrmm issues an error message to describe the failure. *nn* in the completion code is the code returned from the failing service routine used.

Module: EDGQMGR

System Action: The DFSMSrmm subsystem stops.

Operator Response: Report this error to the system programmer.

System Programmer Response: Determine the cause of the error and correct it if possible. If it is not possible to correct the error, report this error to the IBM Support Center.

U0410

Explanation: An error occurred performing a RACROUTE RACDEF - DELETE.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0500

Explanation: An error occurred performing a catalog LOCATE request.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0500

Explanation: DFSMSrmm failed to open the data set referred to by the PARMLIB DD.

Module: EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0510

Explanation: An error occurred performing a catalog DELETE request.

Module: EDGRACF

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0600

Explanation: The DFSMSrmm subsystem did not find the parmlib member to be used for the PARMLIB DD.

Module: EDGPARM

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0650

Explanation: An error occurred determining if the SMS subsystem was active. You have tried to use the VOLCAT processing option for the EDGUTIL utility and SMS must be active if that option is used.

Module: EDGUTIL

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0651

Explanation: An error occurred determining if a volume location name is valid on the current system. You are using the VOLCAT processing option for the EDGUTIL utility and for each volume that is in a system-managed tape library. DFSMSrmm validates the location name prior to checking that the DFSMSrmm location name value matches that recorded in the volume catalog.

Module: EDGUTIL

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0652

Explanation: The utility, EDGUTIL, failed to add a message to the SYSPRINT file.

Module: EDGUTIL

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0653

Explanation: An error occurred releasing a control data set record.

Module: EDGUTIL

System Action: Processing fails. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0654

Explanation: An error occurred updating the control data set control record.

Module: EDGUTIL

System Action: Processing fails. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0655

Explanation: An error occurred sorting data set records.

Module: EDGUTIL

System Action: Processing fails. The system writes a dump.

Operator Response: Report the error to the system programmer.

System Programmer Response: Correct the error that caused the SORT program to fail. Use the //SORTDIAG DD statement to trigger sort messages to the //SYSOUT file. These DD statements must be added to the job step executing the EDGUTIL utility.

If the failure is not sort related, report the problem to the IBM Support Center. Provide the system dump written as a result of the ABEND U0655.

U0656

Explanation: An error occurred locating the UCB address of the control data set.

Module: EDGUTIL

System Action: Processing fails. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0700

Explanation: The DFSMSrmm subsystem could not issue a message because of an error in the message processing routine.

Module: EDGPARM

System Action: DFSMSrmm issues a WTO message and subsystem processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0800

Explanation: An error occurred during LOCDEF validation.

Module: EDGPARM

System Action: Processing ends. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0801

Explanation: An error occurred in dynamic allocation of a temporary data set. The reason code is the return code from the DYNALLOC macro.

Module: EDGCNVRP

System Action: DFSMSrmm writes a dump and recovery processing begins.

Operator Response: Report this error to the system programmer.

System Programmer Response: Review the return codes from DYNALLOC and take appropriate actions.

U0802

Explanation: An error occurred obtaining information from the Job File Control Block (JFCB) of a temporary data set. The reason code is the return code from the RDJFCB macro.

Module: EDGCNVRP

System Action: DFSMSrmm writes a dump and recovery processing begins.

Operator Response: Report this error to the system programmer.

System Programmer Response: Review the return codes from RDJFCB and take appropriate actions.

U0803

Explanation: An error occurred in dynamic allocation of a temporary data set when attempting to deallocate the data set. The reason code is the return code from the DYNALLOC macro.

Module: EDGCNVRP

System Action: DFSMSrmm writes a dump and recovery processing begins.

Operator Response: Report this error to the system programmer.

System Programmer Response: Review the return codes from DYNALLOC and take appropriate actions.

U0810

Explanation: An error occurred processing a request from an OAM installation exit. The error is a result of processing in DFSMSrmm, not in the data passed to EDGLCSUX.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0811

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected Register 15 value on return from a subsystem request.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0812

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected Register 0 value on return from a subsystem request.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0813

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected return code from the DFSMSrmm common message routine.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Programmer Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0841

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected return code from the IDENTIFY macro.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0842

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected return code from the ATTACH macro.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0862

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected return code from the DETACH macro.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0879

Explanation: An error occurred processing a request from an OAM installation exit. The error is an unexpected return code from the STATUS macro.

Module: EDGLCSUX

System Action: Processing ends. The system writes a dump.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0901

Explanation: The message EDG9001E was not found in the DFSMSrmm message table. EDG9001E is required to issue information for an error in message processing. The number of the message that was issued at the time of the abend is in Register 0.

Module: EDGCMSG

System Action: The current message processing fails. Each DFSMSrmm task schedules error recovery processing that can involve stopping the subsystem if the error is severe.

Operator Response: Report this error to the system programmer.

System Programmer Response: This error is probably an error in EDGMTAB, the DFSMSrmm message table. Ensure that any updates to EDGMTAB have been made correctly.

U0950

Explanation: An attempt to issue a message by the DFSMSrmm subsystem failed because of an error in the message processing routine. The associated message is either EDG2050I or EDG2051I.

Module: EDGLOCV

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U0998

Explanation: An attempt to release control of the DFSMSrmm control data set failed. Previous error messages explain the error that was encountered.

System Action: The DFSMSrmm error recovery routines are run. The most probable result is that the DFSMSrmm subsystem will shut down until the error can be corrected.

Module: EDGMFIO

Operator Response: Report this error to the system programmer.

System Programmer Response: Correct the error and restart the DFSMSrmm subsystem. To correct the error, refer to the explanations and actions for the messages that have been issued.

U0999

Explanation: This code can be issued by both EDGVRECR and EDGDFHSM.

Explanation: When the code is issued by EDGVRECR, an error is encountered in issuing a message.

Module: EDGVRECR

System Action: The current VRSEL inventory management requests fails.

Programmer Response: Ensure that the EDGMTAB

message table is correctly installed. If EDGMTAB is correctly installed contact IBM for program support.

Operator Response: None.

Explanation: When the code is issued by EDGDFHSM, an unexpected return code was received in response to a DFSMSrmm subsystem request.

Module: EDGDFHSM

System Action: DFSMSrmm writes a dump and current processing fails.

Operator Response: Report this error to the system programmer.

Programmer Response: The volume being returned to DFSMSrmm from DFSMShsm might not have been correctly processed. If necessary, use the DFSMSrmm ISPF dialog or RMM TSO subcommand to correctly process information about the volume.

System Programmer Response: Report this error to the IBM Support Center.

U1000

Explanation: An error occurred in cross memory communication from the DFSMSrmm subsystem. DFSMSrmm could not issue a message because of an error in the DFSMSrmm message routine.

Module: EDGSXMC

System Action: Processing continues

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U10nn

Explanation: An error occurred in STACK processing while parsing parameters for a request to set up an outfile file for the terminal. *nn* in the completion code is the return code from IKJSTCK.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U1097

Explanation: An internal VSAM control block error was detected during DFSMSrmm VSAM buffer processing.

Module: EDGMVSM

System Action: The current request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Save any dumps written as a result of the abend. Report this error to the IBM Support Center. If the problem persists, restart the DFSMSrmm procedure to attempt recovery.

U11nn

Explanation: An error occurred in STACK processing while parsing parameters for a request to close all input and output files used during parsing. *nn* in the completion code is the return code from IKJSTCK.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U12nn

Explanation: An error occurred in STACK processing while parsing parameters when opening the PARMLIB member. *nn* in the completion code is the return code from IKJSTCK.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: If the DFSMSrmm parmlib data set is defined correctly, report this error to the IBM Support Center.

U13nn

Explanation: An error occurred in STACK processing while parsing parameters when opening the PARMLIB sequential file. *nn* in the completion code is the return code from IKJSTCK.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: If the DFSMSrmm parmlib data set is defined correctly, report this error to the IBM Support Center.

U14nn

Explanation: An error occurred in GETLINE processing while parsing parameters. *nn* in the completion code is the return code from GETLINE.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U15nn

Explanation: An error occurred in PUTLINE processing while parsing parameters. *nn* in the completion code is the return code from PUTLINE.

Module: EDGPARS

System Action: The current parse request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U1600

Explanation: DFSMSrmm is processing a call to the installation exit, EDGUX100. The volume currently being opened should not be controlled by DFSMSrmm. DFSMSrmm checks that the request is valid, but some part of the validity checking process fails.

Module: EDGIX100

System Action: The current open request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U1601

Explanation: DFSMSrmm is processing a call to the installation exit, EDGUX100. Prior to calling the installation exit, DFSMSrmm tries to retrieve existing information it has for the mounted or requested volume. The call to the module that retrieves the information fails.

Module: EDGIX100

System Action: The current open request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U1602

Explanation: DFSMSrmm is processing a call to the installation exit EDGUX100. Prior to calling the installation exit, DFSMSrmm attempts to retrieve existing information it has for the mounted or requested volume. The UCBSCAN macro it uses to find information in UCBs has failed.

Module: EDGBLDUX

System Action: The current request fails.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center. From the summary dump, have available the general purpose registers which are required for problem determination.

U2100

Explanation: Initialization must be performed prior to accessing the DFSMSrmm control data set.

Module: EDGMFIO

System Action: The request fails. The function being tried is indicated in the abend reason code.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U2101

Explanation: RACF tape-related security profiles could not be created, updated, or deleted as a result of an update to the DFSMSrmm control data set and the current settings for installation options. DFSMSrmm issues a message to identify the error.

Module: EDGMFIO

System Action: Processing ends. The abend reason code is the RACROUTE reason code.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U2130

Explanation: The DFSMSrmm subsystem could not issue a message because of an error in the message processing routine. The associated message is EDG2130I.

Module: EDGMFCNV

System Action: Processing ends.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U2200

Explanation: An unexpected return code was received while performing I/O to the control data set. The subtask is unable to continue processing. Message EDG2201E has been issued to give error information.

Module: EDGVRECI

System Action: DFSMSrmm detects the abend and requests an SVC dump. The current inventory management request fails.

Operator Response: Report this error to the system programmer.

Programmer Response: Follow the actions identified for EDG2201E.

System Programmer Response: If no other diagnostic information is available to resolve the problem, report this error to the IBM Support Center.

U2201

Explanation: An error is encountered in vital record processing. The error can be one of the following:

- The SORT program return code is greater than 0. DFSMSrmm also issues message EDG2220E to the MESSAGE file.
- Location and library name validation failed with a return code greater than 8. DFSMSrmm also issues message EDG2222E to the MESSAGE file.

System Action: The current VRSEL inventory management requests fails.

Module: EDGVRECM

Operator Response: None.

System Programmer Response: If the problem occurred performing a sort, correct the error that caused the SORT program to fail. Use the //SORTDIAG DD statement to trigger sort messages to the //SYSOUT file. These DD statements must be added to the DFRMM started procedure.

If the failure occurred during location and library name validation, follow the actions described for message EDG2222E. If the problem cannot be resolved by following the message actions report the problem to the IBM Support Center. Provide the system dump written as a result of the ABEND U2201.

U2220

Explanation: An error is encountered dynamically allocating a required file. DFSMSrmm issues message EDG2223E which contains the DYNALLOC return and reason code. Message EDG2223E is found in the message data set.

System Action: The current VRSEL inventory management requests fails.

Module: EDGVRECI

Programmer Response: Follow the actions identified for EDG2223E. For an explanation of the DYNALLOC codes, refer to *z/OS MVS Programming: Authorized Assembler Services Guide*.

Operator Response: None.

U2222

Explanation: An internal error occurred in DFSMSrmm.

System Action: The current requests fails.

Module: None.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U2410

Explanation: An unexpected return code was received while performing I/O to the control data set. The subtask is unable to continue processing.

Module: EDGMUPD

System Action: An explanatory message, EDG2440I, is issued. DFSMSrmm detects the abend and the system writes an SVC dump. Expiration processing and any other requested inventory management functions end.

Operator Response: Report this error to the system programmer.

System Programmer Response: If you are unable to resolve the problem using the available diagnostic information, report this error to the IBM Support Center.

U2420

Module: EDGMUPD

Explanation: An unexpected return code was received from the installation exit common processing routine.

System Action: DFSMSrmm detects the abend and writes an SVC dump. Expiration processing and any other requested inventory management functions end.

Operator Response: Report this error to the system programmer.

System Programmer Response: Report this error to the IBM Support Center.

U2430

Explanation: An unexpected return code was received performing a function for a volume in a volume catalog. The subtask is unable to continue processing.

Module: EDGMUPD

System Action: An explanatory message, number EDG2433I, is issued. DFSMSrmm detects the abend and writes an SVC dump. Expiration processing and any other requested inventory management functions end.

Operator Response: Report this error to the system programmer.

System Programmer Response: Refer to the actions for message EDG2433I.

U2440

Explanation: An unexpected return code was received while updating action status information for a volume in the DFSMSrmm control data set. The subtask is unable to continue processing.

Module: EDGMUPD

System Action: An explanatory message, one of EDG2430I, EDG2431I, or EDG2432I is issued. DFSMSrmm detects the abend and writes an SVC dump. Expiration processing and any other requested inventory management functions end.

Operator Response: Report this error to the system programmer.

System Programmer Response: Refer to the actions for any accompanying message. If reporting the problem to the IBM Support Center, have available the summary dump information.

U2450

Explanation: An unexpected return code was received while validating software level, location name for a volume, or obtaining volume information from the volume catalog. The subtask is unable to continue processing.

Module: EDGMUPD

System Action: An explanatory message, number EDG2441I, is issued. DFSMSrmm detects the abend and writes an SVC dump. Expiration processing and any other requested inventory management functions end.

Operator Response: Report this error to the system programmer.

System Programmer Response: Refer to the actions for message EDG2441I.

U3000

Explanation: A DFSMSrmm OPEN/CLOSE/EOV routine was invoked for an undetermined OPEN/CLOSE/EOV exit.

Module: EDGOCEXT or EDGOCEOV

System Action: Processing fails.

Operator Response: None

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3001

Explanation: A DFSMSrmm OPEN/CLOSE/EOV routine was invoked for an undetermined OPEN/CLOSE/EOV exit.

Module: EDGOCEOV

System Action: The current request fails.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3002

Explanation: DFSMSrmm returned an unsupported return code value to the module for label anomaly processing.

Module: EDGOCEOV

System Action: The current request fails.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3003

Explanation: DFSMSrmm returned an unsupported return code value to the module for file validation processing.

Module: EDGOCEOV

System Action: The current request fails.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3004

Explanation: An error occurred during O/C/EOV processing.

Module: EDGOCEOV

System Action: The current request fails.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3005

Explanation: DFSMSrmm does not support the request.

Module: EDGOCEOV

System Action: The current request fails.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

U3006

Explanation: DFSMSrmm issues a message but message processing fails. DFSMSrmm returns the return code and reason code from the message processing routine in register 2 and register 3.

Module: EDGOCEXT

System Action: DFSMSrmm writes a system dump and fails the current request.

Operator Response: None.

Programmer Response: Report this error to the system programmer.

System Programmer Response: A logic error occurred during OPEN/CLOSE/EOV processing. Report this error to the IBM Support Center.

Appendix E. Evaluating Removable Media Management Needs

Use the following list of questions to assess your current tape management practices and anticipate future requirements. You need your answers to these questions later, when you assess direct access storage device (DASD) needs for the control data set, journal, and report extract data set.

This same list of questions is in *z/OS DFSMS Migration*. Refer to that book if you used this list during the initial planning for DFSMSrmm.

If you plan to change anything about the removable media library, such as increasing the number of volumes, consider these changes when identifying your DASD needs.

Table 58. Evaluating Removable Media Management Needs

Task	Subtask
Determine the number of resources you have in your removable media library.	How many volumes do you have in your removable media library? A *volume* is any type of removable media, such as a tape cartridge or an optical disk. Add an average of five volumes in your count for each software product in your installation. How many shelf locations or slots do you maintain in your removable media library and in your storage locations? A *shelf location* is a single space on a shelf where you store a volume. Count all shelves in the library and in your storage locations. For DFSMSrmm subcommands and the ISPF dialog, shelf locations in the removable media library are called *rack numbers*. Shelf locations in storage locations are called *bin numbers*. How many data sets do you have on removable media? Count any data sets on your removable media. How many different individuals or groups use removable media? DFSMSrmm can keep track of owners and of removable media in the DFSMSrmm control data set.
Determine the number of requests submitted to your removable media library.	How many scratch tape mounts are performed daily? A *scratch* tape mount is a non-specific tape mount as, for example, when someone requests a blank tape. How many non-scratch tape mounts are performed daily? A *non-scratch* tape mount is a specific tape mount as, for example, when someone requests a tape he or she owns or a software product tape.
Determine the types of activities taking place in your media library.	What activities are performed to support disaster recovery and vital records management? How many volumes enter and leave your removable media library daily? This includes volumes moving to storage locations for disaster recovery and vital records, as well, as foreign tapes entering your library. How many volumes are returned to scratch daily? This number can be used to calculate the space required for the journal. How many volumes expire daily? This number can be used to calculate the space required for the journal. How many logical volumes are imported and exported daily? This number can be used to calculate the space required for the journal.

© Copyright IBM Corp. 1992, 2001

Table 58. Evaluating Removable Media Management Needs (continued)

Task	Subtask
Determine the number of information changes that might be made to DFSMSrmm information.	This number can be used to calculate the space required for the journal. Changes include information about data sets, owners, software products, or volumes made by using the DFSMSrmm TSO subcommands or DFSMSrmm ISPF dialog.

Appendix F. Problem Determination Aid Log Data Set Size Work Sheet for Long-Term Trace History

Use the following work sheet to calculate the size of your PDA log data set (long term).

1. Fill in the blanks with values for your installation.

```
________  =  ?UID          -  The high-level qualifier you want to
                             use for the PDA log data sets.
________  =  ?HOSTID       -  The identifier for the processing unit
                             at your site.
________  =  ?TRACEUNIT    -  The unit identifier for the device on
                             which you want to allocate the PDA log
                             data sets.
________  =  ?TRACEVOL     -  The serial number for the volume on
                             which you want to put your PDA log
                             data sets.
```

2. Allocate the minimum recommended storage for PDA log data sets: 20 cylinders.

   Substitute the values you have provided in step 1 of this work sheet, and run the JCL job shown in Figure 198 on page 345 to allocate and catalog the PDA log data sets.

   If you allocated these data sets as SMS-managed data sets, they must be allocated on a specific volume and they must be associated with a storage class having the GUARANTEED SPACE attribute.

3. Allocate a generation data group (GDG) in which you can archive your site's trace history data.

   The following example defines the generation data group (GDG) name for the archived problem determination output data set. Substitute the applicable values you provided in step 1 of this work sheet, and run the JCL job shown in Figure 199 on page 346 to create a generation data group.

4. Develop a procedure to automatically copy your PDA log data sets to tape.

   The following example shows you how to copy the inactive trace data set to tape as a generation data set (GDS). Substitute the applicable values you have provided in step 1 of this work sheet, and run the JCL job shown in Figure 200 on page 346 to automatically copy your PDA log data sets to tape.

© Copyright IBM Corp. 1992, 2001

Appendix G. Problem Determination Aid Log Data Set Size Work Sheet for Short-Term Trace History

Use the following work sheet to calculate the size of your PDA log data set (short term).

1. Fill in the following blanks with values for your installation.

```
________  =  ?tracehours   -  The number of hours of trace history
                             you want to retain.
________  =  ?UID          -  The high-level qualifier you want to
                             use for the PDA log data sets.
________  =  ?HOSTID       -  The identifier for the processing unit
                             at your site.
________  =  ?TRACEUNIT    -  The unit identifier for the device on
                             which you want to allocate the PDA log
                             data sets.
________  =  ?TRACEVOL     -  The serial number for the volume on
                             which you want to put your PDA log
                             data sets.
```

2. Allocate the minimum recommended storage for PDA log data sets which is 20 cylinders.

   Substitute the values you used in step 1 of this work sheet, and run the JCL job shown in Figure 210 to allocate and catalog the PDA log data sets.

```
//ALLOPDO JOB MSGLEVEL=1,TYPRUN=HOLD
//STEP1   EXEC PGM=IEFBR14
//DD1     DD DSN=?UID..?HOSTID..RMMPDOX,DISP=(,CATLG),
//           UNIT=?TRACEUNIT.,VOL=SER=?TRACEVOL.,SPACE=(CYL,(20))
//DD2     DD DSN=?UID..?HOSTID..RMMPDOY,DISP=(,CATLG),
//           UNIT=?TRACEUNIT.,VOL=SER=?TRACEVOL.,SPACE=(CYL,(20))
```

Figure 210. JCL for Allocating and Cataloging PDA Log Data Sets

   If you have allocated these data sets as SMS-managed, they must be allocated on a specific volume and they must be associated with a storage class having the GUARANTEED SPACE attribute.

3. Measure the cylinders per hour trace history generation rate at your site.

   After one hour of processing (during a time of high DFSMSrmm activity), measure the amount of storage used to record that hour's trace activity. Issue the following MODIFY command to swap the EDGPDOX and EDGPDOY data sets. After you have swapped these data sets, the EDGPDOY data set will be ready to measure and the EDGPDOX data set will be ready to receive additional trace data.

```
F DFRMM,PDALOG=SWAP
```

   Use the information gathered in this step to calculate the cylinders per hour.

```
Cylinders/hr = cylinders per hour of trace history
```

4. Calculate the total amount of cylinders required for your site's trace history data.

```
((tracehours = ________) x (cylinders/hr = ________))  =  ________

  Total = total number of cylinders of trace data
```

5. Divide in half the total cylinders required for your short-term trace history interval. If the result is a fraction, round up to the next whole number.

© Copyright IBM Corp. 1992, 2001

```
(Total =       )      =  _______
---------------
       2
```

This step provides the total number of cylinders to allocate for each data set.

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:
INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Information Enabling Requests
Dept. DZWA

© Copyright IBM Corp. 1992, 2001

5600 Cottle Road
San Jose, CA 95193 U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Programming Interface Information

This publication documents intended Programming Interfaces that allow the customer to write programs to obtain the services of DFSMSrmm.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States, or other countries, or both:

DFSMSdfp
DFSMSdss
DFSMShsm
DFSMSrmm
DFSMS/MVS
DFSORT
IBM
MVS
NetView
OS/390
RACF
SecureWay
z/OS

Tivoli and Tivoli OPC are trademarks of Tivoli Systems Inc. in the United States and/or other countries.

Other company, product, and service names may be trademarks or service marks of others.

Glossary

This glossary defines technical terms and abbreviations used in DFSMS documentation. If you do not find the term you are looking for, refer to the index of the appropriate DFSMS manual or view the *IBM Dictionary of Computing* located at:

http://www.ibm.com/networking/nsg/nsgmain.htm

This glossary includes terms and definitions from:

- The *American National Standard Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42nd Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.
- The *Information Technology Vocabulary* developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Commission (ISO/IEC JTC1/SC1). Definitions of published part of this vocabulary are identified by the symbol (I) after the definition; definitions taken from draft international standards, committee drafts, and working papers being developed by ISO/IEC JTC1/SC1 are identified by the symbol (T) after the definition, indicating that final agreement has not yet been reached among the participating National Bodies of SC1.
- The *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

The following cross-reference is used in this glossary:

See: This refers the reader to (a) a related term, (b) a term that is the expanded form of an abbreviation or acronym, or (c) a synonym or more preferred term.

A

abend. Abnormal end of task

AL. American National Standards Label

AMODE. Addressing mode

ANDVRS. An RMM ADDVRS TSO subcommand operand. See *Using AND*.

ANSI. American National Standards Institute

APAR. Authorized program analysis report

API. Application Programming interface

ASA. American Standards Association

assigned date. The date that the volume is assigned to the current owner. Assigned date is not meaningful for a scratch volume.

AUL. ANSI and user header or trailer label

automated tape library. A device consisting of robotic components, cartridge storage areas, tape subsystems, and controlling hardware and software, together with the set of tape volumes that reside in the library and can be mounted on the library tape drives. Contrast with *manual tape library*. See also *manual tape library or tape library*.

automatic cartridge loader. An optional feature of the 3480 Magnetic Tape Subsystem that allows preloading of multiple tape cartridges. This feature is standard in the 3490 Magnetic Tape Subsystem.

automatic recording. In DFSMSrmm, the process of recording information about a volume and the data sets on the volume in the DFSMSrmm control data set at open or close time.

availability. For a storage subsystem, the degree to which a data set or object can be accessed when requested by a user.

B

backup. The process of creating a copy of a data set or object to be used in case of accidental loss.

basic catalog structure (BCS). The name of the catalog structure in the integrated catalog facility environment. See also *integrated catalog facility catalog*.

BCS. See *basic catalog structure*.

bin number. The specific shelf location where a volume resides in a storage location; equivalent to a rack number in the removable media library. See also *shelf location*.

BLP. Bypass label processing

BTLS. Basic Tape Library Support

built-in storage location. One of the Removable Media Manager defined storage locations: LOCAL, DISTANT, and REMOTE.

© Copyright IBM Corp. 1992, 2001

C

cache fast write. A storage control capability in which the data is written directly to cache without using nonvolatile storage. Cache fast write is useful for temporary data or data that is readily recreated, such as the sort work files created by DFSORT. Contrast with *DASD fast write*.

cartridge eject. For an IBM 3494 Tape Library Dataserver, IBM 3495 Tape Library Dataserver, or a manual tape library, the act of physically removing a tape cartridge usually under robot control, by placing it in an output station. The software logically removes the cartridge by deleting or updating the tape volume record in the tape configuration database. For a manual tape library, the act of logically removing a tape cartridge from the manual tape library by deleting or updating the tape volume record in the tape configuration database.

cartridge entry. For either an IBM 3494 Tape Library Dataserver, IBM 3495 Tape Library Dataserver, or a manual tape library, the process of logically adding a tape cartridge to the library by creating or updating the tape volume record in the tape configuration database. The cartridge entry process includes the assignment of the cartridge to scratch or private category in the library.

Cartridge System Tape. The base tape cartridge media used with 3480 or 3490 Magnetic Tape Subsystems. Contrast with *Enhanced Capacity Cartridge System Tape*.

cell. A single cartridge location within an automated tape library dataserver. See also *rack number*.

circular file. A type of file that appends data until full. Then, starting at the beginning of the file, subsequent incoming data overwrites the data already there.

command line. On a display screen, a display line usually at the bottom of the screen in which only commands can be entered.

concurrent copy. A function to increase the accessibility of data by enabling you to make a consistent backup or copy of data concurrent with the usual application program processing.

confirmation panel. A DFSMSrmm panel that lets you tell DFSMSrmm to continue or stop a delete or release action. You specify whether or not you want to confirm delete or release requests in your dialog user options.

container. A receptacle in which one or more exported logical volumes can be stored. A stacked volume containing one or more logical volumes and residing outside a virtual tape server library is considered to be the container for those volumes.

container volume. See *container*.

control data set. A VSAM key-sequenced data set that contains the complete inventory of your removable media library, as well as the movement and retention policies you define. In the control data set DFSMSrmm records all changes made to the inventory, such as adding or deleting volumes.

control data set ID. A one-to-eight character identifier for the DFSMSrmm control data set used to ensure that, in a multi-system, multi-complex environment, the correct management functions are performed.

convenience input. The process of adding a small number of tape cartridges to the IBM 3494 Tape Library Dataserver and IBM 3495 Tape Library Dataserver without interrupting operations, by inserting the cartridges directly into cells in a convenience input station.

convenience input/output station. A transfer station with combined tape cartridge input and output functions in the IBM 3494 Tape Library Dataservers only.

convenience input station. A transfer station, used by the operator to add tape cartridges to the IBM 3494 Tape Library Dataserver or an IBM 3495 Tape Library Dataserver, which is accessible from outside the enclosure area.

convenience output. The process of removing a small number of tape cartridges from the IBM 3494 Tape Library Dataserver or an IBM 3495 Tape Library Dataserver without interrupting operations, by removing the cartridges directly from cells in a convenience input station.

convenience output station. A transfer station, used by the operator to remove tape cartridges from the automated tape library dataserver, which is accessible from outside the enclosure area.

conversion. In DFSMSrmm, the process of moving your removable media library inventory from another media management system to DFSMSrmm. DFSMSrmm manages the inventory and policies once you have converted it.

create date. Create date for a dataset is the date that the dataset is written to tape. Create date can also be the date a data set was read if it was created before DFSMSrmm is in use. Create date is updated each time a data set is replaced and not extended. Create date for volumes and other resources defined to DFSMSrmm is the date the resource is defined to DFSMSrmm or the date specified on the command as the create date.

D

DASD. Direct access storage device

DASD fast write. An extended function of some models of the IBM 3990 Storage Control in which data

is written concurrently to cache and nonvolatile storage and automatically scheduled for destaging to DASD. Both copies are retained in the storage control until the data is completely written to the DASD, providing data integrity equivalent to writing directly to the DASD. Use of DASD fast write for system-managed data sets is controlled by storage class attributes to improve performance. See also *dynamic cache management*. Contrast with *cache fast write*.

DASD volume. A DASD space identified by a common label and accessed by a set of related addresses. See also *volume*, *primary storage*, *migration level 1*, *migration level 2*.

data column. A vertical arrangement of identical data items, used on list panels to display an attribute, characteristic, or value of one or more objects.

data control block (DCB). A control block used by access method routines in storing and retrieving data.

data entry panel. A panel in which the user communicates with the system by filling in one or more fields.

Data Facility Storage Management Subsystem (DFSMS). An operating environment that helps automate and centralize the management of storage. To manage storage, SMS provides the storage administrator with control over data class, storage class, management class, storage group, and automatic class selection routine definitions.

Data Facility Sort. An IBM licensed program that is a high-speed data processing utility. DFSORT provides an efficient and flexible way to handle sorting, merging, and copying operations, as well as providing versatile data manipulation at the record, field, and bit level.

DCB. See *data control block*.

device. This term is used interchangeably with unit. You mount a tape on a unit or device, such as a 3490.

DFSMSdfp. A DFSMS functional component or base element of z/OS, that provides functions for storage management, data management, program management, device management, and distributed data access.

DFSMSdss. A DFSMS functional component or base element of z/OS, used to copy, move, dump, and restore data sets and volumes.

DFSMShsm. A DFSMS functional component or base element of z/OS, used for backing up and recovering data, and managing space on volumes in the storage hierarchy.

DFSMShsm-managed volume. (1) A primary storage volume, which is defined to DFSMShsm but which does not belong to a storage group. (2) A volume in a storage group, which is using DFSMShsm automatic dump, migration, or backup services. Contrast with *system-managed volume* and *DFSMSrmm-managed volume*.

DFSMShsm-owned volume. A storage volume on which DFSMShsm stores backup versions, dump copies, or migrated data sets.

DFSMSrmm. A DFSMS functional component or base element of z/OS, that manages removable media.

DFSMSrmm control data set. See *control data set*.

DFSMSrmm-managed volume. A tape volume that is defined to DFSMSrmm. Contrast with *system-managed volume* and *DFSMShsm-managed volume*.

disaster recovery. A procedure for copying and storing an installation's essential business data in a secure location, and for recovering that data in the event of a catastrophic problem. Compare with *vital records*.

DISTANT. A DFSMSrmm built-in storage location ID. See *built-in storage location*.

dual copy. A high availability function made possible by nonvolatile storage in some models of the IBM 3990 Storage Control. Dual copy maintains two functionally identical copies of designated DASD volumes in the logical 3990 subsystem, and automatically updates both copies every time a write operation is issued to the dual copy logical volume.

dump class. A set of characteristics that describes how volume dumps are managed by DFSMShsm.

duplexing. The process of writing two sets of identical records in order to create a second copy of data.

dynamic cache management. A function that automatically determines which data sets will be cached based on the 3990 subsystem load, the characteristics of the data set, and the performance requirements defined by the storage administrator.

E

EHPCT. Extended High Performance Cartridge Tape

eject. The process used to remove a volume from a system-managed library. For an automated tape library dataserver, the volume is removed from its cell location and moved to the output station. For a manual tape library, the volume is not moved, but the tape configuration database is updated to show the volume no longer resides in the manual tape library.

Enhanced Capacity Cartridge System Tape. Cartridge system tape with increased capacity that can only be used with 3490E Magnetic Tape Subsystems. Contrast with *Cartridge System Tape*.

entry panel. See *data entry panel*.

EREP. Environmental Record Editing and Printing program

expanded output. Expanded output occurs when you specify OUTPUT=FIELDS and EXPAND=YES. For those subcommands for which expanded output applies, your application program receives more variable data than for standard output.

expiration. The process by which data sets and volumes are identified as available for reuse. In DFSMSrmm, all volumes have an expiration date or retention period set for them either by vital record specification policy, by user-specified JCL when writing a data set to the volume, or by an installation default. When a volume reaches its expiration date or retention period, it becomes eligible for release.

expiration date. The date at which a file is no longer protected against automatic deletion by the system.

expiration processing. The process of inventory management that ensures expired volumes are released and carries out required release actions on those volumes.

export. The operation to remove one or more logical volumes from a virtual tape server library. First, the list of logical volumes to export must be written on an export list volume and then, the export operation itself must be initiated.

exported logical volume. A logical volume that has gone through the export process and now resides on a stacked volume outside a virtual tape server library.

export list volume. A virtual tape server logical volume containing the list of logical volumes to export.

external label. A label attached to the outside of a tape cartridge that is to be stored in an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver. The label might contain the DFSMSrmm rack number of the tape volume.

extract data set. A data set that you use to generate reports.

F

field format. Field format is where the output consists of Structured Field Introducers and variable data rather than output in line format.

filtering. The process of selecting data sets based on specified criteria. These criteria consist of fully or partially-qualified data set names or of certain data set characteristics.

FIPS. Federal Information Processing Standard

FMID. Function modification identifier

FRR. Functional recovery routines

G

generation data group (GDG). A collection of data sets kept in chronological order. Each data set is a generation data set.

generation data set. One generation of a generation data group.

generation number. The number of a generation within a generation data group. A zero represents the most current generation of the group, a negative integer (-1) represents an older generation and, a positive integer (+1) represents a new generation that has not yet been cataloged.

GDG. See *generation data group*.

GDS. See *generation data set*.

giga (G). The information-industry meaning depends upon the context:

1. G = 1,073,741,824(2^{30}) for real and virtual storage
2. G = 1,000,000,000 for disk storage capacity (e.g., 4 Gb fixed disk)
3. G = 1,000,000,000 for transmission rates

GPR. General purpose register

GRS. Global resource serialization

guaranteed space. A storage class attribute indicating the space is to be preallocated when a data set is created. If you specify explicit volume serial numbers, SMS honors them. If space to satisfy the allocation is not available on the user-specified volumes, the allocation fails.

H

hardware configuration definition (HCD). An interactive interface in MVS that enables an installation to define hardware configurations from a single point of control.

HCD. See *hardware configuration definition.*.

high capacity input station. A transfer station, used by the operator to add tape cartridges to the IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver, which is inside the enclosure area.

high capacity output station. A transfer station, used by the operator to remove tape cartridges from the automated tape library dataserver, which is inside the enclosure area.

home. See *home location*.

home location. For DFSMSrmm, the place where DFSMSrmm normally returns a volume when the volume is no longer retained by vital records processing.

HPCT. High Performance Cartridge Tape

I

ICETOOL. DFSORT's multipurpose data processing and reporting utility.

ID. Identifier

IDRC. See *improved data recording capability*.

import. The operation to enter previously exported logical volumes residing on a stacked volume into a virtual tape server library. First, the list of logical volumes to import must be written on an import list volume and the stacked volumes must be entered, and then, the import operation itself must be initiated.

import list volume. A virtual tape server logical volume containing the list of logical volumes to import. This list can contain individual logical volumes to import and/or it can contain a list of stacked volumes in which all logical volumes on the stacked volume are imported.

imported logical volume. An exported logical volume that has gone through the import process and can be referenced as a tape volume within a virtual tape server library. An imported logical volume originates from a stacked volume that went through the export process.

improved data recording capability (IDRC). A recording mode that can increase the effective cartridge data capacity and the effective data rate when enabled and used. IDRC is always enabled on the 3490E Magnetic Tape Subsystem.

installation defined storage location. A storage location defined using the LOCDEF command in the EDGRMMxx parmlib member.

integrated catalog facility catalog. A catalog that is composed of a basic catalog structure (BCS) and its related volume tables of contents (VTOCs) and VSAM volume data sets (VVDSs). See also *basic catalog structure* and *VSAM volume data set*.

Interactive Storage Management Facility (ISMF). The interactive interface of DFSMS that allows users and storage administrators access to the storage management functions.

Interactive Problem Control System (IPCS). A system facility that allows interactive problem analysis.

Interactive System Productivity Facility (ISPF). An IBM licensed program used to develop, test, and run interactive, panel-driven dialogs.

internal label. The internal label for standard label tapes is recorded in the VOL1 header label, magnetically recorded on the tape media.

in transit. A volume is in transit when it must be moved from one location to another and DFSMSrmm believes that the move has started, but has not yet received confirmation that the move is complete. For a volume moving from a system-managed library, the move starts when the volume is ejected.

inventory management. The regular tasks that need to be performed to maintain the control data set. See also *expiration processing*, *storage location management processing*, and *vital record processing*.

IPCS. See *Interactive Problem Control System*.

IPL. Initial program load.

ISPF. See *Interactive System Productivity Facility*.

ISMF. See *Interactive Storage Management Facility*.

ISO. See *International Organization for Standardization*.

J

JCL. Job control language

JES2. Job entry subsystem 2

JES3. Job entry subsystem 3

JFCB. Job file control block

journal. A sequential data set that contains a chronological record of changes made to the DFSMSrmm control data set. You use the journal when you need to reconstruct the DFSMSrmm control data set.

K

keyword. A predefined word that is used as an identifier.

kilo (K). The information-industry meaning depends upon the context:

1. K = 1024(2^{10}) for real and virtual storage
2. K = 1000 for disk storage capacity (e.g., 4 KB fixed disk)
3. K = 1000 for transmission rates

L

Library Control System. The Object Access Method component that controls optical and tape library operations and maintains configuration information.

Line Format. Line format is where text and variable data are formatted into lines suitable for displaying at a terminal or printing on hardcopy output.

LOCAL. A DFSMSrmm built-in storage location ID. See *built-in storage location*.

location name. A name given to a place for removable media that DFSMSrmm manages. A location name can be the name of a system-managed library, a storage location name, or the location *SHELF*, identifying shelf space outside a system-managed library or storage locations.

logical volume. Logical volumes have a many-to-one association with physical tape media and are used indirectly by MVS applications. They reside in a Virtual Tape Server or on exported stacked volumes. Applications can access the data on these volumes only when they reside in a Virtual Tape Server, which makes the data available via its tape volume cache or after the data has been copied to a physical volume through the use of special utilities.

low-on-scratch management. The process by which DFSMSrmm replenishes scratch volumes in a system-managed library when it detects that there are not enough available scratch volumes.

M

management class. A collection of management attributes that are defined by the storage administrator, used to control the release of allocated but unused space: to control the retention, migration, and backup of data sets: to control the retention and backup of aggregate groups, and to control the retention, backup, and class transition of objects. If assigned by ACS routine to system-managed tape volumes, it can be used to identify a DFSMSrmm vital record specification.

manual cartridge entry processing. The process by which a volume is added to the tape configuration database when it is added to a manual tape library. DFSMSrmm can initiate this process.

manual mode. An operational mode where DFSMSrmm runs without recording volume usage or validating volumes. The DFSMSrmm TSO commands, ISPF dialog, and inventory management functions are all available in manual mode.

manual tape library. An installation-defined set of stand-alone tape drives and the set of tape volumes that can be mounted on those drives.

master system. The MVS system where the master DFSMSrmm control data set resides.

master volume. A private volume that contains data that is available for write processing based on the DFSMSrmm EDGRMMxx parmlib MASTEROVERWRITE operand.

media format. The type of volume, recording format and techniques used to create the data on the volume.

media library. See *removable media library*.

media management system. A program that helps you manage removable media. DFSMSrmm is a media management system.

media name. An up to 8 character value that describes the shape or type of removable media stored in a storage location. Examples of media name are: SQUARE, ROUND, CARTRDGE, 3480

media type. A value that specifies the volume's media type. Media type can be specified as: *, CST, ECCST, HPCT, or EHPCT.

MEDIA 1. cartridge system tape

MEDIA 2. enhanced capacity cartridge system tape

MEDIA 3. high performance cartridge tape

MEDIA 4. extended high performance cartridge tape

mega (M). The information-industry meaning depends upon the context:

1. M = 1,048,576(2^{20}) for real and virtual storage
2. M = 1,000,000 for disk storage capacity (e.g., 4 MB fixed disk)
3. M = 1,000,000 for transmission rates

migration. The process of moving unused data to lower cost storage in order to make space for high-availability data. If you wish to use the data set, it must be recalled. See also *migration level 1* and migration level 2.

migration level 1. DFSMShsm-owned DASD volumes that contain data sets migrated from primary storage volumes. The data can be compressed. See also *storage hierarchy*. Contrast with *primary storage* and *migration level 2*.

migration level 2. DFSMShsm-owned tape or DASD volumes that contain data sets migrated from primary storage volumes or from migration level 1 volumes. The data can be compressed. See also *storage hierarchy*. Contrast with *primary storage* and *migration level 1*.

MVS image. A single occurrence of the MVS/ESA operating system that has the ability to process work.

N

name vital record specification. A vital record specification used to define additional retention and movement policy information for data sets or volumes.

NEXTVRS. An RMM ADDVRS TSO subcommand operand. See *Using Next*.

NL. No label

non-scratch volume. A volume that is not scratch, which means it has valid or unexpired data on it. Contrast with *scratch*.

NSL. Nonstandard label

O

OAM. See *object access method*.

object. A named byte stream having no specific format or record orientation.

object access method (OAM). An access method that provides storage, retrieval, and storage hierarchy management for objects and provides storage and retrieval management for tape volumes contained in system-managed libraries.

OPC/ESA. Operations Planning and Control/Enterprise Systems Architecture

optical volume. Storage space on an optical disk, identified by a volume label. See also *volume*.

optical disk. A disk that uses laser technology for data storage and retrieval.

option line. See *command line*

owner. In DFSMSrmm, a person or group of persons defined as a DFSMSrmm user owning volumes. An owner is defined to DFSMSrmm through an owner ID.

owner ID. In DFSMSrmm, an identifier for DFSMSrmm users who own volumes.

P

parallel. During conversion, when you install DFSMSrmm concurrently with an existing media management system, it is called running in parallel.

partitioned data set (PDS). A data set on direct access storage that is divided into partitions, called members, each of which can contain a program, part of a program, or data.

permanent data set. A user-named data set that is normally retained for longer than the duration of a job or interactive session. Contrast with *temporary data set*.

PF. Program function key

physical stacked volume. See *stacked volume*.

physical volume. Physical volumes have a one-to-one association with physical tape media and are used directly by MVS applications. They may reside in an automated tape library dataserver or be kept on shelf storage either at vault sites or within the data center where they can be mounted on stand-alone tape drives.

pool. A group of shelf locations in the removable media library whose rack numbers share a common prefix. The shelf locations are logically grouped so that the volumes stored there are easier to find and use.

pool ID. The identifier for a pool. You define pool IDs in parmlib member EDGRMMxx.

pooling. The process of arranging shelf locations in the removable media library into logical groups.

pool storage group. A type of storage group that contains system-managed DASD volumes. Pool storage groups allow groups of volumes to be managed as a single entity. See also *storage group*.

primary space allocation. Amount of space requested by a user for a data set when it is created. Contrast with *secondary space allocation*.

primary storage. A DASD volume available to users for data allocation. The volumes in primary storage are called primary volumes. See also *storage hierarchy*. Contrast with *migration level 1* and *migration level 2.*

primary vital record specification. The first retention and movement policy that DFSMSrmm matches to a data set and volume used for disaster recovery and vital record purposes. See also vital record specification and secondary vital record specification.

private tape volume. A volume assigned to specific individuals or functions.

protect mode. In protect mode, DFSMSrmm validates all volume requests.

pseudo-generation data group. A collection of data sets, using the same data set name pattern, to be managed like a generation data group. The ¬ masking character is used in DFSMSrmm to identify the characters in the pattern that change with each generation.

PSW. Program status word

PTF. Program temporary fix

pull list. A list of scratch volumes to be pulled from the library for use.

PUT. Program update tape

R

RACF. Resource Access Control Facility

rack number. A six-character identifier that corresponds to a specific volume's shelf location in the installation's removable media library, and is the identifier used on the external label of the volume to identify it. The rack number identifies the pool and the external volume serial number for a volume residing in an automated tape library dataserver. The rack number identifies the pool, the external volume serial, and shelf location number for a volume not residing in an automated tape library dataserver. The rack number is not written by the tape drive. It exists as an entry in the DFSMSrmm control data set and on the external label of the tape. See also *shelf location*

rack pool. A group of shelves that contains volumes that are generally read-only.

ready to scratch. This describes the condition where a volume is eligible for scratch processing while it resides in a storage location. Since no other release actions are required, the volume can be returned to scratch directly from the storage location.

recording format. For a tape volume, the format of the data on the tape; for example, 18 tracks or 36 tracks.

record-only mode. The operating mode where DFSMSrmm records information about volumes as you use them, but does not validate or reject volumes.

recovery. The process of rebuilding data after it has been damaged or destroyed, often by using a backup copy of the data or by reapplying transactions recorded in a journal.

relative start generation. Relative generation zero is the latest generation of a tape; Relative generation -1 is the previous generation of that tape. Relative generation -2 is the generation before the previous one.

REMOTE. A DFSMSrmm built-in storage location ID. See *built-in storage location*.

removable media. See *volume*.

removable media library. The volumes that are available for immediate use, and the shelves where they could reside.

Resource Access Control Facility (RACF). An IBM licensed program that provides for access control by identifying and verifying the users to the system; authorizing access to protected resources; logging the detected unauthorized attempts to enter the system; and logging the detected accesses to protected resources.

Resource Group. A collection of structured fields that describe the attributes of a resource such as a volume.

Restructured Extended Executor (REXX) Language. A general-purpose, high-level programming language, particularly suitable for EXEC procedures or programs for personal computing.

retention date. Retention date can be the date that a data set or volume is retained by a vital record specification or the date of the inventory management run when the data set or volume is no longer retained by a vital record specification.

retention period. The time for which DFSMSrmm retains a volume or data set before considering it for release. You can retain a data set or volume as part of disaster recovery or vital records management. You set a retention period through a vital record specification that overrides a data set's expiration date.

retention type. The types of retention for which DFSMSrmm retains a volume or data set before considering it for release. The retention types for data sets are BYDAYSCYCLE, CYCLES, DAYS, EXTRADAYS, LASTREFERENCEDAYS, UNTILEXPIRED, and WHILECATALOG. The retention types for volumes are DAYS and CYCLE.

REXX. Restructured Extended Executor Language

RMF. Resource Measurement Facility

RMM complex (RMMplex). One or more MVS images that share a common DFSMSrmm control data set.

RMODE. Residence mode

S

SAF. System Authorization Facility

scratch. The status of a tape volume that is available for general use, because the data on it is incorrect or is no longer needed. You request a scratch volume when you omit the volume serial number on a request for a tape volume mount.

scratch pool. The collection of tape volumes from which requests for scratch tapes can be satisfied. Contrast with *rack pool*.

scratch processing. The process for returning a volume to scratch status once it is no longer in use and has no outstanding release actions pending.

scratch tape. See *scratch volume*.

scratch volume. A tape volume that contains expired data only. See *scratch*.

SDB. Structured database

SDSF. Spool display and search facility

secondary space allocation. Amount of additional space requested by the user for a data set when primary space is full. Contrast with *primary space allocation*.

secondary vital record specification. The second retention and movement policy that DFSMSrmm matches to a data set and volume used for disaster recovery and vital records purposes. See also vital record specification and primary vital record specification.

SFI. See *structured field introducer*.

shelf. A place for storing removable media, such as tape and optical volumes, when they are not being written to or read.

shelf location. A single space on a shelf for storage of removable media. DFSMSrmm defines a shelf location in the removable media library by a rack number, and a shelf location in a storage location by a bin number. See also *rack number* and *bin number*

shelf-management. Is the function provided to manage the placement of volumes in individual slots in a location. Shelf-management is provided for the removable media library using rack numbers. For storage locations it is optional as defined by the LOCDEF options in parmlib and uses bin numbers.

shelf-resident volume. A volume that resides in a non-system-managed tape library.

shelf space. See *shelf*.

SL. Standard label

slot. See *shelf location*.

SMF. System management facility

SMP/E. System Modification Program Extended

stacked volume. Stacked volumes have a one-to-one association with physical tape media and are used in a Virtual Tape Server to store logical volumes. Stacked volumes are not used by MVS applications but by the Virtual Tape Server and its associated utilities. They may be removed from a Virtual Tape Server to allow transportation of logical volumes to a vault or to another Virtual Tape Server.

standard label. An IBM standard tape label.

Standard output. Standard output is the amount of variable data displayed, printed or put into a REXX variable in response to a subcommand. When you specify OUTPUT=LINES or EXPAND=NO with OUTPUT=FIELDS, your application program receives standard output as opposed to expanded output.

storage administrator. A person in the data processing center who is responsible for defining, implementing, and maintaining storage management policies.

storage class. A collection of storage attributes that identify performance goals and availability requirements, defined by the storage administrator, used to select a device that can meet those goals and requirements.

storage group. A collection of storage volumes and attributes, defined by the storage administrator. The collections can be a group of DASD volumes or tape volumes, or a group of DASD volumes and optical volumes treated as a single object storage hierarchy.

storage location. A location physically separate from the removable media library where volumes are stored for disaster recovery, backup, and vital records management.

(storage) location dominance. The priority used by DFSMSrmm to decide where to move a volume within the removable media library during vital record specification processing. It covers all the locations; SHELF, storage locations, and system-managed tape libraries.

storage location management processing. The process of inventory management that assigns a shelf location to volumes that have moved as a result of vital record processing. See also *vital record processing*

stripe. In DFSMS, the portion of a striped data set that resides on one volume. The records in that portion are not always logically consecutive. The system distributes records among the stripes such that the volumes can be read from or written to simultaneously to gain better performance. Whether it is striped is not apparent to the application program.

striping. A software implementation of a disk array that distributes a data set across multiple volumes to improve performance.

structured field. Output from the DFSMSrmm application programming interface consisting of a Structured Field Introducer and output data.

structured field introducer (SFI). An 8-byte entity that either introduces the beginning of a group of data or introduces output data that immediately follows the introducer.

subsystem. A special MVS task that provides services and functions to other MVS users. Requests for service are made to the subsystem through a standard MVS facility known as the subsystem interface (SSI). Standard MVS subsystems are the master subsystem and the job entry subsystems JES2 and JES3.

subsystem interface (SSI). The means by which system routines request services of the master

subsystem, a job entry subsystem, or other subsystems defined to the subsystem interface.

SUL. IBM standard and user header or trailer label

SVC. Supervisor call

system-managed storage. Storage managed by the Storage Management Subsystem. SMS attempts to deliver required services for availability, performance, and space to applications. See also *system-managed storage environment*.

system-managed storage environment. An environment that helps automate and centralize the management of storage. This is achieved through a combination of hardware, software, and policies. In the system-managed storage environment for z/OS, the function is provided by DFSORT, RACF, and the combination of DFSMS and z/OS.

system-managed tape library. A collection of tape volumes and tape devices, defined in the tape configuration database. A system-managed tape library can be automated or manual. See also *tape library.*

system-managed volume. A DASD, optical, or tape volume that belongs to a storage group. Contrast with *DFSMShsm-managed volume* and *DFSMSrmm-managed volume*.

system programmer. A programmer who plans, generates, maintains, extends, and controls the use of an operating system and applications with the aim of improving overall productivity of an installation.

T

tape configuration database (TCDB). One or more volume catalogs used to maintain records of system-managed tape libraries and tape volumes.

tape librarian. The person who manages the tape library. This person is a specialized storage administrator.

tape library. A set of equipment and facilities that support an installation's tape environment. This can include tape storage racks, a set of tape drives, and a set of related tape volumes mounted on those drives. See also *system-managed tape library* and *automated tape library*.

Tape Library Control System (TLCS). IBM program offering 5785-EAW. DFSMSrmm replaces TLCS.

Tape Library Dataserver. A hardware device that maintains the tape inventory associated with a set of tape drives. An automated tape library dataserver also manages the mounting, removal, and storage of tapes. An automated tape library dataserver that supports system-managed storage of tape volumes. IBM's automated tape library dataservers include the IBM 3494 Tape Library Dataserver and the IBM 3495 Tape Library Dataserver.

tape storage group. A type of storage group that contains system-managed private tape volumes. The tape storage group definition specifies the system-managed tape libraries that can contain tape volumes. See also *storage group*.

tape subsystem. A magnetic tape subsystem consisting of a controller and devices, which allows for the storage of user data on tape cartridges. Examples of tape subsystems include the IBM 3490 and 3490E Magnetic Tape Subsystems.

tape volume. A tape volume is the recording space on a single tape cartridge or reel. See also *volume*.

TCDB. See *tape configuration database*.

temporary data set. An uncataloged data set whose name begins with & or &&, that is normally used only for the duration of a job or interactive session. Contrast with *permanent data set*.

tera (T). The information-industry meaning depends upon the context:

1. T = 1,099,511,627,776(2^{40}) for real and virtual storage
2. T = 1,000,000,000,000 for disk storage capacity (e.g., 4 TB of DASD storage)
3. T = 1,000,000,000,000 for transmission rates

TLCS. See *Tape Library Control System*.

TSO. Time Sharing Option

U

Until Expired. Allows the use of vital record specification policies for managing retention in a location as long as the volume expiration date has not been reached.

use attribute. (1) The attribute assigned to a DAD volume that controls when the volume can be used to allocate new data sets; use attributes are *public*, *private*, and *storage*. (2) For system-managed tape volumes, use attributes are *scratch* and *private*.

user volume. A volume assigned to a user, that can contain any data and can be rewritten as many times as the user wishes until the volume expires.

using AND. A method for linking DFSMSrmm vital record specifications to create chains of vital record specifications. DFSMSrmm applies policies in chains using AND only when all the retention criteria are true.

using NEXT. A method for linking DFSMSrmm vital record specifications to create chains of vital record

specifications. DFSMSrmm applies policies in chains using NEXT one vital record at a time.

V

virtual export. Mark a volume as exported by using the DFSMSrmm subcommands.

virtual input/output (VIO) storage group. A type of storage group that allocates data sets to paging storage, which simulates a DASD volume. VIO storage groups do not contain any actual DASD volumes. See also *storage group*.

Virtual Tape Server (VTS). This subsystem, integrated into the Magstar 3494 Tape Library, combines the random access and high performance characteristics of DASD with outboard hierarchical storage management and virtual tape devices and tape volumes.

vital record group. A set of data sets with the same name that matches to the same DFSMSrmm vital record specification

vital record processing. The process of inventory management that determines which data sets and volumes DFSMSrmm should retain and whether a volume needs to move. These volumes and data sets have been assigned a vital record specification.

vital records. A data set or volume maintained for meeting an externally-imposed retention requirement, such as a legal requirement. Compare with *disaster recovery*.

vital record specification. Policies defined to manage the retention and movement of data sets and volumes used for disaster recovery and vital records purposes.

vital record specification management value. A one-to-eight character name defined by your installation and used to assign management and retention values to tape data sets. The vital record management value can be any value you chose to create a match between a vital record specification and data sets and volumes in your installation. By matching the vital record specifications to the data set or volumes, DFSMSrmm applies the retention and movement policies you define in the vital record specifications. During inventory management VRSEL processing, DFSMSrmm selects the correct, best matching vital record specification for a tape data set or volume.

VOLSER. See *volume serial number*.

volume. The storage space on DASD, tape, or optical devices, which is identified by a volume label. See also *DASD volume*, *logical volume*, *optical volume*, *stacked volume*, and *tape volume*.

volume catalog. See *tape configuration database*.

volume expiration date. The date the volume should expire based on the highest expiration date of the data sets that reside on the volume.

volume serial number (VOLSER). An identification number in a volume label that is assigned when a volume is prepared for use on the system. For standard label volumes, the volume serial number is the VOL1 label of the volume. For no label volumes, the volume serial number is the name the user assigns to the volume. In DFSMSrmm, volume serial numbers do not have to match rack numbers.

VTS. See *virtual tape server*.

W

warning mode. The operating mode in which DFSMSrmm validates volumes as you use them, but issues warning messages when it discovers errors instead of rejecting volumes.

write-to-operator (WTO). An optional user-coded service that allows a message to be written to the system console operator informing the operator of errors and unusual system conditions that may need to be corrected.

WTO. See *write-to-operator*.

Index

A

ABARS (aggregate backup and recovery support)
  authorization to DFSMSrmm resources 226
  defining ABARS to RACF 33
  retaining accompany tapes 237
  retaining backup tapes 239
  retaining tapes written by 236
ABEND
  codes 389
  retaining data sets closed during ABEND processing 270
  retention of data set closed by abend processing 6
ABEND vital record specification 270
access method services REPRO command 287
accessibility code 217
ACCODE processing 201
accompany tapes 237
ACCOUNTING, EDGRMMxx operand 126
acero 198
ACS processing 69
active requests, number of 48
ACTIVITY file
  description 266
  printing 267
  viewing 267
adding
  local dialog extensions 332
  volumes to DFSMSrmm 49
ADDOWNER subcommand 49
ADDVOLUME subcommand 83
ADDVRS subcommand 154
  examples for retaining DFSMShsm tapes 229
  planning 51
allocating data sets
  backup copies 251
  control data set 37
  extract data set 252
  inventory management 251
  journal 41
alternate tape 232
American date format 128, 256
AMS LIBRARY command 103, 104
ANYUSE, EDGRMMxx operand 145
ARCTVEXT programming interface
  managing DFSMShsm tapes 177, 179
  planning 177, 195
  updating during implementation 24
assigning
  bin numbers 9
  bin numbers using DSTORE 271
  expiration dates 210
  storage locations 272
assigning a storage group 63, 69
assigning a storage groupr 151
associating a pool with a system 59
audit tape library using a list of barcode scanned volumes 385
authorization
  administrator functions 159
  for EDGINERS utility 157
  for users 42
  ignoring duplicate or undefined volumes 199
  initialize and erase functions 157
  librarian functions 160
  operator functions 161
  performing inventory management 161
  resources 154, 157
  system programmer functions 160
  user functions 158
  users 153, 170
authorizing users
  for use of DFSMSrmm subcommands 26
  for use of DFSMSrmm utilities 26
  users by defining resources to RACF 16
automated labeling by DFSMSdfp 323
automated tape library dataserver
  cartridge entry processing 78
  defining volumes for 78
  description 2
  ejecting volumes from 79
  moving volumes to 82
  replenishing scratch volumes 340
  reserving shelf space for ejected volumes 48
  scratch pool restrictions 60
  specifying a name 78
automatic message handling 150
automatic recovery 294
automating control data set backup 278

B

backing up
  DFSMSrmm control data set 287
  journal 289
  using EDGBKUP with access method services REPRO command 287
  using EDGBKUP with DFSMSdss DUMP 287
  using EDGHSKP with access method services REPRO command 280
  using EDGHSKP with DFSMSdss DUMP 278
  when the DFSMSrmm subsystem is active 278
  when the DFSMSrmm subsystem is inactive 278
backup function
  DFSMSrmm control data set 278
  journal 289
BACKUP parameter 253, 278
backup procedure
  automating 290
  sample procedure 341
  specifying the procedure name 126
BACKUPPROC, EDGRMMxx operand 126
Basic Tape Library Support (BTLS)
  defining scratch pools 103
  description 103
  inventory management considerations 104

© Copyright IBM Corp. 1992, 2001

Basic Tape Library Support (BTLS) *(continued)*
scratch management 106
updating the catalog 105
using EDGINERS with 105
batch processing 316
bin number
assignment using DSTORE 271
estimating the number of 407
BLP, EDGRMMxx operand 127
BUFFER.CONTROL resource symbolic name 28
building
ADDVOLUME subcommands from a list of barcode scanned volumes 385
RMM CHANGEVOLUME subcommands for volumes in storage locations 385
RMM subcommands to add volumes to DFSMSrmm 386
built-in storage locations
description 3, 107
priority of moves to 3
shelf-management 107
switching to installation defined locations 112
bypass label processing
defined in installation options 4
DFSMSrmm control of 127
processing support 13
bypassing tape label processing 162

C

calculating space for
control data set 36
extract data set 252
journal 40
cartridge entry processing for logical volume cartridges 86
catalog control 266
catalog processing
catalog support 141
retaining data sets while cataloged 270
return to scratch 274
catalog retention period
displayed in vital records retention report 265, 266
setting 127
catalog sharing 249
catalog status tracking
identifying system IDs 128
catalog synchronization setup with CATSYSID, EDGRMMxx operand 128
cataloging the DFSMSrmm control data set in a shared user catalog 36
catalogs, synchronizing with the DFSMSrmm control data set 254, 304
CATRETPD, EDGRMMxx operand 127
CATSYSID, EDGRMMxx operand 128
CBRSPPIM — sample JCL for import list volume private request 92, 95
CBRSPPIM-sample JCL for import list volume scratch request 92
CBRSPPXP — sample JCL for export list volume scratch request 94
CBRSPPXP-sample JCL for export list volume scratch request 90
CBRSPSIM — sample JCL for import list volume scratch request 92, 95
CBRSPSIM-sample JCL for import list volume scratch request 92
CBRSPSXP — sample JCL for export list volume scratch request 94
CBRSPSXP-sample JCL for export list volume scratch request 90
CBRUXCUA exit
description 385
reason codes 181
return codes 181
volume status change 100
where to find source code 24
CBRUXEJC exit
description 385
return codes 181
where to find source code 24
CBRUXENT exit
description 385
entering volumes 78
modifying 102
return codes 181
where to find source code 24
CBRUXVNL exit
description 385
processing support 81
retrieving information about a volume 190
retrieving information about VTS volumes 190
return codes 181
where to find source code 24
CDSID, EDGRMMxx operand 128, 304
chaining vital record specifications 6
CHANGEVOLUME subcommand 154
changing
ADD product volume dialog panel defaults 333
DFSMSrmm dialog panel navigation 331
pool definition 60
running modes 52, 133
changing owner information 184
changing storage location managementtype 110
changing storage location medianame 110
changing storage locations 110
character set
chart xxv
use in statement xxv
checking
DATASET class resource 173
TAPEVOL class resource 174
checking dfsmsrmm status 48
checking for DFSMSrmm license 29
checkpoint data set creation 17
clearing the journal 278, 288
CLIST operand 15
combining retention types 269
completing the export processing 91
completion codes 389
concatenated parmlib support 31, 34

confirming
global release actions 277
global volume movement 276
volume movement in the system-managed tape environment 310
volume movement to system-managed libraries 82
volume release actions 274
considerations for multiple MVS images or shared-DASD complexes 23
control data set
allocating the index and data components 37
audit information 162
backing up 8, 287
calculating space 36
cataloging in a shared user catalog 36
control record 303
controlling access to 37
creating during installation
allocating space 37
backing up 39
initializing 38
creating the control record 303
displaying information 309
EDGJMFAL SAMPLIB member 37
EDGJUTIL SAMPLIB member 38
ensuring access in shared environment 36
forward recovering 292
global resource serialization 36
GUARANTEED SPACE attribute, using 36
improving performance 37
index and data components 37
moving to a different device 295
naming 129
placement of 36
recovering 8, 292
reorganizing 293
restoring 290, 292
scheduling back up 247
sharing 309
specifying ID 128
synchronizing with system catalogs 254, 304
update failures 294
updating the control record 303
updating volume status 100
validating against TCDB 306
verifying the contents 305, 306
control data set control record
creating 303
updating during recovery 293
controlling
controlling access to the control data set 37
data set recording 206
message case 133
tape relabeling 74
controlling tape erasure 317
controlling tape initialization 317
controlling volume movement 132
controlling volume retention 136
conversion
changing duplicate volume serial numbers 74
detecting errors during 287
conversion *(continued)*
fixing errors resulting from 287
ignoring duplicate volume serial numbers 75, 197
converting
duplicate volume serial numbers 74
scratch pool information 51
volume information using EDGCLMS 51
converting CLIST output 90, 92, 94, 95
correcting rack or bin number counts 303
creating
a monthly archive from weekly audit reports 385
a report about owners sorted by name and department number 386
a report about volumes 386
a report based on rack number prefixes 386
a report containing information about lost volumes 386
a report of data sets sorted by data set name 385
a report of volumes recently returned to scratch status 386
a report using the extended report extract file 386
a weekly archive from daily audit reports 385
an import list from CLIST output 386
extract data set 280
reports 14
table for controlling data set recording 206
volume label 324
creating checkpoint data sets 17
creating non-checkpoint data sets 17
customizing
ADD Product Volume dialog panel defaults 333
DFSMSrmm messages 333
DSSOPT DD Statement 279
EDGP@LCL, dummy panel 332
EDGXPROC procedure 340
installation exits 177, 195
ISPF dialog 331
notification messages and notes 334
report trailer lines 333
RMMISPF exec 331
user exits 177

D

data set
allocating for inventory management 251
managing 13
order of matching during vital record processing 269
protection 169
recording information 206
retention by job name 142
types of retention 5
uncataloging during expiration processing 275
data set profile 169
data set recording
table for controlling data set recording 206
using EDGUX100 206
data set vital record specification
example 7
for managing special dates 199

date format
extract data set 280
setting for use in reports and messages 128
DATEFORM
in EDGHSKP 255, 280
operand in EDGRMMxx 128
default retention period, specifying 136
defining
a volume in a system-managed tape library 78
ABARS user ID to RACF 33
DFSMShsm user ID to RACF 33, 177
DFSMSrmm subsystem name to MVS 25
home location 5
MCS console 203
mount messages 120
original expiration date 150
pools in parmlib member with the VLPOOL command 148
RACF profiles 153
security classes 145
SMF audit records 138
SMF records generated by DFSMSrmm 27
SMF security records 138
TAPEVOL class resource 174
volumes to DFSMSrmm 49
defining storage locations 108
DELETEVOLUME subcommand 154
DELETEVRS subcommand 154
deleting storage locations 110
delimiters xxiv
designing
rack pool 61
scratch pool 61
device types supported 2, 3
DFRMM Program Offering
inventory management considerations 310
sharing control data set with DFSMSrmm 309
support for non-system-managed tape libraries 309
DFSMSdfp automated labeling 323
DFSMSdss
changing options 279
clearing the journal during back up processing 278
commands used by DFSMSrmm 279
DSSOPT DD statement 251
inventory management considerations 249
STGADMIN.ADR.DUMP.CNCURRNT 250
using with EDGBKUP 287
DFSMShsm
ADDVRS examples for retaining DFSMShsm tapes 229
alternate tape 232
authorization to DFSMSrmm resources 225
defining DFSMShsm to RACF 33, 177
disaster recovery using DFSMShsm alternate tapes 240
expiration date protection 228
retaining
ABARS accompany tapes 237
backup tapes 232
control data set backup tapes 237
dump tapes 233, 238
DFSMShsm *(continued)*
retaining *(continued)*
migration tapes 231
TAPECOPY tapes 232
tapes 228
tapes written by ABARS 236, 239
running with DFSMSrmm 225, 241
system options 227
using EDGDFHSM programming interface 179
using EDGTVEXT programming interface 177
validating data set name 17
DFSMSrmm
adding local dialog extensions 332
authorization checking 171
basic tape library support 103
changing ADD product volume dialog panel defaults 333
changing DFSMSrmm dialog panel navigation 331
changing volume dialog panel defaults 333
concatenated parmlib support 31, 34
control record 303
customizing messages 333
defining owner to 49
description 1
duplicate volume serial number support 73
EDGUX100 installation exit 195
EDGUX200 installation exit 220
general user tasks 20
initializing the subsystem 52
modes of operation 17
operator tasks 21
panel navigation 331
protecting resources 153
RACF considerations 168
refreshing DFSMSrmm installation exits 215, 222
removing from the system 173
running modes 133
running utilities 7
security classification 163
storage administrator tasks 20
storage group name support 84
system completion codes 389
system-managed tape libraries support 77
system programmer tasks 20
tape initialization and erase control 317
tape librarian tasks 20
tape mount validation rules 17
undefined volume serial number support 73
user completion codes 389
validating tape volumes 17
volume rejection rules 18
wrong label processing 317
DFSMSrmm application programming interface 16
DFSMSrmm utility
EDGBKUP, backing up the control data set 287
EDGHSKP, inventory management program 247
EDGINERS, initializing and erasing volumes 163, 311
EDGRESET utility, removing DFSMSrmm from the system 173
EDGUTIL, verifying control data set contents 287

DFSORT 15
  sample EDGJACTP print job 267
diagnosing errors 252
  using SYSPRINT data set 288
  using the message file 307
  using the TRACE operand 331
dialog customization 331
disabling
  automatic cartridge loader 202
  PDA trace facility 135
  the DFSMSrmm subsystem interface 47
disabling the autoloader 201
DISPDDNAME, EDGRMMxx operand 129
displaying information 309
DISPMSGID, EDGRMMxx operand 129
disposition control
  defining the message returned by disposition processing 129
  modifying label output using EDGUX100 205
  naming a disposition control file 129
  setting up 30, 347
DISTANT storage location 3
DITTO, using 97
DSNAME, EDGRMMxx operand 129
DSSOPT
  changing options 279
  description 251
DSTORE parameter 253, 272
duplicate volume serial number
  changing duplicate volume serial numbers 74
  ignoring 75, 197
  using EDGUX100 195
dynamic shelf-management 272

E

EBCDIC labels 326
EDG0154I 46
EDG019VM, programming interface 342
EDG2107E 130
EDG2108E 130
EDG3IIP1 SAMPLIB member
  using 244
EDG3LVVR SAMPLIB member
  description 385
  using 244
EDG3UX29 SAMPLIB member 24
EDG3UX62 SAMPLIB member
  description 385
EDG3UX71 SAMPLIB member
  description 385
  using 244
EDG3X71, programming interface 192
EDG4026I 312
EDGBETT 385
EDGBKP1 385
EDGBKP2 385
EDGBKUP control data set backup program
  backing up the control data set and journal 289
  description 385
  DFSMSrmm control data set back up and restore program 287
EDGBKUP control data set backup program *(continued)*
  exec parameters 288
  restoring the control data set 290, 292
  return codes 293
EDGCLIBQ SAMPLIB member
  description 385
  using 339
EDGCMOV 385
EDGDFHSM, programming interface 179
EDGDFRMM SAMPLIB member
  description 385
EDGHSKP inventory management utility
  control data set backup processing 278
  description 247
  expiration processing 274
  extract data set processing 280
  return codes 281
  storage location management processing 271
  vital record processing 260
EDGINERS initializing and erasing volumes utility
  automatic processing 312
  creating volume label 324
  description 311
  differences and similarities to IEHINITT 8
  initialize and erase program 311
  ISO/ANSI label support 311
  JCL 313
  manual processing 313
  replacing IEHINITT with EDGINERS 312
  return codes 325
  running for BTLS 105
  running with DFSMSrmm 309
  SYSIN commands for 318
  using EDGINERS instead of IEHINITT 163
  wrong label processing 317
EDGINERS.volser resource symbolic name 28
EDGIVP1 SAMPLIB member
  description 385
  using 363
EDGIVP2 SAMPLIB member
  description 385
  using 363
EDGIVPPM SAMPLIB member
  description 385
  using to specify DFSMSrmm options 360
EDGJACTP SAMPLIB member
  description 385
EDGJAUDM 385
EDGJAUDW 385
EDGJBCAV 385
EDGJCOMB 385
EDGJCVB 385
EDGJDHKP 385
EDGJDSN 385
EDGJEJC 385
EDGJEXP 385
EDGJHKPA 385
EDGJHKPA SAMPLIB member
  description 385
EDGJHSKP 385

EDGJHSKP SAMPLIB member
  description 385
EDGJIMPC 386
EDGJIMPC sample 95
EDGJINER 386
EDGJINER SAMPLIB member
  description 385
EDGJLOPC 386
EDGJLOPC SAMPLIB member
  description 385
EDGJMFAL 386
EDGJMFAL SAMPLIB member
  description 385
  using during implementation 37
EDGJMOVE 386
EDGJNLAL 386
EDGJNLAL SAMPLIB member
  description 385
  using during implementation 41
EDGJNSCR 386
EDGJRACK 386
EDGJRECL 386
EDGJRECV 386
EDGJROWN 386
EDGJRVOL 386
EDGJSCRL 386
EDGJSMF 386
EDGJSMFP 386
EDGJUTIL 386
EDGJUTIL SAMPLIB member
  description 385
  using during implementation 38
EDGJVFY 386
EDGJVLT 386
EDGJVLTM 386
EDGJVME 386
EDGJVOL 386
EDGJVRSV 386
EDGJWHKP 386
EDGLABEL SAMPLIB member
  defining in ICHRIN03 33
  description 385
  RACF requirement 33
  using 341
EDGLCSUP macro programming interface 365
EDGLCSUX
  managing automated tape library dataserver volumes 179
  planning 177
  return codes 181
EDGLIBQ SAMPLIB member
  description 385
  using 339
EDGMSGEX, programming interface 192
EDGP@LCL, dummy panel 332
EDGPACTA 386
EDGPACTC 386
EDGPACTD 386
EDGPACTI 386
EDGPACTM 386
EDGPACTP 386
EDGPACTT 386
EDGPACTV 386
EDGPBKUP 386
EDGPCMOV 386
EDGPDOX PDA trace data set 343
EDGPDOY PDA trace data set 343
EDGPEJC 386
EDGPEXP 386
EDGPHKP 386
EDGPHKPA 387
EDGPINER 387
EDGPL100 macro programming interface 372
EDGPL200 macro programming interface 377
EDGPMOVE 387
EDGPMSGA 387
EDGPMSGC 387
EDGPRPTA 387
EDGPRPTX 387
EDGPSCRL 387
EDGPVFY 387
EDGPVRSA 387
EDGRESET utility
  invoking by the DFSMSrmm procedure 161
  removing DFSMSrmm from the system 157, 173
EDGRHKPA 387
EDGRMMxx, DFSMSrmm parmlib member
  creating parmlib member definitions 34
  defining during implementation 34
  example 115
  MNTMSG command 120
  OPTION command 122
  REJECT command 144, 167
  SECCLS command 145
  specifying options for 115
  VLPOOL command 148
EDGRPTD DFSMSrmm inventory and movement report utility
  extract data set as input to 280
EDGRRPTE exec
  extract data set as input to 280
EDGRVCLN 387
EDGRVCLN exec
  description 385
EDGSETT 387
EDGSLAB macro programming interface 379
EDGSSSI 25
EDGTVEXT
  description 177
EDGTVEXT, programming interface 177
EDGUTIL control data set contents verification program
  creating the control record 303
  DFSMSrmm control data set create and verify program 299
  enabling stacked volume support 303
  exec parameters 300
  JCL 299
  mending the control data set 299
  return codes 308
  verify system-managed volume information 83
  verifying control data set contents 306

EDGUX100 SAMPLIB member
assigning expiration dates 210
bypassing tape label processing 162
data set recording 206
description 385
installing 214
managing scratch pools 201
modifying disposition control processing label output 205
refreshing 215, 222
return codes 220
tailoring 198, 200
using 67, 70, 195
EDGUX200 SAMPLIB member
description 385
installing 221
refreshing 222
return codes 224
using 220
EDGXMP1 SAMPLIB member
description 385
EDGXMP2 SAMPLIB member
description 385
EDGXPROC SAMPLIB member
defining in parmlib 138
RACF requirement 33
using EDGXPROC procedure 340
ejecting volumes from system-managed libraries 79, 272
enabling
DFSMSrmm and tape recording 26
DFSMSrmm subsystem interface 52
PDA trace facility 135
enabling stacked volume support 303
ERASE, EDGRMMxx operand 147
erase volume release action 277
erasing tape volumes using EDGINERS 311
error diagnosis 331
European date format 128, 256
evaluating removable media management needs 407
exec, LIBQ 339
EXPDTCHECK, EDGRMMxx operand 149
expiration date
assigning 210
protection 150
updating 137
expiration processing 106
description 274
retaining DFSMShsm tapes 228
scheduling 247
exploiting high speed cartridge tape positioning 17
export processing 90
EXPROC parameter 253, 274
extract data set
calculating space for 252
placement of 252
scheduling creation 247

F

finding samples xxi
formatting a list of logical volumes from RMM SEARCHVOLUME CLIST output 95
forward recovery 8, 291

G

general-use programming interfaces
EDGLCSUP 365
EDGSLAB 379
general user
access to DFSMSrmm resources 158
tasks 20
generic volume serial number 7
global confirmation 276
global resource serialization
control data set 36
global resource serialization(GRS)
converting the RESERVE to a SYSTEMS enqueue 28
converting the SYSTEMS enqueue to a local SYSTEM enqueue 27
reducing global resource serialization traffic 131
reserve names 28
SYSZRMM 28
updating GRSRNLxx 27
GRS(global resource serialization)
converting the RESERVE to a SYSTEMS enqueue 28
converting the SYSTEMS enqueue to a local SYSTEM enqueue 27
reducing global resource serialization traffic 131
reserve names 28
SYSZRMM 28
updating GRSRNLxx 27
GRSRNLxx 27
GUARANTEED SPACE attribute
control data set 36
journal 41

H

hierarchy of moves 3
hierarchy of storage location names 270
high speed cartridge tape positioning support 17
home location
changing 98, 102
definition 5
updating 80

I

I/O errors on a volume 12
IBM standard and user header or trailer labels (SUL) 12
IBM standard labels (SL) 12
ICETOOL, DFSORT utility
description 14, 15
ICHRIN03, started procedure table
defining ABARS user ID 33

ICHRIN03, started procedure table *(continued)*
defining DFSMShsm user ID 33, 177
defining DFSMSrmm user ID 33
ID, EDGRMMxx operand 121
IEC507D 66, 150
IEC704A 84
IEFRDER DD 31
IEFSSNxx 25
IEHINITT
description 8
differences with EDGINERS 312
limiting use of 163
replacing with EDGINERS 312
IFAPRD00, ensure update of 29
IGDACERO, mapping macro 204
IGDACSXT, pre-ACS installation exit 204
ignoring
duplicate or undefined volumes 199
volumes 75, 197
IGXMSGEX programming interface
displaying DFSMSrmm messages 192
planning 177, 195
updating during implementation 24
IKJEFTxx member 27
IKJTSOxx 26
implementation
adding volumes 49
assigning a RACF user ID 33
authorizing users 42
creating the control data set 35
defining
DFSMSrmm to MVS 25
EDGRMMxx 34
owner information 49
shelf locations 48
dynamically adding DFSMSrmm 26
enabling DFSMSrmm and tape recording 26
initializing the DFSMSrmm subsystem 52
installation defined storage locations 108
installing
JES3 USERMOD 24
with SMP/E 23
journal 39
modifying ISPF 42
planning vital record specifications 51
protect mode 52
restarting MVS 44
running the IVP 23
setting up utilities 53
START command 45
starting DFSMSrmm 45
tailoring EDGRMMxx 35
tasks 23, 55
TSO HELP 44
updating
ARCTVEXT 24
GRSRNLxx 27
IEFSSNxx 25
IGXMSGEX 24
IKJTSOxx 26
operational procedures 52
implementation *(continued)*
updating *(continued)*
procedure library 30
SCHEDxx 29
SMFPRMxx 27
SYS1.PARMLIB members 25
import processing 91, 93, 94
INACTIVE resource symbolic name 28
initialize volume release action 277
initializing
DFSMSrmm control data set 38
DFSMSrmm subsystem 52
volumes in system-managed libraries 84
volumes with unknown volume serial numbers 317
initializing and erasing volumes
batch processing 316
examples 325
replacement for IEHINITT 312
scheduling 247
using EDGINERS 311
using LABEL procedure 341
volumes in system-managed libraries 84
input only volume 101
installation defined storage locations
defining location names 116
defining with the LOCDEF parmlib command 108
description 3, 107
implementing 108
priority of moves to 3
segregating shelf locations 107
setting a destination for volumes 107
shelf-management 107
switching built-in storage locations 112
installation exit
CBRUXCUA 179
CBRUXEJC 179
CBRUXENT 179
CBRUXVNL 179
displaying DFSMSrmm messages 192
EDGTVEXT 177
EDGUX100 195
IATUX71 192
IFG019VM 342
IGXMSGEX 192
processing NL label tapes 342
installation verification program (IVP)
description of EDGIVPPM, EDGIVP1, EDGIVP2 385
steps for running 359
integrated catalog facility 249
inventory management
allocating data sets 251
backing up the DFSMSrmm control data set 278
creating an extract data set 280
creating reports 280
description 7
EDGHSKP, inventory management program 247
expiration processing 274
management reports 257
message file 257, 307
processing order 253

inventory management *(continued)*
report file 261
return codes for 281
scheduling 247
storage location management 271
trial run vital record processing 8
using VRSCHANGE EDGRMMxx operand to set up trial run 142
vital record processing 260
where to run 104, 309
IOS000I 312
IPL date checking 129
IPLDATE, EDGRMMxx operand 129
ISO/ANSI accessibility 217
ISO/ANSI and user header or trailer labels (AUL) 12
ISO/ANSI label versions, specifying 320
ISO/ANSI labels 326
ISO/ANSI labels (AL) 12
ISO/ANSI tape labels, EDGINERS example 329
ISO/ANSI X3.4–1986 character set 319
ISO date format 128, 256
ISPF
adding a selection to an ISPF panel 42
changing ADD product volume dialog panel defaults 333
making the ISPF dialog available 43
modifying during installation 42

J

JES2
installing a USERMOD during implementation 24
setting subsystem name example 25
JES3
defining an MCS console 203
DFSMSrmm SAMPLIB member EDG3IIP1 244
DFSMSrmm SAMPLIB member EDG3LVVR 244
DFSMSrmm SAMPLIB member EDG3UX29 243
DFSMSrmm SAMPLIB member EDG3UX62 245
DFSMSrmm SAMPLIB member EDG3UX71 244
message IATUX29 24
mount and fetch messages 57, 120, 196
running with DFSMSrmm 243
setting the SETPARAM DSN option 244
job name
controlling policy selection 142
description 5
order of matching during vital record processing 269
using for pool selection 211
jobs from non-MVS systems, defining owner information 49
journal
allocating space for 41
backing up 42, 289
calculating space for 40
clearing 278, 288
defining a threshold 130
EDGJNLAL SAMPLIB member 41
GUARANTEED SPACE attribute, using 41
moving to a different device 295
journal *(continued)*
naming 130
placement of 40
protecting 41
resetting 280
scheduling back up 247
JOURNAL DD 32
JOURNALFULL, EDGRMMxx operand 130
JRNLNAME, EDGRMMxx operand 130
Julian date format 128, 256

K

KB 36

L

LABEL procedure 341
label types supported 12
LIBQ exec 339
library
automated tape 1
manual tape 1
non-system-managed 1
removable media 1
system-managed 1
LIBRARY command 103, 105
limiting searches 131
limiting tape volume usage at the system level 144
LINECOUNT, EDGRMMxx operand 130
LISTCONTROL subcommand 154
LISTVRS subcommand 154
LOCAL storage location 3
location
defining installation defined storage locations 116
for more than one destination request 270
specifying move locations 6
LOCDEF, command in EDGRMMxx
LOCATION operand 116
MANAGEMENTTYPE operand 116
MEDIANAME operand 117
PRIORITY operand 117
TYPE operand 118
using 119
logical volume cartridge entry processing 86
logical volume support 85
low-on-scratch condition 340

M

macros
EDGLCSUP 365
EDGPL100 372
EDGPL200 377
EDGSLAB 379
Installation Exit mapping macro — EDGPL100 372
Installation Exit mapping macro — EDGPL200 377
Library Control System interface — EDGLCSUP 365
sticky label data— EDGSLAB 379
maintaining the user access list 168

management class
assigning 71
defining for volume retention 71
retaining
system-managed volumes 71
usage in vital record processing 268
management class names 6
managing
DFSMShsm tapes 225
managing scratch tape pools 67
scratch tape pools with EDGUX100 201
special dates with vital record management values 199
storage locations 107
VM tapes 339
managing stacked volumes 88
manual cartridge entry processing 79
manual mode
implementation, during 46
specifying 133
manual move control 113
manual recovery 294
manual tape library
adding volumes to 79
description 2
ejecting volumes from 79, 272
moving volumes to 82
marking volumes for replacement 275
MASK, EDGRMMxx operand 147
MASTER DD 31
MASTER.RESERVE resource symbolic name 28
master status 9
master status volumes, controlling tape initialization 317
master volume
controlling overwriting of 130
validating owner information 188
MASTEROVERWRITE, EDGRMMxx operand 130
matching order for vital record specifications 269
MAXHOLD, EDGRMMxx operand 131
maximum retention period, specifying 132
MAXRETPD, EDGRMMxx operand 132
MB 36
MCS console 203
media name
assigning for storage locations 110
defining for storage locations 117
defining for volume pools 58
using to move volumes to non-shelf-managed storage locations 111
using to segregate storage locations 110
media shape 110
media type pooling 61
MEDIANAME, EDGRMMxx operand 150
mending the control data set 299
message file 257
messages
CBR3660A 340
controlling message case 133
customizing messages 333
EDG0103D 361
messages *(continued)*
EDG2103D 295
EDG2111I 294
EDG2115I 294
EDG2235E 257
EDG2236I 257
EDG2237E 257
EDG2307I 276
EDG2404W 270, 276
EDG2405 through EDG2409 334
EDG2420I 276
EDG2421I 276
EDG2422I 276
EDG2423I 276
EDG2424I 276
EDG2425I 276
EDG2429I 276
EDG2700 through EDG2713 334
EDG3017I 250
EDG3018I 250
EDG3212E 250
EDG4001D 295
EDG4010D 280
EDG4026I 312
EDG6401I 276
EDG6417I 308
EDG6433I 308
EDG6434I 308
EDG6901I 308
EDG8008D 295
EDG8121D 190
EDG8122D 190
EDG8123D 190
IATUX29 24
IEC502E 363
IEC507D 150
IEC704A 84
IOS000I 312
release notification 335
sample EDGUTIL SYSPRINT output 308
sample messages issued by RMM ADDRACK TSO subcommand 250
setting date format for 128
updating 120
MHKP.ACTIVE resource symbolic name 28
migrating to vts 86
mixed case messages 133
MNTMSG, command in EDGRMMxx
ID operand 121
MSGID operand 121
RACK operand 121
VOLUME operand 122
mode of operation
changing during implementation 52
definitions 17
description 17
in parmlib member EDGRMMxx 133
type 133
monthly archive from weekly audit reports 385
movement and retention policies 260
movement hierarchy 7

movement priority number 7
moving
DFSMSrmm data sets to different devices 295
moving volumes to a system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver 102
volumes to storage locations 110
volumes using vital record specification chains 6
moving volumes in a multi-volume set 132
MSG, EDGRMMxx operand 133, 147
MSGID, EDGRMMxx operand 121
multi-record update failure 294

N

NAME, EDGRMMxx operand 147
name set vital record specification
checking for 303
name vital record specification 7
NETVIEW 52
no label tapes
setting up RACF profiles to use 156
usage 12
use of 74
using BLP to create 127
non-checkpoint data set creation 17
non-scratch tape 407
non-system-managed tape library 3
DFRMM support for 309
moving from 102
nonstandard tape label 13
NOTIFY, EDGRMMxx operand 133
notifying
customizing messages and notes 334
during inventory management 274
owners 133
release action 274
volume and software product owners 274
volume release 133
NUMBER, EDGRMMxx operand 147

O

OAM (object access method)
cartridge entry processing 78
EDGLCSUP macro 365
manual cartridge entry processing 79
volume-not-in-library processing 81
obtaining updated versions of IKJEFTxx member 27
open data sets
during expiration processing 276
retaining 270
OPEN vital record specification 270
operational procedures 52
operator
access to DFSMSrmm resources 158
tasks 21
OPMODE
EDGRMMxx operand 133
manual mode 133
protect mode 134
record-only mode 133
OPMODE *(continued)*
warning mode 134
OPTION, command in EDGRMMxx
ACCOUNTING operand 126
BACKUPPROC operand 126
BLP operand 127
CATRETPD operand 127
CATSYSID operand 128
CDSID operand 128
DATEFORM operand 128
DISPDDNAME operand 129
DISPMSGID operand 129
DSNAME operand 129
IPLDATE operand 129
JOURNALFULL operand 130
JRNLNAME operand 130
LINECOUNT operand 130
MASTEROVERWRITE operand 130
MAXHOLD operand 131
MAXRETPD operand 132
MOVEBY operand 132
MSG operand 133
NOTIFY operand 133
OPMODE operand 133
PDA operand 135
PDABLKCT operand 136
PDABLKSZ operand 136
PDALOG operand 136
RETAINBY operand 136
RETPD operand 136
SCRATCHPROC operand 138
setting during startup 45
SMFAUD operand 138
SMFSEC operand 138
SYSID operand 139
TPRACF operand 139
VRSCHANGE operand 142
VRSEL operand 143
VRSJOBNAME operand 142
VRSMIN operand 143
original expiration date 163
OUTPUT, EDGRMMxx operand 145
owner
defining owner information 49
information recorded in the TCDB 83
managing information 14

P

panel navigation 331
parmlib member definitions 34
parmlib member EDGRMMxx
defining
implementation, during 34
mount and fetch messages — MNTMSG 120
pools — VLPOOL 148
security classes — SECCLS 145
system options — OPTION 122
tables not available on systems — REJECT 144
description 5
specifying options 115

partitioning a system-managed tape library 78, 101
partitioning a VTS 101
partitioning an IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver 101
PDA, EDGRMMxx operand 135
PDABKLSZ, EDGRMMxx operand 136
PDABLKCT, EDGRMMxx operand 136
PDALOG, EDGRMMxx operand 136
permanent errors 275
planning
  evaluating removable media management needs 407
  owner information 49
  pooling 55
  programming interfaces 177, 195
  user exits 177, 195
  vital record specifications 51
policy
  defining for data sets and volumes 5
  defining for management class and vital record management values 70
  defining retention and movement policies 5
  expiration management 70
  retention and movement 260
pool
  changing definition 60
  creating 58
  default 58, 148
  designing 60
    rack pools 61
    scratch pools 61
  name 59, 119
  prefixes 59
  size 59
  types of 60
  VLPOOL command 58, 148
pooling
  based on media type 61
  defining shelf locations during implementation 48
  definition 9, 55
  example 66
  planning 55
  rack 9
  scratch 9
  selection using DFSMSrmm EDGUX100 installation exit 211
  selection using job name 211
  selection using system name 211
  types 9
  using a BTLS category name 151
  using VLPOOL to specify 148
  within system-managed libraries 10
pre-acs processing 204
pre-ACS processing 68
predicting when a volume is released 255
PREFIX, EDGRMMxx operand 151
preventing
  a volume from returning to scratch status 220
  the use of IEHINITT 163
  volume use on specific systems 144
primary vital record specification 269
priority
  of location names 270
  setting with PRIORITY operand 117
  volume moves 3
private volume
  controlling overwriting of 130
  definition 9
  validating owner information 188
Problem Determination Aid (PDA)
  controlling tracing 344
  data sets 343
  description 30, 343
  PDA parmlib option for enabling and disabling PDA trace 135
problem diagnosis 331
procedure library updates
  during implementation 30
  for IVP 359
processing ACCODE 201
product-sensitive programming interfaces
  EDGPL200 377
programming interfaces
  EDG019VM 342
  EDG3X71 192
  EDGDFHSM 179
  EDGLCSUX 179
  EDGMSGEX 192
  planning 177, 195
protect mode
  running during implementation 52
  setting to validate data set names 167
  specifying 133
pseudo-GDG 235

Q

QNAME 28
quiescing the DFSMSrmm subsystem interface 47

R

RACF
  profiles for no label tapes 156
RACF (Resource Access Control Facility)
  assigning DFSMSrmm a user ID during implementation 33
  audit information 163
  authorizing users 16, 153, 167
  checking for DATASET class resource 173
  checking for TAPEVOL class resource 174
  considerations for using under DFSMSrmm 168
  controlling profile processing 164
  data set profile 169
  defining a TAPEVOL class resource 174
  defining ABARS to RACF 33
  defining DFSMShsm to RACF 33, 177
  defining profiles 153
  defining resource classes 198
  maintaining the user access list 168
  no protection 164
  protected DFSMSrmm resources 153
  RACF operand in EDGRMMxx 152

RACF (Resource Access Control Facility) *(continued)*
recording changes to vital record specifications 154
STGADMIN.ADR.DUMP.CNCURRNT 250
STGADMIN.IGG.LIBRARY 101
tape profiles, setting DFSMSrmm's use of 139
tape protection 164
TAPEDSN 164
TAPEVOL 164
updating ICHRIN03 33
using profile processing 167
using tape profiles 12
RACK, EDGRMMxx operand 121
rack number
assigning a 321
estimating the number of 407
inserting into a message 121
rack pool
definition 9
designing 61
using 67
using VLPOOL to define in parmlib member 148
RACROUTE calls 171
read-only mode
running during implementation 50
specifying 133
switching modes 52
reclaiming volume from pending release 249
recovery
description 8
from control data set update failures 294
updating the DFSMSrmm control record during 293
using DITTO 97
refreshing DFSMSrmm installation exits 215, 222
REJECT, command in EDGRMMxx
ANYUSE operand 145
OUTPUT operand 145
reject processing 144
rejecting
a range of tape volumes 144
volumes 18
volumes on specific systems 144, 167
relabeling tapes 162
release action
confirming 274
erase 277
initialize 277
notify owner 274
pending 274
replace 275
return to owner 275
return to scratch 275
types 11
release notification messages 335
releasing
volume from pending release status 249
REMOTE storage location 3
removable media library
definition 1
removing DFSMSrmm from the system 173
reorganizing the control data set 293
replace volume release action 275
report
about owners sorted by name and department number 386
about volumes 386
based on rack number prefixes 386
containing information about lost volumes 386
creating 14
customizing titles 333
data sets sorted by data set name 385
default lines per page, specifying 130
EDGAUD DFSMSrmm security and audit report 8
EDGRPTD DFSMSrmm movement and inventory report 15
EDGRRPTE exec 8
Expiration Processing Report 276
extract data set 280
monthly archive from weekly audit report 385
sample JCL for 385
setting date format for 128
SMF records 386
types of SMF record found 386
Vital Records Retention Report 262
volumes currently in storage locations sorted by volume serial number 386
volumes moving to storage locations 386
volumes recently returned to scratch status 386
volumes sorted by volume serial number 386
weekly archive from daily audit reports 385
report trailer lines, customizing 333
resetting the journal 280, 287
resource symbolic names 28
restoring the control data set 290
restoring the control data set with forward recovery 292
retaining
ABARS accompany 237
based on catalog status 266
data set retention types 5
data sets 5
DFSMShsm backup tapes 232
DFSMShsm control data set backup tapes 237
DFSMShsm dump tapes 233, 238
DFSMShsm migration tapes 231
DFSMShsm TAPECOPY tapes 232
DFSMShsm tapes 228
tapes written by ABARS 236, 239
types of retention 5
volumes 199
retaining volumes forever 201
retaining volumes in a multi-volume set 136
retention and movement policies 260
retention by job name 142
retention period
default, specifying 136
maximum, specifying 132
retention types 5
RETPD, EDGRMMxx operand 136
return codes
EDGBKUP 293
EDGHSKP 281
EDGINERS 325

return codes *(continued)*
EDGUTIL 308
EDGUX100 220
EDGUX200 224
OAM 181
return to owner release action 275
return to scratch release action 275
returning volumes to scratch 106, 310
RMM ADDVRS subcommand 154
RMM CHANGEVOLUME subcommand 154
RMM DELETEVOLUME subcommand 154
RMM DELETEVRS subcommand 154
RMM LISTCONTROL subcommand 154
RMM LISTVRS subcommand 154
RMM SEARCHVRS subcommand 154
RMMISPF exec 331
RMMISPF EXEC 42
RNAME 28
RPTEXT parameter 253
rules for tape mount validation 17
running mode
description 17
initial setting in parmlib member EDGRMMxx 50
manual 133
protect 134
record-only 133
set for full validation and recording 52
types 133
warning 134

S

SAF (System Authorization Facility)
authorization checking 171
description 16
processing to ignore a volume 75, 197
using the interface 170
SAMPLIB members
EDG3UX29 installing a JES3 USERMOD 24
EDGCLIBQ 339
EDGCLMS 51
EDGDFRMM 30
EDGIVP1 IVP Job 1 initializing tape volumes 23
EDGIVP2 IVP Job 2 using tape volumes 23
EDGIVPPM installation verification procedure 23
EDGJBKUP 287
EDGJHKPA 251
EDGJHSKP 247
EDGJINER 311
EDGJMFAL 37
EDGJNLAL 41
EDGJUTIL 38
EDGJVME 339
EDGLABEL 30
EDGLIBQ 339
EDGPHKP 247
EDGPHKPA 251
EDGRCSCR 51
EDGUX100 24
EDGUX200 24
EDGXPROC 30
SAMPLIB members *(continued)*
list of 385
scheduling
back up 247
inventory management 8, 247
SCHEDxx 29
scratch management for BTLS 106
scratch mount management 100
scratch pool
definition 9
designing 61
managing with EDGUX100 installation exit 201
using VLPOOL to define in parmlib member 148
scratch pooling using storage groups 63
scratch volumes, replenishing in an automated tape library dataserver 340
SCRATCHPROC, EDGRMMxx operand 138
searches, limiting 131
SEARCHVRS subcommand 154
SECCLS, command in EDGRMMxx
DESCRIPTION operand 147
ERASE operand 147
MASK operand 147
MSG operand 147
NAME operand 147
NUMBER operand 147
SMF operand 148
secondary vital record specification 269
security
audit trails 162
considerations when running DFSMShsm and DFSMSrmm 241
controlling RACF profile processing 164
controlling volume use in a system complex 167
DFSMSrmm resources 153
security classes — SECCLS 145
SMFAUD 162
special processing 163
using RACF profile processing 167
selecting a volume pool 151
SETPARAM DSN option in JES3 244
setting
maximum retention period 11
message case 133
mode of operation 133
setting location priority 117
volume expiration date 11
shared user catalog 36
sharing
catalogs 249
the control data set 309
shelf location
defining during implementation 48
defining new locations 48
definition of 407
management 8
prefix, in pools 59
shelf management
built-in storage location 3
description 9
for storage locations 107

shelf management *(continued)*
installation defined storage location 3
using LOCDEF MANAGEMENTTYPE operand to specify 116
SHUTDOWN resource symbolic name 28
SMF, EDGRMMxx operand 148
SMF record number
collecting audit information 163
defining audit records 138
defining security records 138
SMFAUD, EDGRMMxx operand 138
SMFPRMxx 27
SMFSEC, EDGRMMxx operand 138
SMP/E (System Modification Program Extended)
implementation, installing DFSMSrmm during 23
SMPSTS members
ARCTVEXT 24
CBRUXCUA 24
CBRUXEJC 24
CBRUXENT 24
CBRUXVNL 24
IGXMSGEX 24
list of 385
space requirement
calculating for control data set 36
calculating for journal 40
special expiration date 45
specifying ISO/ANSI label versions 320
specifying pool prefixes 59
specifying the ISO/ANSI volume accessibility code 319
stacked volume
enabling support 305
stacked volume support 89, 93
START command 45
starting
DFSMSrmm 45
DFSMSrmm subsystem address space 30
STGADMIN.ADR.DUMP.CNCURRNT 250
STGADMIN.EDG.HOUSEKEEP
READ access 161
user 161
STGADMIN.EDG.IGNORE.TAPE.volser
example 172
using 75, 197
STGADMIN.EDG.LABEL.volser
controlling tape relabeling 162
enabling use of no label output 74
STGADMIN.EDG.LISTCONTROL
CONTROL access 158
user functions 158
STGADMIN.EDG.MASTER
administrator functions 159
CONTROL access 159, 160, 161
librarian functions 160
operator functions 161
READ access 158
system programmer functions 160
user functions 158
STGADMIN.EDG.NOLABEL.volser
controlling tape relabeling 162
STGADMIN.EDG.OPERATOR
librarian functions 160
operator functions 161
READ access 160
system programmer functions 160
UPDATE access 160, 161
STGADMIN.EDG.OWNER
administrator functions 159
READ access 159
UPDATE access 159
user functions 159
STGADMIN.EDG.RELEASE
READ access 159
user functions 159
STGADMIN.EDG.VRS
administrator functions 159
librarian functions 160
READ access 159
system programmer functions 160
UPDATE access 159, 160
user functions 159
STGADMIN.IGG.LIBRARY 101
sticky label support 205
sticky labels
modifying label output using EDGUX100 205
stopping the DFSMSrmm subsystem interface 46
storage administrator
access to DFSMSrmm resources 158
tasks 20
storage group
name recorded in DFSMSrmm control data set 100
name validation 85
storage group, assigning 63, 69
storage groups for DFSMSrmm scratch pooling 63
storage location
assigning bin numbers 9
built-in 3, 107
changing 110
defining 108
definition 3
deleting 110
DISTANT 3
installation defined 3, 107
LOCAL 3
managing using DSTORE 271
more than one destination request 270
moving volumes to 110
priority of storage location names 270
REMOTE 3
segregating by media name 58
shelf-management 3, 107
storage location management
description 272
scheduling 247
storage requirements
control data set 36
extract data set 252
journal 40
switching volumes to a system-managed IBM 3494 Tape Library Dataserver or IBM 3495 Tape Library Dataserver 102

SYS1.PARMLIB
updating during implementation 25
SYSID, EDGRMMxx operand 59, 139, 152
SYSPRINT data set 288
system
name, defining 139
options, defining 122
system catalogs, synchronizing with the DFSMSrmm control data set 254, 304
system completion codes 389
system-managed tape library
confirming volume movement to 82
defining existing volumes 82
defining volumes to DFSMSrmm 98
description 2
DFSMSrmm defining name of 78
DFSMSrmm support of 77
ejecting volumes from 79, 272
initializing volumes in 84
partitioning 101
pool selection 211
removing DFSMSrmm from 157
system programmer
access to DFSMSrmm resources 158
tasks 20
SYSZRMM 28

T

tape
erasing 316
initializing 316
labeling 311
no label 74
processing tape labels 17
validating mounts 17
tape configuration database
definition 2
obtaining volume information from 50
rebuilding after system failure 83
updates performed by DFSMSrmm 83
verifying against the control data set 306
tape label
bypassing tape label processing 162
creating a VOL1 311
expiration date 150
processing 19
restriction 105
types supported 12
validation 19, 311
tape librarian
access to DFSMSrmm resources 158
DFSMSrmm ISPF Librarian Menu 21
tasks 20
tape mount validation rules 17
tape profile
creating a tape profile 167
processing 164
protection options 164
TAPEDSN 139, 164
TAPEVOL 139, 164
tasks
general user 20
tasks *(continued)*
operator 21
storage administrator 20
system programmer 20
tape librarian 20
temporary read error
information recorded by DFSMSrmm 324
listed in the extract data set 281
Tivoli OPC
EDGBETT sample procedure 385
EDGBKP1 sample procedure 385
EDGBKP2 sample procedure 385
EDGCMOV sample procedure 385
EDGJDHKP sample procedure 385
EDGJEJC sample procedure 385
EDGJEXP sample procedure 385
EDGJMOVE sample procedure 386
EDGJSCRL sample procedure 386
EDGJVFY sample procedure 386
EDGJVRSV sample procedure 386
EDGJWHKP sample procedure 386
EDGPACTA sample procedure 386
EDGPACTC sample procedure 386
EDGPACTD sample procedure 386
EDGPACTI sample procedure 386
EDGPACTM sample procedure 386
EDGPACTP sample procedure 386
EDGPACTT sample procedure 386
EDGPACTV sample procedure 386
EDGPBKUP sample procedure 386
EDGPCMOV sample procedure 386
EDGPEJC sample procedure 386
EDGPEXP sample procedure 386
EDGPHKP sample procedure 386
EDGPHKPA sample procedure 387
EDGPINER sample procedure 387
EDGPMOVE sample procedure 387
EDGPMSGA sample procedure 387
EDGPMSGC sample procedure 387
EDGPRPTA sample procedure 387
EDGPRPTX sample procedure 387
EDGPSCRL sample procedure 387
EDGPVFY sample procedure 387
EDGPVRSA sample procedure 387
EDGRHKPA sample procedure 387
EDGSETT sample procedure 387
TPRACF, EDGRMMxx operand 139, 241
tracing errors 331
trial run
description 271
set based on EDGRMMxx VRSCHANGE operand 142
validating vital record specifications without control data set update 54
vital record specification before they are processed 256
trial run processing 8
TSO HELP 44
TYPE, EDGRMMxx operand 152

U

UNCATALOG, EDGRMMxx operand 141

uncataloging
controlling with UNCATALOG EDGRMMxx operand 141
data sets 141
data sets during expiration processing 275
updating
GRSRNLxx 27
ICHRIN03 33
SCHEDxx 29
SMFPRMxx 27
volume expiration date 137
upper case messages 133
user access list 168
user completion codes 390
user exits
planning 195
using 177
user group pooling 61
user status 9
user status volumes, controlling tape initialization 317
using
a shared user catalog 36
EDGUX100 installation exit 195
EDGUX200 installation exit 220
manual move control 113
media shape to segregate shelf locations 110
using the sms pre-ACS interface 73
utility
EDGAUD, security and audit 8
EDGBKUP, backing up control data set 8, 287
EDGHSKP, inventory management 7, 247
EDGINERS, initializing and erasing volumes 8, 311
EDGRESET utility 173
EDGRPTD, movement and inventory 15
EDGUTIL, verifying control data set contents 8, 83, 287

V

validating
control data set integrity 305
magnetic tape mounts 17
owner information on a master volume 188
primary vital record specification 269
storage group name 85
vital record specification chains 268
vital record specifications without control data set update 54
VERIFY parameter 253
verifying DFSMSrmm control data set contents 299
virtual tape server
completing export processing 91
confirming volume moves for exported volumes 94
creating a volume export list 90
creating a volume import list 95
creating an import list 386
creating export list of volumes 90, 94
creating import list of volumes 92, 95
DFSMSrmm support for 82
export processing 90, 93
import processing 91, 93, 94
virtual tape server *(continued)*
logical volume cartridge entry processing 86
logical volume support 85
migrating to 86
partitioning a 101
stacked volume support 89, 93
volume-not-in-library processing 81
virtual tape server subsystem 2
vital record processing
description 267
identifying volumes to be retained 73, 201
scheduling 247
trial run set up VRSCHANGE EDGRMMxx operand 142
Vital Records Retention Report 262
vital record specification
chaining 6
checking for 268
defining 72
for data sets closed during ABEND processing 270
for data sets still open during inventory management 270
management values 199
matching order 269
minimum number 268
order of matching 269
planning 51
recording changes to 154
secondary vital record specification 269
testing vital record specification before they are processed 256
using old data set naming conventions 238
validating vital record specification chains 268
vital record specification management value
assigned by DFSMSrmm EDGUX100 sample 6
defining 199
description 6
retaining volumes using 199
setting with DFSMSrmm EDGUX100 installation exit 195
Vital Records Retention Report
customizing trailer lines 333
using 262
VLPOOL, command in EDGRMMxx
DESCRIPTION operand 149
EXPDTCHECK operand 149, 229
MEDIANAME operand 150
PREFIX operand 151
RACF operand 152
SYSID operand 152
TYPE operand 152
VLPOOL definitions 104
VM tape
getting rack number with LIBQ exec 339
managing 339
volume
adding details 49
automatic notification of release 133
changing ADD product volume dialog panel defaults 333
confirming moves 276

volume *(continued)*
defining 83, 98
defining details 49
defining existing 82
duplicate serial numbers 73
ejecting from system-managed libraries 79, 272
ignoring 75, 197
initializing volumes in system-managed libraries 84
input only 101
managing volumes with special expiration dates 70
marking for replacement 275
master status 9
moving 82
preventing use on specific systems in a complex 167
private 9
protecting 241
reclaiming volume from pending release 249
rejecting 144
relabeling 74
retaining
DFSMShsm tape volumes 228
using management class 71
using vital record specification 199
retention types 5
returning volumes to scratch status 275
scratch volume 9
segregating by media shape 110
undefined serial numbers 73
updating expiration date 137
updating status 100
user status 9
using manual move control 113
validating mounts 17
VM tapes, managing 339
volume access 168
with duplicate volume serial numbers 74
with permanent errors 275
with special expiration date 45
VOLUME, EDGRMMxx operand 122
volume DFSMSrmm ISPF dialog panel defaults 333
volume-not-in-library processing 81
volume serial number
changing duplicates 74
external 1
ignoring duplicates 75, 197
rules for matching shelf location 61
VRSBYJOBNAME
description 5
VRSCHANGE, EDGRMMxx operand 142
VRSEL, EDGRMMxx operand 143
VRSEL parameter 253, 261
VRSJOBNAME, EDGRMMxx operand 142
VRSMIN, EDGRMMxx operand 143

W

waiting requests, number of 48
warning mode
running during implementation 51
specifying 133
weekly archive from daily audit reports 385
WHILECATALOG
catalog date format, WHILECATLG 266
writing
EBCDIC labels 326
ISO/ANSI labels 326
wrong label processing 317

Readers' Comments — We'd Like to Hear from You

z/OS
DFSMSrmm Implementation
and Customization Guide
Release 1

Publication No. SC26-7405-00

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	☐	☐	☐	☐	☐

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	☐	☐	☐	☐	☐
Complete	☐	☐	☐	☐	☐
Easy to find	☐	☐	☐	☐	☐
Easy to understand	☐	☐	☐	☐	☐
Well organized	☐	☐	☐	☐	☐
Applicable to your tasks	☐	☐	☐	☐	☐

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? ☐ Yes ☐ No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name _____ Address _____

Company or Organization _____

Phone No. _____

Readers' Comments — We'd Like to Hear from You
SC26-7405-00

Cut or Fold
Along Line

Fold and Tape **Please do not staple** Fold and Tape

NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
RCF Processing Department
M86/050
5600 Cottle Road
SAN JOSE, CAU.S.A 95193-0001

Fold and Tape **Please do not staple** Fold and Tape

Cut or Fold
Along Line

Program Number: 5694-A01

Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC26-7405-00

Spine information:

z/OS

z/OS V1R1.0 DFSMSrmm Implementation and Customization Guide

Release 1